



---

## System Administration Guide, Volume I

---

Sun Microsystems, Inc.  
901 San Antonio Road  
Palo Alto, CA 94043  
U.S.A.

Part No: 805-3727-10  
October 1998

Copyright 1998 Sun Microsystems, Inc. 901 San Antonio Road, Palo Alto, California 94303-4900 U.S.A. All rights reserved.

This product or document is protected by copyright and distributed under licenses restricting its use, copying, distribution, and decompilation. No part of this product or document may be reproduced in any form by any means without prior written authorization of Sun and its licensors, if any. Third-party software, including font technology, is copyrighted and licensed from Sun suppliers.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, SunSoft, SunDocs, SunExpress, Solstice, Solstice AdminSuite, Solstice DiskSuite, Solaris Solve, Java, JavaStation, DeskSet, OpenWindows and Solaris are trademarks, registered trademarks, or service marks of Sun Microsystems, Inc. in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon an architecture developed by Sun Microsystems, Inc. DLT is claimed as a trademark of Quantum Corporation in the United States and other countries.

The OPEN LOOK and Sun™ Graphical User Interface was developed by Sun Microsystems, Inc. for its users and licensees. Sun acknowledges the pioneering efforts of Xerox in researching and developing the concept of visual or graphical user interfaces for the computer industry. Sun holds a non-exclusive license from Xerox to the Xerox Graphical User Interface, which license also covers Sun's licensees who implement OPEN LOOK GUIs and otherwise comply with Sun's written license agreements.

**RESTRICTED RIGHTS:** Use, duplication, or disclosure by the U.S. Government is subject to restrictions of FAR 52.227-14(g)(2)(6/87) and FAR 52.227-19(6/87), or DFAR 252.227-7015(b)(6/95) and DFAR 227.7202-3(a).

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

---

Copyright 1998 Sun Microsystems, Inc. 901 San Antonio Road, Palo Alto, Californie 94303-4900 Etats-Unis. Tous droits réservés.

Ce produit ou document est protégé par un copyright et distribué avec des licences qui en restreignent l'utilisation, la copie, la distribution, et la décompilation. Aucune partie de ce produit ou document ne peut être reproduite sous aucune forme, par quelque moyen que ce soit, sans l'autorisation préalable et écrite de Sun et de ses bailleurs de licence, s'il y en a. Le logiciel détenu par des tiers, et qui comprend la technologie relative aux polices de caractères, est protégé par un copyright et licencié par des fournisseurs de Sun.

Des parties de ce produit pourront être dérivées du système Berkeley BSD licenciés par l'Université de Californie. UNIX est une marque déposée aux Etats-Unis et dans d'autres pays et licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, le logo Sun, SunSoft, SunDocs, SunExpress, Solstice, Solstice AdminSuite, Solstice DiskSuite, Solaris Solve, Java, JavaStation, DeskSet, OpenWindows et Solaris sont des marques de fabrique ou des marques déposées, ou marques de service, de Sun Microsystems, Inc. aux Etats-Unis et dans d'autres pays. Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux Etats-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems, Inc. Quantum Corporation réclame DLT comme sa marque de fabrique aux Etats-Unis et dans d'autres pays.

L'interface d'utilisation graphique OPEN LOOK et Sun™ a été développée par Sun Microsystems, Inc. pour ses utilisateurs et licenciés. Sun reconnaît les efforts de pionniers de Xerox pour la recherche et le développement du concept des interfaces d'utilisation visuelle ou graphique pour l'industrie de l'informatique. Sun détient une licence non exclusive de Xerox sur l'interface d'utilisation graphique Xerox, cette licence couvrant également les licenciés de Sun qui mettent en place l'interface d'utilisation graphique OPEN LOOK et qui en outre se conforment aux licences écrites de Sun.

CETTE PUBLICATION EST FOURNIE "EN L'ETAT" ET AUCUNE GARANTIE, EXPRESSE OU IMPLICITE, N'EST ACCORDEE, Y COMPRIS DES GARANTIES CONCERNANT LA VALEUR MARCHANDE, L'APTITUDE DE LA PUBLICATION A REpondre A UNE UTILISATION PARTICULIERE, OU LE FAIT QU'ELLE NE SOIT PAS CONTREFAISANTE DE PRODUIT DE TIERS. CE DENI DE GARANTIE NE S'APPLIQUERAIT PAS, DANS LA MESURE OU IL SERAIT TENU JURIDIQUEMENT NUL ET NON AVENU.



# Contents

---

**About This Book   xxix**

**Part I   Managing User Accounts and Groups**

**1.   Managing User Accounts and Groups (Overview)   3**

What Are User Accounts and Groups?   3

Guidelines for Managing User Accounts   4

    Name Services   4

    User (Login) Names   4

    User ID Numbers   5

    Passwords   8

    Password Aging   9

    Home Directories   9

    The User's Work Environment   10

Guidelines for Managing Groups   10

Tools for Managing User Accounts and Groups   11

What You Can Do With Admintool   14

    Modify User Accounts   14

    Delete User Accounts   15

    Add Customized User Initialization Files   15

    Administer Passwords   15

	Disable User Accounts	16
	Where User Account and Group Information Is Stored	16
	Fields in the <code>passwd</code> File	16
	Fields in the Shadow File	17
	Fields in the Group File	18
	Customizing a User's Work Environment	20
	Use Site Initialization Files	21
	Avoid Local System References	21
	Shell Features	22
	Shell Environment	23
	The <code>PATH</code> Variable	26
	The Locale Variables	27
	Default File Permissions ( <code>umask</code> )	28
	Examples of User and Site Initialization Files	29
	Example—Site Initialization File	30
<b>2.</b>	<b>Setting Up and Maintaining User Accounts and Groups (Tasks)</b>	<b>33</b>
	Becoming Superuser ( <code>root</code> )	34
	▼ How to Become Superuser ( <code>root</code> )	34
	Setting Up User Accounts Task Map	34
	User Information Data Sheet	35
	▼ How to Customize User Initialization Files	36
	▼ How to Start Admintool	37
	▼ How to Add a Group	38
	▼ How to Add a New User Account	39
	▼ How to Share a User's Home Directory	41
	▼ How to Mount a User's Home Directory	43
	Maintaining User Accounts Task Map	44
	▼ How to Modify a Group	45

- ▼ How to Delete a Group 46
- ▼ How to Modify a User Account 46
- ▼ How to Disable a User Account 48
- ▼ How to Change a User's Password 49
- ▼ How to Change Password Aging for a User Account 50
- ▼ How to Delete a User Account 51

Solaris User Registration 52

    Accessing Solaris<sup>SM</sup> Solve<sup>SM</sup> 52

    Troubleshooting Solaris User Registration Problems 53

- ▼ How to Restart Solaris User Registration 54
- ▼ How To Disable User Registration 55

## **Part II Managing Server and Client Support**

### **3. Managing Server and Client Support (Overview) 59**

Where to Find Server and Client Tasks 60

What Are Servers and Clients? 60

What Does Support Mean? 60

Overview of System Types 61

    Servers 62

    Standalone Systems 62

    Diskless Clients 62

    JavaStation Client 63

    AutoClient Systems 63

Guidelines for Choosing System Types 63

Tools for Managing Server and Client Support 64

What You Can Do With Host Manager 65

    Add and Maintain Support 65

    Update System Types 66

    Convert System Types 67

	Add OS Services	67
	Set Up Remote Installation Services	68
	Queue Tasks	69
	Set Root Passwords	69
	Enable Scripts	69
	Add a Multihomed Host	70
	What You Can't Do With Host Manager	70
	Running Host Manager as Superuser	71
<b>4.</b>	<b>Managing Server and Client Support (Tasks)</b>	<b>73</b>
	Adding Server and Client Support Task Map	74
	▼ How to Start Solstice Host Manager	75
	▼ How to Update System Types	76
	▼ How to Set Defaults for Adding Support	77
	▼ How to Add Support for a Standalone System or OS Server	77
	▼ How to Convert a System to an OS Server	80
	▼ How to Add SunOS 4.0 and Compatible OS Services to an OS Server	82
	▼ How to Add Solaris 7 OS Services to an OS Server	86
	▼ How to Add Support for an AutoClient System	88
	▼ How to Add Support for a Diskless Client	90
	Maintaining Server and Client Support Task Map	93
	▼ How to Modify Support for a System	94
	▼ How to Delete Support for a System	94
	Using the Host Manager Command-Line Interface to Automate Setup Tasks	95
	<b>Part III Shutting Down and Booting a System</b>	
<b>5.</b>	<b>Shutting Down and Booting a System (Overview)</b>	<b>99</b>
	What's New in Shutting Down and Booting a System?	99
	Bringing a System to Run Level S (Single-User Mode)	100

	Booting a System Running the 32-bit or 64-bit Solaris 7 Operating Environment	100
	Where to Find Shutting Down and Booting Tasks	100
	Terminology	100
	Guidelines for Shutting Down a System	101
	Guidelines for Booting a System	101
	Performing a Reconfiguration Boot	102
	When to Shut Down a System	102
	When to Boot a System	104
<b>6.</b>	<b>Run Levels and Boot Files (Tasks)</b>	<b>107</b>
	Run Levels	107
	▼ How to Determine a System's Run Level	108
	The <code>/etc/inittab</code> File	109
	Example—Default <code>inittab</code> File	110
	What Happens When the System Is Brought to Run Level 3	111
	Run Control Scripts	112
	Using a Run Control Script to Stop or Start Services	113
	▼ How to Use a Run Control Script to Stop or Start a Service	113
	Adding a Run Control Script	114
	▼ How to Add a Run Control Script	114
	Disabling a Run Control Script	115
	▼ How to Disable a Run Control Script	115
	Run Control Script Summaries	116
<b>7.</b>	<b>Shutting Down a System (Tasks)</b>	<b>119</b>
	When to Shut Down the System	119
	How to Shut Down a System	120
	When to Turn Off Power to Devices	121
	Notifying Users of System Down Time	121

- ▼ How to Determine Who Is Logged in to a System 121
- ▼ How to Shut Down a Server 122
- ▼ How to Shut Down a Standalone System 125
- ▼ How to Turn Off Power to All Devices 127

## 8. **Booting a SPARC System (Tasks) 129**

SPARC: Using the Boot PROM 129

- ▼ How to Switch to the ok Prompt 130
- ▼ How to Find the PROM Release for a System 130
- ▼ How to Change the Default Boot Device 130
- ▼ How to Reset the System 132

Booting a SPARC System 132

- ▼ How to Boot a System to Run Level 3 (Multiuser State) 134
- ▼ How to Boot a System to Run Level S (Single-User State) 135
- ▼ SPARC: How to Boot a System Interactively 136
- ▼ How to Boot a System for Recovery Purposes 138
- ▼ How to Stop the System for Recovery Purposes 140
  - SPARC: Forcing a Crash Dump and Rebooting the System 141
- ▼ How to Force a Crash Dump and Reboot the System 141
- ▼ How to Boot the System Using the Kernel Debugger (kadb) 142

## 9. **x86: Booting a System (Tasks) 145**

Booting an x86 System 145

- ▼ How to Boot a System to Run Level 3 (Multiuser State) 146
- ▼ How to Boot a System to Run Level S (Single-User State) 147
- ▼ How to Boot a System Interactively 149
- ▼ How to Boot a System for Recovery Purposes 151
- ▼ How to Stop the System for Recovery Purposes 154
  - x86: Forcing a Crash Dump and Rebooting the System 155
- ▼ How to Force a Crash Dump and Reboot the System 155



<b>10.</b>	<b>The Boot Process (Reference)</b>	<b>157</b>
	SPARC: The Boot PROM	157
	SPARC: The Boot Process	158
	SPARC: The Boot Process Details	158
	x86: The PC BIOS	159
	x86: Boot Subsystems	160
	x86: Booting Solaris	161
	x86: Menus Displayed During the Device Identification Phase	161
	x86: Menus Displayed During the Boot Phase	164
	x86: The Boot Process	165
	x86: The Boot Process Details	166
	<b>Part IV Managing Removable Media</b>	
<b>11.</b>	<b>Guidelines for Using CDs and Diskettes (Overview)</b>	<b>171</b>
	Where to Find Managing Removable Media Tasks	171
	Features and Benefits	172
	Comparison of Automatic and Manual Mounting	172
	What You Can Do With Diskettes and CDs	173
<b>12.</b>	<b>Using CDs From the Command Line (Tasks)</b>	<b>175</b>
	Using CDs Task Map	175
	Using CD Names	176
	▼ How to Load a CD	177
	▼ How to Examine the Contents of a CD	177
	▼ How to Copy Information From a CD	177
	▼ How to Find Out If a CD Is Still in Use	178
	▼ How to Eject a CD	179
	▼ How to Access CDs on Other Systems	180
	▼ How to Make Local CDs Available to Other Systems	181
	▼ How to Configure a System to Play Musical CDs	184

- ▼ How to Prepare a System for a New CD-ROM Drive 185
- Configuring Volume Management 186
- ▼ How to Stop Volume Management 186
- ▼ How to Restart Volume Management 186
- 13. Formatting and Using Diskettes From the Command Line (Tasks) 189**
  - Formatting Diskettes Task Map 189
    - Using Diskette Names 190
    - Hardware Considerations 191
  - ▼ How to Format a UFS Diskette 193
  - ▼ How to Place a UFS File System on a Diskette 196
  - ▼ How to Format a DOS Diskette 197
  - Using Diskettes Task Map 200
  - ▼ How to Load a Diskette 200
  - ▼ How to Examine the Contents of a Diskette 202
  - ▼ How to Copy or Move Information From a Diskette 202
  - ▼ How to Copy or Move Information to a Diskette 204
  - ▼ How to Find Out If a Diskette Is Still in Use 205
  - ▼ How to Eject a Diskette 206
  - ▼ How to Access Diskettes on Other Systems 206
  - ▼ How to Make Local Diskettes Available to Other Systems 208
- 14. Using PCMCIA Memory Cards From the Command Line (Tasks) 213**
  - Formatting PCMCIA Memory Cards Task Map 213
    - Using PCMCIA Memory Cards Names 214
    - Hardware Considerations 215
  - ▼ How to Format a UFS PCMCIA Memory Card 215
  - ▼ How to Place a UFS File System on a PCMCIA Memory Card 218
  - ▼ How to Format a DOS PCMCIA Memory Card 220
  - Using PCMCIA Memory Cards Task Map 222

▼	How to Load a PCMCIA Memory Card	223
▼	How to Examine the Contents of a PCMCIA Memory Card	225
▼	How to Copy or Move Information From a PCMCIA Memory Card	225
▼	How to Copy or Move Information to a PCMCIA Memory Card	226
▼	How to Find Out If a PCMCIA Memory Card Is Still In Use	228
▼	How to Eject a PCMCIA Memory Card	228
▼	How to Access PCMCIA Memory Cards on Other Systems	229
▼	How to Make Local PCMCIA Memory Cards Available to Other Systems	231
<b>15.</b>	<b>How Volume Management Works (Reference)</b>	<b>235</b>
	Volume Management Mounts All Removable Media	235
	Volume Management Provides Access to Diskettes	236
	Volume Management Provides Access to CDs	237
	Volume Management Supplies Convenient Mount Points for Easier Access	238
	Volume Management Creates Two Sets of Symbolic Links	240
	Symbolic Links for File System Access	240
	Symbolic Links for Raw Device Access	240
	Volume Management Can Be Limited by UFS Formats	241
	What About Mixed Formats?	242
	<b>Part V Managing Software</b>	
<b>16.</b>	<b>Software Administration (Overview)</b>	<b>247</b>
	Where to Find Software Administration Tasks	247
	Software Packages	248
	Tools for Managing Software	248
	What Happens When You Add or Remove a Package	249
	What You Should Know Before Adding or Removing Packages	250
	Guidelines for Client Software Administration	250
	Installing Sun Packages on Servers and Clients	251
	Installing Third-Party Packages on Servers and Clients	252

	Installing Packages in Heterogeneous Environments	252
	Guidelines for Removing Packages	252
	Avoiding User Interaction When Adding Packages	253
	Using an Administration File	253
	Using a Response File	254
<b>17.</b>	<b>Software Administration (Tasks)</b>	<b>255</b>
	Commands for Handling Software Packages	256
	Known Problem With Adding and Removing Packages	256
	Adding Packages	257
	▼ How to Add Packages to a Standalone System	257
	Using a Spool Directory	259
	▼ How to Add a Package to a Spool Directory	259
	Adding Packages in a Homogeneous Client/Server Environment	261
	Adding Sun Packages on Clients	262
	Adding Third-Party Packages on Clients	263
	Adding Packages in a Heterogeneous Client/Server Environment	263
	▼ How to Determine Where a Package's Files Will Be Installed	264
	▼ How to Add a Package to a Diskless or AutoClient System's root (/) File System	265
	▼ How to Add Packages to a Server	267
	Checking the Installation of Packages	270
	▼ How to List Information About All Installed Packages	270
	▼ How to Check the Integrity of an Installed Package	271
	▼ How to Display Detailed Information About a Package	273
	Removing Packages From Servers and Standalone Systems	274
	▼ How to Remove a Package	274
	▼ How to Remove a Spooled Package	274
	▼ How to Remove a Diskless or AutoClient System's Package	275

	Adding and Removing Packages Using Admintool	276
	▼ How to Add Packages With Admintool	276
	▼ How to Remove Packages With Admintool	278
<b>18.</b>	<b>Patch Administration (Overview)</b>	<b>281</b>
	What Is a Patch	281
	Tools For Managing Patches	282
	Patch Distribution	282
	What You Need to Access Sun Patches	283
	Patch Access Via the World Wide Web	283
	Patch Access Via ftp	284
	Patch Numbering	284
	What Happens When You Install a Patch	284
	What Happens When You Remove a Patch	285
	<b>Part VI Managing Devices</b>	
<b>19.</b>	<b>Device Management (Overview/Tasks)</b>	<b>289</b>
	What's New in Device Management?	289
	Dynamic Reconfiguration	290
	x86: SCSI Disk Driver (sd)	290
	Where to Find Device Management Tasks	290
	About Device Drivers	291
	Automatic Configuration of Devices	291
	Features and Benefits	292
	What You Need For Unsupported Devices	292
	Adding a Peripheral Device to a System	293
	▼ How to Add a Peripheral Device	293
	▼ How to Add a Device Driver	295
	Displaying Device Configuration Information	296
	driver not attached Message	296

	Identifying a System's Devices	297
▼	How to Display System Configuration Information	297
▼	How to Display Device Information	299
<b>20.</b>	<b>Accessing Devices (Overview)</b>	<b>301</b>
	Accessing Devices	301
	How Device Information Is Created	301
	Device Naming Conventions	302
	Logical Disk Device Names	302
	Specifying the Disk Subdirectory	303
	Specifying the Slice	304
	SPARC: Disks With Direct Controllers	304
	x86: Disks With Direct Controllers	305
	SPARC: Disks With Bus-Oriented Controllers	305
	x86: Disks With SCSI Controllers	306
	Logical Tape Device Names	306
	Logical CD-ROM Device Names	307
	<b>Part VII Managing Disks</b>	
<b>21.</b>	<b>Disk Management (Overview)</b>	<b>311</b>
	Where to Find Disk Management Tasks	311
	Introduction	312
	Disk Terminology	312
	About Disk Slices	312
	SPARC: Disk Slices	313
	x86: Disk Slices	314
	Using Raw Data Slices	316
	Slice Arrangements on Multiple Disks	316
	Determining Which Slices to Use	317
	The <code>format</code> Utility	318

	Definition	318
	Features and Benefits	318
	When to Use the <code>format</code> Utility	319
	Guidelines for Using the <code>format</code> Utility	320
	Formatting a Disk	321
	About Disk Labels	322
	Partition Table	322
	Dividing a Disk Into Slices	325
	Using the Free Hog Slice	325
<b>22.</b>	<b>Administering Disks (Tasks)</b>	<b>327</b>
	Administering Disks Task Map	327
	Identifying Disks on a System	329
	▼ How to Identify the Disks on a System	329
	Formatting a Disk	331
	▼ How to Determine If a Disk is Formatted	331
	▼ How to Format a Disk	332
	Displaying Disk Slices	334
	▼ How to Display Disk Slice Information	334
	Creating and Examining a Disk Label	336
	▼ How to Label a Disk	336
	▼ How to Examine a Disk Label	338
	Recovering a Corrupted Disk Label	339
	▼ How to Recover a Corrupted Disk Label	339
	Adding a Third-Party Disk	342
	Creating a <code>format.dat</code> Entry	343
	▼ How to Create a <code>format.dat</code> Entry	343
	Automatically Configuring SCSI Disk Drives	344
	▼ How to Automatically Configure a SCSI Drive	345

Repairing a Defective Sector 347

▼ How to Identify a Defective Sector by Using Surface Analysis 347

▼ How to Repair a Defective Sector 349

Tips and Tricks 350

Debugging `format` Sessions 350

Label Multiple Disks by Using the `prtvtoc` and `fmthard` Commands 350

**23. SPARC: Adding a Disk (Tasks) 353**

SPARC: About System and Secondary Disks 353

SPARC: Adding a System or Secondary Disk Task Map 354

▼ How to Connect a System Disk and Boot 354

▼ How to Connect a Secondary Disk and Boot 355

▼ How to Create Disk Slices and Label a Disk 356

▼ How to Create File Systems 361

▼ How to Install a Boot Block on a System Disk 362

**24. x86: Adding a Disk (Tasks) 365**

x86: About System and Secondary Disks 365

x86: Adding a System or Secondary Disk Task Map 366

x86: Guidelines for Creating an `fdisk` Partition 366

▼ How to Connect a System Disk and Boot 367

▼ How to Connect a Secondary Disk and Boot 368

▼ How to Create a Solaris `fdisk` Partition 369

▼ How to Create Disk Slices and Label a Disk 376

▼ How to Create File Systems 379

▼ How to Install a Boot Block on a System Disk 380

**25. The `format` Utility (Reference) 381**

Requirements or Restrictions for Using the `format` Utility 381

Recommendations for Preserving Information When Using `format` 382



Format Menu and Command Descriptions	382
The partition Menu	384
x86: The fdisk Menu	385
The analyze Menu	386
The defect Menu	388
Files Used by <code>format—format.dat</code>	389
Structure	390
Syntax	390
Keywords	390
Slice Tables	393
Location	394
Rules for Input to <code>format</code> Commands	394
Numbers	394
Block Numbers	394
Command Names	395
Other Names	396
Help	396
Associated Man Pages	396
<b>Part VIII Managing File Systems</b>	
<b>26. File Systems (Overview)</b>	<b>399</b>
What's New in File Systems?	399
Introduction	400
Types of File Systems	401
Disk-based File Systems	401
Network-based File Systems	402
Virtual File Systems	402
File System Administration Commands	404
How the File System Commands Determine the File System Type	405

	Manual Pages for Generic and Specific Commands	406
	The Default Solaris File Systems	406
	Swap Space	407
	The UFS File System	407
	Parts of a UFS File System	408
	UFS Logging	408
	Planning UFS File Systems	409
	Mounting and Unmounting File Systems	410
	The Mounted File System Table	411
	The Virtual File System Table	412
	The Network File System (NFS)	413
	AutoFS	413
	The Cache File System (CacheFS)	414
	Deciding How to Mount File Systems	414
	Determining a File System's Type	415
	▼ How to Determine a File System's Type	415
<b>27.</b>	<b>Creating File Systems (Tasks)</b>	<b>417</b>
	Creating a UFS File System	417
	File System Parameters	418
	▼ How to Create a UFS File System	418
	Creating a Temporary File System (TMPFS)	420
	▼ How to Create a TMPFS File System	420
	Creating a Loopback File System (LOFS)	422
	▼ How to Create a LOFS File System	422
<b>28.</b>	<b>Mounting and Unmounting File Systems (Tasks)</b>	<b>425</b>
	Mounting File Systems	425
	Commands Used to Mount and Unmount File Systems	426
	Commonly Used Mount Options	427

▼	How to Determine Which File Systems Are Mounted	429
	Mounting File Systems Using the <code>/etc/vfstab</code> File	430
	<code>/etc/vfstab</code> Field Descriptions	430
▼	How to Add an Entry to the <code>/etc/vfstab</code> File	431
▼	How to Mount Multiple File Systems Listed in the <code>/etc/vfstab</code> File	433
▼	How to Mount a File System Listed in the <code>/etc/vfstab</code> File	434
	Mounting File Systems Using the <code>mount</code> Command	435
▼	How to Mount a UFS File System	435
▼	How to Remount a UFS File System Without Large Files	436
▼	How to Mount an NFS File System	437
▼	How to Mount a System V (S5FS) File System	438
▼	How to Mount a PCFS (DOS) File System From a Hard Disk	438
	Unmounting File Systems	439
	Prerequisites	440
	Verifying an Unmounted File System	440
▼	How to Stop All Processes for a File System	440
▼	How to Unmount a File System	441
▼	How to Unmount File Systems Listed in the <code>/etc/vfstab</code> File	442
<b>29.</b>	<b>The Cache File System (Tasks)</b>	<b>445</b>
	How CacheFS Works	446
	Setting Up a Cached File System Task Map	447
	Creating a Cache	448
▼	How to Create a Cache	448
	Specifying a File System to Be Mounted in the Cache	449
▼	How to Specify a File System to Be Mounted in a Cache With <code>mount</code>	449
▼	How to Mount a File System in a Cache by Editing the <code>/etc/vfstab</code> File	452
▼	How to Mount a File System in a Cache With AutoFS	453
	Maintaining a Cached File System Task Map	454

## Maintaining the Cache 454

- ▼ How to Modify File Systems in a Cache 455
- ▼ How to Display Information About Cached File Systems 456
- ▼ How to Specify Consistency Checking on Demand 457
- ▼ How to Delete a Cached File System 457
- ▼ How to Check the Integrity of Cached File Systems 459

## Managing Your Cache File Systems With `cachefspack` 460

- ▼ How to Pack Files in the Cache 460

## Packing Lists 461

- ▼ How to Create a Packing List 461
- ▼ How to Pack Files in the Cache as Specified in a Packing List 462
- ▼ How to Specify Files in the Packing List to be Treated as Regular Expressions 462
- ▼ How to Pack Files From a Shared Directory 463

## Unpacking Files 464

- ▼ How to Unpack Files or Packing Lists From the Cache 464

## Displaying Packed Files Information 466

- ▼ How to Display Packed Files Information 466

## Viewing Help on the `cachefspack` Command 467

## `cachefspack` Errors 468

## CacheFS Statistics 472

## Prerequisites for Setting Up and Viewing the CacheFS Statistics 473

## Setting Up CacheFS Statistics Task Map 474

## CacheFS Logging 474

- ▼ How to Set Up the Logging Process 474
  - How to Locate the Log File 475
  - How to Stop the Logging Process 476

## Viewing the Cache Size 476

▼	How to View the Working Set (Cache) Size	476
	Viewing the Statistics	477
▼	How to View Cache Statistics	478
	The Cache Structure and Behavior	479
	Consistency Checking of Cached File Systems With the Back File System	480
	Consistency Checking on Demand	480
<b>30.</b>	<b>Configuring Additional Swap Space (Tasks)</b>	<b>481</b>
	About Swap Space	481
	Swap Space and Virtual Memory	482
	Swap Space and the TMPFS File System	483
	How Do I Know If I Need More Swap Space?	483
	Swap-Related Error Messages	483
	TMPFS-Related Error Messages	484
	How Swap Space Is Allocated	484
	The <code>/etc/vfstab</code> File	485
	Planning for Swap Space	485
	Monitoring Swap Resources	486
	Adding More Swap Space	487
	Creating a Swap File	487
▼	How to Create a Swap File and Make It Available	488
	Removing a Swap File From Use	489
▼	How to Remove Extra Swap Space	489
<b>31.</b>	<b>Checking File System Integrity</b>	<b>491</b>
	Understanding How the File System State Is Recorded	492
	What <code>fsck</code> Checks and Tries to Repair	494
	Why Inconsistencies May Occur	494
	The UFS Components That Are Checked for Consistency	495
	Modifying Automatic Boot Checking	500

	The <code>/etc/vfstab</code> File	500
▼	How to Modify Automatic Checking Done During Booting	501
	Interactively Checking and Repairing a UFS File System	502
▼	How to See If a File System Needs Checking	502
▼	How to Check File Systems Interactively	502
	Preening UFS File Systems	504
▼	How to Preen a File System	504
	Restoring a Bad Superblock	505
▼	How to Restore a Bad Superblock	505
	How to Fix a UFS File System <code>fsck</code> Cannot Repair	506
	Syntax and Options for the <code>fsck</code> Command	507
	Generic <code>fsck</code> Command Syntax, Options, and Arguments	507
<b>32.</b>	<b>File System Reference</b>	<b>511</b>
	Default Directories for root ( <code>/</code> ) and <code>/usr</code> File Systems	511
	The Platform-Dependent Directories	518
	The Structure of UFS File System Cylinder Groups	519
	The Boot Block	519
	The Superblock	519
	Inodes	520
	Data Blocks	521
	Free Blocks	521
	Deciding on Custom File System Parameters	522
	Logical Block Size	522
	Fragment Size	523
	Minimum Free Space	524
	Rotational Delay (Gap)	524
	Optimization Type	525
	Number of Files	525

Commands for Creating a Customized File System	525
The <code>newfs</code> Command Syntax, Options, and Arguments	526
The Generic <code>mkfs</code> Command	528

## **Part IX Backing Up and Restoring Data**

<b>33. Backing Up and Restoring File Systems (Overview)</b>	<b>533</b>
Where to Find Backup and Restore Tasks	533
Definition: Backing Up and Restoring File Systems	534
Why You Should Back Up File Systems	535
Choosing a Tape Device	535
Planning Which File Systems to Back Up	536
Overview of the Backup and Restore Commands	538
Choosing the Type of Backup	539
Guidelines For Scheduling Backups	540
What Drives a Backup Schedule	540
How Often Should You Do Backups?	541
Using Dump Levels to Create Incremental Backups	541
Sample Backup Schedules	542
Example—Daily Cumulative, Weekly Cumulative Backups	542
Example—Daily Cumulative, Weekly Incremental Backups	544
Example—Daily Incremental, Weekly Cumulative Backups	545
Example—Backup Schedule for a Server	546
Other Backup Scheduling Suggestions	548
<b>34. Backing Up Files and File Systems (Tasks)</b>	<b>551</b>
Preparing to Do Backups	551
▼ How to Find File System Names	552
▼ How to Determine the Number of Tapes for a Full Backup	552
Doing Backups	553
▼ How to Do Backups to Tape	554

<b>35.</b>	<b>Restoring Files and File Systems (Tasks)</b>	<b>561</b>
	Preparing to Restore Files and File Systems	561
	Determining the Disk Device Name	562
	Determining the Type of Tape Drive You Will Use	562
	Determining the Tape Device Name	562
	Restoring Complete File Systems	562
	Restoring Individual Files and Directories	563
	Restoring Files and File Systems	563
	▼ How to Determine Which Tapes to Use	563
	▼ How to Restore Files Interactively	565
	▼ How to Restore Specific Files Non-Interactively	567
	▼ How to Restore Files Using a Remote Tape Drive	569
	▼ How to Restore a Complete File System	570
	▼ How to Restore the root (/) and /usr File Systems	573
<b>36.</b>	<b>The <code>ufsdump</code> and <code>ufsrestore</code> Commands (Reference)</b>	<b>577</b>
	How <code>ufsdump</code> Works	577
	Determining Device Characteristics	577
	Detecting the End of Media	578
	Copying Data	578
	The Role of the <code>/etc/dumpdates</code> File	578
	Backup Device ( <i>dump-file</i> ) Argument	579
	Specifying Files to Back Up	580
	End-of-Media Detection	581
	Specifying Tape Characteristics	581
	Limitations of the <code>ufsdump</code> Command	581
	Options and Arguments for the <code>ufsdump</code> Command	582
	Default Command Options	582
	Options for the <code>ufsdump</code> Command	583



	The <code>ufsdump</code> Command and Security Issues	585
	Options and Arguments for the <code>ufsrestore</code> Command	585
	Command Syntax	585
	Options and Arguments	586
	Commands for Interactive Restore	588
<b>37.</b>	<b>Copying UFS Files and File Systems (Tasks)</b>	<b>591</b>
	Commands for Copying File Systems	592
	Copying File Systems Between Disks	593
	Making a Literal File System Copy	593
	▼ How to Clone a Disk ( <code>dd</code> )	594
	Copying Directories Between File Systems using the <code>cpio</code> Command	597
	▼ How to Copy Directories Between File Systems ( <code>cpio</code> )	597
	Copying Files and File Systems to Tape	599
	Copying Files to Tape With <code>tar</code>	601
	▼ How to Copy Files to a Tape ( <code>tar</code> )	601
	▼ How to List the Files on a Tape ( <code>tar</code> )	602
	▼ How to Retrieve Files From a Tape ( <code>tar</code> )	603
	Copying Files to a Tape With <code>pax</code>	604
	▼ How to Copy Files to a Tape ( <code>pax</code> )	604
	▼ How to Copy All Files in a Directory to a Tape ( <code>cpio</code> )	605
	▼ How to List the Files on a Tape ( <code>cpio</code> )	606
	▼ How to Retrieve All Files From a Tape ( <code>cpio</code> )	607
	▼ How to Retrieve Specific Files From a Tape ( <code>cpio</code> )	608
	▼ How to Copy Files to a Remote Tape Drive ( <code>tar</code> and <code>dd</code> )	609
	▼ How to Extract Files From a Remote Tape Drive	610
	Copying Files and File Systems to Diskette	611
	Things You Should Know When Copying Files to Diskettes	612
	▼ How to Copy Files to a Single Formatted Diskette ( <code>tar</code> )	612

- ▼ How to List the Files on a Diskette (`tar`) 613
- ▼ How to Retrieve Files From a Diskette (`tar`) 614
- ▼ How to Archive Files to Multiple Diskettes 615
- Copying Files With a Different Header Format 615
- ▼ How to Create an Archive for Older SunOS Releases 615
  - Retrieving Files Created With the `bar` Command 616
- ▼ How to Retrieve `bar` Files From a Diskette 616
- 38. Managing Tape Drives (Tasks) 619**
  - Choosing Which Media to Use 619
  - Backup Device Names 620
    - Specifying the Default Density for a Tape Drive 621
    - Specifying Different Densities for a Tape Drive 622
  - Displaying Tape Drive Status 622
  - ▼ How to Display Tape Drive Status 622
  - Handling Magnetic Tape Cartridges 623
    - ▼ How to Retension a Magnetic Tape Cartridge 623
    - ▼ How to Rewind a Magnetic Tape Cartridge 624
  - Guidelines for Drive Maintenance and Media Handling 624
  - A. The 64-bit Solaris Operating Environment 627**
    - Overview of the 64-bit Solaris Operating Environment 627
      - Do I Need to Use the 64-bit Solaris Application Environment? 628
      - Do I Need to Use the 64-bit Solaris Operating Environment? 628
      - Which SPARC Systems Support 64-bit Application Development? 628
      - How Do I Install the 64-bit Solaris Operating Environment? 628
      - How Do I Know Whether a System Can Run the 64-bit Solaris Operating Environment? 629
    - ▼ How Do I Determine Whether a System Has 64-bit Solaris Capabilities Enabled? 630

How Do I Run Applications in the 64-bit Solaris Operating Environment? 631

Do I Boot Systems Running a 32-bit and 64-bit Solaris 7 Kernel the Same Way? 632

Troubleshooting 64-bit Solaris Boot Problems 633

64-bit Solaris Package Changes 633

Automatically Mounting 32-bit or 64-bit Applications 634

**Index 635**



# About This Book

---

*System Administration Guide, Volume I* is part of a two-volume set that covers a significant part of the Solaris™ system administration information. It includes both SPARC™ and x86 information and describes how to use the Solstice™ AdminSuite™ tools to perform some of the system administration tasks.

This book assumes that you have already installed the SunOS 5.7™ operating system and Solstice AdminSuite, and you have set up any networking software that you plan to use. The SunOS 5.7 operating system is part of the Solaris 7 product family, which also includes many utilities and OpenWindows™ Version 3. The SunOS 5.7 operating system is compliant with AT&T's System V, Release 4 operating system.

For the Solaris 7 release, new features interesting to system administrators are covered in sections called *What's New in ... ?* in the appropriate chapters.

---

**Note** - The term "x86" refers to the Intel 8086 family of microprocessor chips, including the Pentium and Pentium Pro processors and compatible microprocessor chips made by AMD and Cynix. In this document the term "x86" refers to the overall platform architecture, whereas "*Intel Platform Edition*" appears in the product name.

---

The following table describes the system administration topics found in *System Administration Guide, Volume I* and *System Administration Guide, Volume II*.

System Administration Guide, Volume I	System Administration Guide, Volume II
Chapter 1	"Print Management (Overview)" in <i>System Administration Guide, Volume II</i>
Chapter 3	"Working With Remote Systems (Tasks)" in <i>System Administration Guide, Volume II</i>

System Administration Guide, Volume I	System Administration Guide, Volume II
Chapter 5	“Managing Terminals and Modems (Overview)” in <i>System Administration Guide, Volume II</i>
Chapter 11	“Managing System Security (Overview)” in <i>System Administration Guide, Volume II</i>
Chapter 16	“Managing System Resources (Overview)” in <i>System Administration Guide, Volume II</i>
Chapter 19	“System Performance (Overview)” in <i>System Administration Guide, Volume II</i>
Chapter 21	“Troubleshooting Software Problems (Overview)” in <i>System Administration Guide, Volume II</i>
Chapter 26	
Chapter 33	
Appendix A	

## Who Should Use This Book

This book is intended for anyone responsible for administering one or more systems running the Solaris 7 release. To use this book, you should have 1-2 years of UNIX<sup>®</sup> system administration experience and preferably a Computer Science B.S. degree or equivalent knowledge.

---

## How This Book Is Organized

This book is split into parts that each cover a major system administration topic. Each part contains chapters that provide both overview and task information.

Most of the overview information about a topic is usually described in the beginning chapters of each part, and the other chapters provide step-by-step instructions on system administration tasks that you need to perform. Each set of steps is usually followed by a way to verify that the task was successfully performed and an example of how to perform the task.

---

## Using AnswerBook2™ to Read This Book

You can click on any cross reference, represented by underlined text, to quickly access referenced information in the AnswerBook2 collections. To return to the previous display, click on Back.

---

## Ordering Sun Documents

The SunDocs™ program provides more than 250 manuals from Sun Microsystems, Inc. If you live in the United States, Canada, Europe, or Japan, you can purchase documentation sets or individual manuals using this program.

For a list of documents and how to order them, see the catalog section of the SunExpress<sup>SM</sup> Internet site at [sunexpress](http://sunexpress).

---

## SPARC and x86 Information

This book provides system administration information for both SPARC and x86 systems. Unless otherwise noted, information throughout this book applies to both types of systems. Table P-1 summarizes the differences between the SPARC and x86 system administration tasks.

**TABLE P-1** SPARC and x86 System Administration Differences

Category	SPARC	x86
System operation before kernel is loaded	<ul style="list-style-type: none"> <li>■ A programmable read-only memory (PROM) chip with a monitor program runs diagnostics and displays device information.</li> <li>■ It is also used to program default boot parameters and test the devices connected to the system.</li> </ul>	<ul style="list-style-type: none"> <li>■ The basic input/output system (BIOS) runs diagnostics and displays device information.</li> </ul> <p>A Solaris Device Configuration Assistant boot diskette with the Multiple Device Boot (MDB) program is used to boot from non-default boot partitions, the network, or CD-ROM.</p>
Booting the system	<ul style="list-style-type: none"> <li>■ Commands and options at the PROM level are used to boot the system.</li> </ul>	<ul style="list-style-type: none"> <li>■ Commands and options at the MDB, primary, and secondary boot subsystems level are used to boot the system.</li> </ul>
Boot programs	<ul style="list-style-type: none"> <li>■ <code>bootblk</code>, the primary boot program, loads <code>ufsboot</code>.</li> <li>■ <code>ufsboot</code>, the secondary boot program loads the kernel.</li> </ul>	<ul style="list-style-type: none"> <li>■ <code>mboot</code>, the master boot record, loads <code>pboot</code>.</li> </ul> <p><code>pboot</code>, the Solaris partition boot program, loads <code>bootblk</code>.</p> <ul style="list-style-type: none"> <li>■ <code>bootblk</code>, the primary boot program, loads <code>ufsboot</code>.</li> </ul> <p><code>ufsboot</code>, the secondary boot program, loads the kernel.</p>
System shutdown	<ul style="list-style-type: none"> <li>■ The <code>shutdown</code> and <code>init</code> commands can be used without additional operation intervention.</li> </ul>	<ul style="list-style-type: none"> <li>■ The <code>shutdown</code> and <code>init</code> commands are used but require operator intervention at the <code>type</code> any key to continue prompt.</li> </ul>
Disk controllers	<ul style="list-style-type: none"> <li>■ SCSI</li> </ul>	<ul style="list-style-type: none"> <li>■ SCSI and IDE</li> </ul>
Disk slices and partitions	<ul style="list-style-type: none"> <li>■ A disk may have a maximum of eight slices, numbered 0-7.</li> <li>■ The Solaris <code>fdisk</code> partition may contain up to ten slices, numbered 0-9, but only 0-7 can be used to store user data.</li> </ul>	<ul style="list-style-type: none"> <li>■ A disk may have a maximum of four <code>fdisk</code> partitions.</li> <li>■ The Solaris <code>fdisk</code> partition may contain up to ten slices, numbered 0-9, but only 0-7 can be used to store user data.</li> </ul>
Diskette drives	<ul style="list-style-type: none"> <li>■ Desktop systems usually contain one 3.5-inch diskette drive.</li> </ul>	<ul style="list-style-type: none"> <li>■ Systems may contain two diskette drives: a 3.5-inch and a 5.25 inch drive.</li> </ul>



## What Typographic Changes Mean

The following table describes the typographic changes used in this book.

TABLE P-2 Typographic Conventions

Typeface or Symbol	Meaning	Example
<i>AaBbCc123</i>	The names of commands, files, and directories; on-screen computer output	Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. <code>machine_name%</code> You have mail.
<b>AaBbCc123</b>	What you type, contrasted with on-screen computer output	<code>machine_name%</code> <b>su</b> Password:
<i>AaBbCc123</i>	Command-line placeholder: replace with a real name or value	To delete a file, type <code>rm filename</code> .
<i>AaBbCc123</i>	Book titles, new words or terms, or words to be emphasized	Read Chapter 6 in <i>User's Guide</i> . These are called <i>class</i> options. You <i>must</i> be root to do this.

## Shell Prompts in Command Examples

The following table shows the default system prompt and superuser (root) prompt for the Bourne shell and Korn shell.

TABLE P-3 Shell Prompts

Shell	Prompt
Bourne shell and Korn shell prompt	\$
Bourne shell and Korn shell superuser prompt	#

## General Conventions

Be aware of the following conventions used in this book.

- When following steps or using examples, be sure to type double-quotes ("), left single-quotes ('), and right single-quotes (') exactly as shown.
- The key referred to as Return is labeled Enter on some keyboards.
- It is assumed that the root path includes the `/sbin`, `/usr/sbin`, `/usr/bin`, and `/etc` directories, so the steps in this book show the commands in these directories without absolute path names. Steps that use commands in other, less common, directories show the absolute path in the example.
- The examples in this book are for a basic SunOS 5.7 software installation without the Binary Compatibility Package installed and without `/usr/ucb` in the path.



**Caution** - If `/usr/ucb` is included in a search path, it should always be at the end of the search path. Commands like `ps` or `df` are duplicated in `/usr/ucb` with different formats and options from the SunOS 5.7 commands.

# PART I Managing User Accounts and Groups

---

This part provides instructions for managing users and groups. This part contains these chapters.

Chapter 1	Provides overview information about setting up user accounts and groups in a network environment.
Chapter 2	Provides step-by-step instructions for setting up user accounts and groups with Admintool.



## Managing User Accounts and Groups (Overview)

---

This chapter provides guidelines and planning information for managing user accounts and groups, and it provides overview information about setting up user accounts and groups in a network environment. This chapter also includes information about the files used to store user account and group information and about customizing the user's work environment.

This is a list of the overview information in this chapter.

- “What Are User Accounts and Groups?” on page 3
- “Guidelines for Managing User Accounts” on page 4
- “Guidelines for Managing Groups” on page 10
- “Tools for Managing User Accounts and Groups” on page 11
- “Where User Account and Group Information Is Stored” on page 16
- “Customizing a User's Work Environment” on page 20

For instructions about how to manage users accounts and groups, see Chapter 2.

---

## What Are User Accounts and Groups?

One of the basic system administration tasks is to set up a user account for each user at a site. A typical user account includes the information a user needs to log in and use a system (without having the system's root password). User account information consists of four main components:

- User name – A name that a user uses to log in to a system (also known as a login name).

- Password – A secret combination of characters that a user must enter with a user name to gain access to a system.
- User's home directory – A directory that is usually the user's current directory at login. It typically contains most of the user's files.
- User initialization files – Shell scripts that control how the user's working environment is set up when a user logs in to a system.

Also, when you set up a user account, you can add the user to predefined groups of users. A typical use of groups is to set up file and directory access only to users who are part of a group (using the group permissions on a file or directory).

For example, you might have a directory containing top secret files that only a few users should be able to access. You could set up a group called `topsecret` that included the users working on the top secret project, and you could set up the top secret files with read permission for the `topsecret` group. That way, only the users in the `topsecret` group would be able to read the files.

---

## Guidelines for Managing User Accounts

The following sections describe some guidelines and planning information for creating user accounts.

### Name Services

If you are managing user accounts for a large site, you may want to consider using a name service such as NIS or NIS+. A name service enables you to store user account information in a centralized manner instead of storing user account information in every system's `/etc` files. When using a name service for user accounts, users can move from system to system using the same user account without having site-wide user account information duplicated in every system's `/etc` files. Using a name service also promotes centralized and consistent user account information.

### User (Login) Names

User names, also called login names, let users access their own systems and remote systems that have the appropriate access privileges. You must choose a user name for each user account you create. User names must:

- Be unique within your organization, which may span multiple domains
- Contain from two to eight letters and numerals (the first character must be a letter and at least one character must be a lowercase letter)

- Not contain an underscore or space

It is helpful to establish a standard way of forming user names, and the names should be easy for users to remember. A simple scheme when selecting a user name is to use the first name initial and first seven letters of the user's last name. For example, Ziggy Ignatz becomes `zignatz`. If that scheme results in duplicate names, you can use the first initial, middle initial, and the first six characters of the user's last name. For example, Ziggy Top Ignatz becomes `ztignatz`. If that still results in duplicate names, you can use the first initial, middle initial, first five characters of the user's last name, and the number 1, or 2, or 3, and so on, until you have a unique name.

---

**Note** - Each new user name must be distinct from any mail aliases known to the system or to an NIS or NIS+ domain. Otherwise, mail may be delivered to the alias rather than to the actual user.

---

## User ID Numbers

Associated with each user name is a user identification (UID) number. The UID number identifies the user name to any system on which the user attempts to log in, and it is used by systems to identify the owners of files and directories. If you create user accounts for a single individual on a number of different systems, always use the same user name and user ID. In that way, the user can easily move files between systems without ownership problems.

UID numbers must be a whole number less than or equal to 2147483647, and they are required for both regular user accounts and special system accounts. Table 1-1 lists the UID numbers reserved for user accounts and system accounts.

TABLE 1-1 Reserved UID Numbers

User ID Numbers	Login Accounts	Reserved For ...
0 - 99	<code>root</code> , <code>daemon</code> , <code>bin</code> , <code>sys</code> , etc.	System accounts
100 - 2147483647	Regular users	General purpose accounts
60001	<code>nobody</code>	Unauthenticated users
60002	<code>noaccess</code>	Compatibility with Solaris 2.0 and compatible versions and SVR4 releases

Although UID numbers 0 through 99 are reserved, you can add a user with one of these numbers. However, do not use them for regular user accounts. By definition,

root always has UID 0, daemon has UID 1, and pseudo-user bin has UID 2. In addition, you should give uucp logins and pseudo user logins, like who, tty, and ttytype, low UIDs so they fall at the beginning of the passwd file.

As with user (login) names, you should adopt a scheme to assign unique UIDs. Some companies assign unique employee numbers, and administrators add 1000 to the employee number to create a unique UID number for each employee.

To minimize security risks, you should avoid reusing the UIDs from deleted accounts. If you must reuse a UID, “wipe the slate clean” so the new user is not affected by attributes set for a former user. For example, a former user may have been denied access to a printer—by being included in a printer deny list—but that attribute may not be appropriate for the new user. If need be, you can use duplicate UIDs in an NIS+ domain if the supply of unique UIDs is exhausted.

## Using Large User IDs and Group IDs

Previous Solaris software releases used 32-bit data types to contain the user IDs (UIDs) and group IDs (GIDs), but UIDs and GIDs were constrained to a maximum useful value of 60000. Starting with the Solaris 2.5.1 release and compatible versions, the limit on UID and GID values has been raised to the maximum value of a signed integer, or 2147483647.

UIDs and GIDs over 60000 do not have full functionality and are incompatible with many Solaris features, so avoid using UIDs or GIDs over 60000. See Table 1–2 for a complete list of interoperability issues with Solaris products and commands.

Table 1–2 describes interoperability issues with previous Solaris and Solaris product releases.

**TABLE 1–2** Interoperability Issues for UIDs/GIDs Over 60000

Category	Product/Command	Issues/Cautions
NFS™ Interoperability	SunOS 4.0 NFS software and compatible versions	NFS server and client code truncates large UIDs and GIDs to 16 bits. This can create security problems if SunOS 4.0 and compatible machines are used in an environment where large UIDs and GIDs are being used. SunOS 4.0 and compatible systems require a patch.
Name Service Interoperability	NIS name service File-based name service	Users with UIDs above 60000 can log in or use the su command on systems running the Solaris 2.5 and compatible versions, but their UIDs and GIDs will be set to 60001 (nobody).



**TABLE 1-2** Interoperability Issues for UIDs/GIDs Over 60000 (continued)

Category	Product/Command	Issues/Cautions
	NIS+ name service	Users with UIDs above 60000 are denied access on systems running Solaris 2.5 and compatible versions and the NIS+ name service.
Printed UIDs/GIDs	OpenWindows File Manager	Large UIDs and GIDs will not display correctly if the OpenWindows™ File Manager is used with the extended file listing display option.

**TABLE 1-3** Large UID/GID Limitation Summary

A UID or GID Of ...	Limitations
60003 or greater	<ul style="list-style-type: none"> <li>Users in this category logging into systems running Solaris 2.5 and compatible releases and the NIS or files name service will get a UID and GID of <i>nobody</i>.</li> </ul>
65535 or greater	<ul style="list-style-type: none"> <li>Solaris 2.5 and compatible releases systems running the NFS version 2 software will see UIDs in this category truncated to 16 bits, creating possible security problems.</li> <li>Users in this category using the <code>cpio</code> command (using the default archive format) to copy files will see an error message for each file and the UIDs and GIDs will be set to <i>nobody</i> in the archive.</li> <li>SPARC systems: Users in this category running SunOS 4.0 and compatible applications will see <code>EOverflow</code> returns from some system calls, and their UIDs and GIDs will be mapped to <i>nobody</i>.</li> <li>x86 systems: Users in this category on x86 systems running SVR3-compatible applications will probably see <code>EOverflow</code> return codes from system calls.</li> <li>x86 systems: If users in this category attempt to create a file or directory on a mounted System V file system, the System V file system returns an <code>EOverflow</code> error.</li> </ul>
100000 or greater	<ul style="list-style-type: none"> <li>The <code>ps -l</code> command displays a maximum five-digit UID so the printed column won't be aligned when they include a UID or GID larger than 99999.</li> </ul>
262144 or greater	<ul style="list-style-type: none"> <li>Users in this category using the <code>cpio</code> command (using <code>-H odc</code> format) or the <code>pax -x cpio</code> command to copy files will see an error message returned for each file, and the UIDs and GIDs will be set to <i>nobody</i> in the archive.</li> </ul>

**TABLE 1-3** Large UID/GID Limitation Summary *(continued)*

A UID or GID Of ...	Limitations
1000000 or greater	■ Users in this category using the <code>ar</code> command will have their UIDs and GIDs set to <code>nobody</code> in the archive.
2097152 or greater	■ Users in this category using the <code>tar</code> command, the <code>cpio -H ustar</code> command, or the <code>pax -x tar</code> command have their UIDs and GIDs set to <code>nobody</code> .

## Passwords

Although user names are publicly known, passwords must be kept secret and known only to users. Each user account should be assigned a password, which is a combination of six to eight letters, numbers, or special characters. You can set a user's password when you create the user account and have the user change it when logging in to a system for the first time.

To make your computer systems more secure, ask users to change their passwords periodically. For a high level of security, you should require users to change their passwords every six weeks. Once every three months is adequate for lower levels of security. System administration logins (such as `root` and `sys`) should be changed monthly, or whenever a person who knows the root password leaves the company or is reassigned.

Many breaches of computer security involve guessing a legitimate user's password. You should make sure that users avoid using proper nouns, names, login names, and other passwords that a person might guess just by knowing something about the user.

Good choices for passwords include:

- Phrases (`beammeup`)
- Nonsense words made up of the first letters of every word in a phrase (`swotrb` for `SomeWhere Over The RainBow`)
- Words with numbers or symbols substituted for letters (`sn00py` for `snoopy`)

Do not use these choices for passwords:

- Your name, forwards, backwards, or jumbled
- Names of family members or pets
- Car license numbers
- Telephone numbers
- Social Security numbers

- Employee numbers
- Names related to a hobby or interest
- Seasonal themes, such as Santa in December
- Any word in the dictionary

## Password Aging

If you are using NIS+ or the `/etc` files to store user account information, you can set up password aging on a user's password. Password aging enables you to force users to change their passwords periodically or to prevent a user from changing a password before a specified interval. If you want to prevent an intruder from gaining undetected access to the system by using an old and inactive account, you can also set a password expiration date when the account will be disabled.

## Home Directories

The home directory is the portion of a file system allocated to a user for storing private files. The amount of space you allocate for a home directory depends on the kinds of files the user creates and the type of work done. As a general rule, you should allocate at least 15 Mbytes of disk space for each user's home directory.

A home directory can be located either on the user's local system or on a remote file server. In either case, by convention the home directory should be created as `/export/home/username`. For a large site, you should store home directories on a server. Use a separate file system for each `/export/home` directory to facilitate backing up and restoring home directories (for example, `/export/home1`, `/export/home2`).

Regardless of where their home directory is located, users usually access their home directories through a mount point named `/home/username`. When AutoFS is used to mount home directories, you are not permitted to create any directories under the `/home` mount point on any system. The system recognizes the special status of `/home` when AutoFS is active. For more information about automounting home directories, see the *NFS Administration Guide*.

To use the home directory anywhere on the network, you should always refer to it as `$HOME`, not as `/export/home/username`. The latter is machine-specific. In addition, any symbolic links created in a user's home directory should use relative paths (for example, `../../../../x/y/x`), so the links will be valid no matter where the home directory is mounted.

## The User's Work Environment

Besides having a home directory to create and store files, users need an environment that gives them access to the tools and resources they need to do their work. When a user logs in to a system, the user's work environment is determined by initialization files that are defined by the user's startup shell, such as the C, Korn, or Bourne shell.

A good strategy for managing the user's work environment is to provide customized user initialization files (`.login`, `.cshrc`, `.profile`) in the user's home directory. See "Customizing a User's Work Environment" on page 20 for detailed information about customizing user initialization files for users. After you create the customized user initialization files, you can add them to a user's home directory when you create a new user account.

A recommended one-time task is to set up separate directories, called skeleton directories, on a server (you can use the same server where the user's home directories are stored). The skeleton directories enable you to store customized user initialization files for different types of users.

---

**Note** - Do not use system initialization files (`/etc/profile`, `/etc/.login`) to manage a user's work environment, because they reside locally on systems and are not centrally administered. For example, if AutoFS is used to mount the user's home directory from any system on the network, then you would have to modify the system initialization files on each system to ensure a consistent environment when a user moves from system to system.

---

---

## Guidelines for Managing Groups

A *group* is a collection of users who can share files and other system resources. For example, the set of users working on the same project could be formed into a group. A group is traditionally known as a UNIX group.

Each group must have a name, a group identification (GID) number, and a list of user names that belong to the group. A GID identifies the group internally to the system. There are two types of groups that a user can belong to:

- **Primary group** – Specifies a group that the operating system will assign to files created by the user. Each user must belong to a primary group.
- **Secondary groups** – Specifies one or more groups to which a user also belongs. Users can belong to up to 16 secondary groups.

Sometimes a user's secondary group is not important. For example, ownership of files reflect the primary group, not any secondary groups. Other applications, however, may rely on a user's secondary memberships. For example, a user has to be

a member of the `sysadmin` group (group 14) to use the Solstice AdminSuite software, but it doesn't matter if group 14 is his or her current primary group.

The `groups` command shows the groups a user belongs to. A user can have only one primary group at a time. However, the user can temporarily change the primary group (with the `newgrp` command) to any other group in which he or she is a member.

When adding a user account, you must assign a primary group for a user or accept the default: `staff` (group 10). The primary group should already exist (if it doesn't exist, specify the group by a GID number). User names are not added to primary groups. If they were, the list might become too long. Before you can assign users to a new secondary group, you must create the group and assign it a GID number.

Groups can be local to a system or can be managed through a name service. To simplify group administration, you should use a name service like NIS+, which enables you to centrally manage group memberships.

---

## Tools for Managing User Accounts and Groups

Table 1-4 lists the recommended tools for managing users and groups.

**TABLE 1-4** Recommended Tools for Managing Users and Groups

If You Are Managing Users and Groups ...	The Recommended Tool Is ...	And You Will Need ...	To Start This Tool See ...
On remote and/or local systems in a networked, name service (NIS, NIS+) environment	Solstice™ AdminSuite™'s User and Group Manager (graphical user interface)	Graphics monitor running an X window such as CDE or OpenWindows	<i>Solstice AdminSuite 2.3 Administration Guide</i>
On a local system	Admintool (graphical user interface)	Graphics monitor running an X window system such as CDE or OpenWindows	Chapter 2

The Solaris commands `useradd` and `groupadd` also let you set up users and groups on a local system; however, the commands do not change name service maps or tables. Table 1-5 describes the Solaris command used to manage user accounts and groups if you are not using Solstice AdminSuite or Admintool.

**TABLE 1-5** Managing User Accounts and Groups by Using Solaris Commands

<b>Task</b>	<b>If You Use This Name Service ...</b>	<b>Then Use These Commands</b>
Add a User Account	NIS+	<code>nistbladm</code> <code>nisclient</code>
	NIS	<code>useradd</code> <code>make</code>
	None	<code>useradd</code>
Modify a User Account	NIS+	<code>nistbladm</code>
	NIS	<code>usermod</code> <code>make</code>
	None	<code>usermod</code>
Delete a User Account	NIS+	<code>nistbladm</code> <code>nisclient</code>
	NIS	<code>userdel</code> <code>make</code>
	None	<code>userdel</code>
Set Up User Account Defaults	NIS+	<b>not available</b>
	NIS	<code>useradd -D</code> <code>make</code>
	None	<code>useradd -D</code>
Disable a User Account	NIS+	<code>nistbladm</code>

**TABLE 1-5** Managing User Accounts and Groups by Using Solaris Commands *(continued)*

<b>Task</b>	<b>If You Use This Name Service ...</b>	<b>Then Use These Commands</b>
Change a User's Password	NIS	<code>passwd -r nis -l</code> <code>make</code>
	None	<code>passwd -r files -l</code>
	NIS+	<code>passwd -r nisplus</code>
	NIS	<code>passwd -r nis</code>
Sort User Accounts	None	<code>passwd -r files</code>
	NIS+	<code>niscat</code> <code>sort</code>
	NIS	<code>ypcat</code> <code>sort</code>
	None	<code>awk</code> <code>sort</code>
Find a User Account	NIS+	<code>nismatch</code>
	NIS	<code>ypmatch</code>
	None	<code>grep</code>
Add a Group	NIS+	<code>nistbladm</code>
	NIS	<code>groupadd</code> <code>make</code>
	None	<code>groupadd</code>
Modify Users in a Group	NIS+	<code>nistbladm</code>
	NIS	<code>groupmod</code> <code>make</code>

**TABLE 1-5** Managing User Accounts and Groups by Using Solaris Commands *(continued)*

<b>Task</b>	<b>If You Use This Name Service ...</b>	<b>Then Use These Commands</b>
Delete a Group	None	groupmod
	NIS+	nistbladm
	NIS	groupdel make
	None	groupdel

## What You Can Do With Admintool

Admintool is a graphical user interface that enables you to set up user accounts on a local system.

### Modify User Accounts

Unless you define a user name or UID number that conflicts with an existing one, you should never need to modify a user account's login name or UID number. Use the following steps if two user accounts have duplicate user names or UID numbers:

- If two user accounts have duplicate UID numbers, use Admintool to remove one account and re-add it with a different UID number. You cannot use Admintool to modify a UID number of an existing user account.
- If two user account have duplicate user names, use Admintool to modify one of the accounts and change the user name.

If you do use Admintool to change a user name, the home directory's ownership is changed (if a home directory exists for the user).

One part of a user account that you can change is a user's group memberships. Admintool Modify option lets you add or delete a user's secondary groups. Alternatively, you can use the Groups window to directly modify a group's member list.

You can also modify the following parts of a user account:



- Comment
- Login shell
- Passwords
- Home directory
- AutoHome setup
- Credential table setup
- Mail server

## Delete User Accounts

When you delete a user account with Admintool, the software deletes the entries in the `passwd` and `group` files. In addition, you can delete the files in the user's home directory and delete the contents of the user's mailbox.

Only the single mail alias that directs mail to the user's mail box is deleted; the user name is not deleted from any other mail aliases. If you want to delete entries from mail aliases other than the one set up to direct mail to your mailbox, you must delete them by hand.

## Add Customized User Initialization Files

Although you can't create customized user initialization files with Admintool, you can populate a user's home directory with user initialization files located in a specified "skeleton" directory.

You can customize the user initialization templates in the `/etc/skel` directory and then copy them to users' home directories.

## Administer Passwords

You can use Admintool for password administration, which includes specifying a normal password for a user account, enabling users to create their own passwords during their first login, disabling or locking a user account, or specifying expiration dates and password aging information.

---

**Note** - Password aging is not supported by the NIS name service.

---

## Disable User Accounts

Occasionally, you may need to temporarily or permanently disable a login account. Disabling or locking a user account means that an invalid password, \*LK\*, is assigned to the user account, preventing future logins.

The easiest way to disable a user account is to use Admintool to lock the password for an account. You can also enter an expiration date in the Expiration Date field to set how long the user account is disabled.

Other ways to disable a user account is to set up password aging or by just changing the user's password.

---

## Where User Account and Group Information Is Stored

Depending on your site policy, you can store user account and group information in a name service or a local system's `/etc` files. In the NIS+ name service, information is stored in tables, and in the NIS name service, information is stored in maps.

---

**Note** - To avoid confusion, the location of the user account and group information will be generically referred to as a *file* rather than a *file*, *table*, or *map*.

---

Most of the user account information is stored in the `passwd` file. However, password encryption and password aging is stored in the `passwd` file when using NIS or NIS+ and in the `/etc/shadow` file when using `/etc` files. Password aging is not available when using NIS.

Group information is stored in the `group` file.

## Fields in the `passwd` File

The fields in the `passwd` file are separated by colons and contain the following information:

<code>username:password:uid:gid:comment:home-directory:login-shell</code>
---

For example:

<code>kryten:x:101:100:Kryten Series 4000:/export/home/kryten:/bin/csh</code>
---

Table 1-6 describes the `passwd` file fields.

**TABLE 1-6** Fields in the `passwd` File

Field Name	Description
<i>username</i>	Contains the user or login name. User names should be unique and consist of 1-8 letters (A-Z, a-z) and numerals (0-9). The first character must be a letter, and at least one character must be a lowercase letter. User names cannot contain underscores or spaces.
<i>password</i>	Contains an <code>x</code> , a placeholder for the encrypted password. The encrypted password is stored in the <code>shadow</code> file.
<i>uid</i>	Contains a user identification (UID) number that identifies the user to the system. UID numbers for regular users should range from 100 to 60000. All UID numbers should be unique.
<i>gid</i>	Contains a group identification (GID) number that identifies the user's primary group. Each GID number must be a whole number between 0 and 60002 (60001 and 60002 are assigned to <code>nobody</code> and <code>noaccess</code> , respectively).
<i>comment</i>	Usually contains the full name of the user. (This field is informational only.) It is sometimes called the GECOS field because it was originally used to hold the login information needed to submit batch jobs to a mainframe running GECOS (General Electric Computer Operating System) from UNIX systems at Bell Labs.
<i>home-directory</i>	Contains user's home directory path name.
<i>login-shell</i>	Contains the user's default login shell, which can be <code>/bin/sh</code> , <code>/bin/csh</code> or <code>/bin/ksh</code> . Table 1-11 contains a description of shell features.

## Fields in the Shadow File

The fields in the `shadow` file are separated by colons and contain the following information:

```
username:password:lastchg:min:max:warn:inactive:expire
```

For example:

```
rimmer:86Kg/MNT/dGu.:8882:0::5:20:8978
```

Table 1–7 describes the `shadow` file fields.

**TABLE 1–7** Fields in the `shadow` File

Field Name	Description
<i>username</i>	Contains the user or login name.
<i>password</i>	May contain the following entries: a 13-character encrypted user password; the string <code>*LK*</code> , which indicates an inaccessible account; or the string <code>NP</code> , which indicates no password for the account.
<i>lastchg</i>	Indicates the number of days between January 1, 1970, and the last password modification date.
<i>min</i>	Contains the minimum number of days required between password changes.
<i>max</i>	Contains the maximum number of days the password is valid before the user is prompted to specify a new password.
<i>inactive</i>	Contains the number of days a user account can be inactive before being locked.
<i>expire</i>	Contains the absolute date when the user account expires. Past this date, the user cannot log in to the system.

## Fields in the Group File

The fields in the `group` file are separated by colons and contain the following information:

```
group-name:group-password:gid:user-list
```

For example:

```
bin::2:root,bin,daemon
```

Table 1–8 describes the `group` file fields.

**TABLE 1–8** Fields in the `group` File

Field Name	Description
<i>group-name</i>	Contains the name assigned to the group. For example, members of the chemistry department in a university may be called <code>chem</code> . Group names can have a maximum of nine characters.
<i>group-password</i>	Usually contains an asterisk or is empty. The <i>group-password</i> field is a relic of earlier versions of UNIX. If a group has a password, the <code>newgrp</code> command prompts users to enter it. However, there is no utility to set the password.
<i>gid</i>	Contains the group's GID number. It must be unique on the local system, and should be unique across the entire organization. Each GID number must be a whole number between 0 and 60002. Numbers under 100 are reserved for system default group accounts. User defined groups can range from 100 to 60000. (60001 and 60002 are reserved and assigned to <code>nobody</code> and <code>noaccess</code> , respectively.)
<i>user-list</i>	Contains a list of comma-separated list of user names, representing the user's secondary group memberships. Each user can belong to a maximum of 16 secondary groups.

## UNIX User Groups

By default, all Solaris 7 systems have these groups:

```
root::0:root
other::1:
bin::2:root,bin,daemon
sys::3:root,bin,sys,adm
adm::4:root,adm,daemon
uucp::5:root,uucp
mail::6:root
tty::7:root,tty,adm
lp::8:root,lp,adm
nuucp::9:root,nuucp
staff::10:
daemon::12:root,daemon
sysadmin::14:
nobody::60001:
noaccess::60002:
nogroup::65534:
```

## Customizing a User's Work Environment

Part of setting up a user's home directory is providing user initialization files for the user's login shell. A *user initialization file* is a shell script that sets up a work environment for a user after the user logs in to a system. Basically, you can perform any task in a user initialization file that you can do in a shell script, but its primary job is to define the characteristics of a user's work environment, such as a user's search path, environment variables, and windowing environment. Each login shell has its own user initialization file (or files), which are listed in Table 1-9.

**TABLE 1-9** User Initialization Files for Bourne, C, and Korn Shells

Shell	User Initialization File	Purpose
Bourne	<code>\$HOME/.profile</code>	Defines user's environment at login
C	<code>\$HOME/.cshrc</code>	Defines user's environment for all C shells; invoked after login shell
	<code>\$HOME/.login</code>	Defines user's environment at login
Korn	<code>\$HOME/.profile</code>	Defines user's environment at login
	<code>\$HOME/\$ENV</code>	Defines user's environment at login in the file; specified by the Korn shell's <code>ENV</code> environment variable

The Solaris system software provides default user initialization files for each shell in the `/etc/skel` directory on each system, as shown in Table 1-10.

**TABLE 1-10** Default User Initialization Files

Shell	Default File
C	<code>/etc/skel/local.login</code>
	<code>/etc/skel/local.cshrc</code>
Bourne or Korn	<code>/etc/skel/local.profile</code>

TABLE 1-10 Default User Initialization Files (continued)

You can use these as a starting point and modify them to create a standard set of files that will provide the work environment common to all users, or you can modify them to provide the working environment for different types of users. See “How to Customize User Initialization Files” on page 36 for step-by-step instructions on how to create sets of user initialization files for different types of users.

## Use Site Initialization Files

When customizing a user initialization file, it is important that the user initialization files can be customized by both the administrator and the user. This important feature can be accomplished with centrally located and globally distributed user initialization files, called site initialization files. Site initialization files enable you to continually introduce new functionality to the user’s work environment, while enabling the user to also customize the user initialization file.

When you reference a site initialization file in a user initialization file, all updates to the site initialization file are automatically reflected when the user logs in to the system or when a user starts a new shell. Site initialization files are designed for you to distribute site-wide changes to users’ work environments that you did not anticipate when you added the users.

Any customization that can be done in a user initialization file can be done in a site initialization file. These files typically reside on a server (or set of servers), and appear as the first statement in a user initialization file. Also, each site initialization file must be the same type of shell script as the user initialization file that references it.

To reference a site initialization file in a C-shell user initialization file, place a line similar to the following at the beginning of the user initialization file:

```
source /net/machine-name/export/site-files/site-init-file
```

To reference a site initialization file in a Bourne- or Korn-shell user initialization file, place a line similar to the following at the beginning of the user initialization file:

```
. /net/machine-name/export/site-files/site-init-file
```

## Avoid Local System References

You should not add specific references to the local system in the user’s initialization file. You want the instructions in a user initialization file to be valid regardless of the system to which the user logs in. For example:

- To make a user's home directory available anywhere on the network, always refer to the home directory with the variable `$HOME`. For example, use `$HOME/bin`; do not use `/export/home/username/bin`. `$HOME` works when the user logs in to another system, when home directories are automounted.
- To access files on a local disk, use global path names, like `/net/machine-name/directory-name`. Any directory referenced by `/net/machine-name` can be mounted automatically on any system on which the user logs in, assuming the system is running AutoFS.

## Shell Features

Table 1–11 lists basic shell features that each shell provides, which can help you determine what you can and can't do when creating user initialization files for each shell.

**TABLE 1–11** Basic Features of Bourne, C, and Korn Shells

Feature	Bourne	C	Korn
Known as the standard shell in UNIX	Yes	No	No
Compatible syntax with Bourne shell	-	No	Yes
Job control	Yes	Yes	Yes
History list	No	Yes	Yes
Command-line editing	No	Yes	Yes
Aliases	No	Yes	Yes
Single-character abbreviation for login directory	No	Yes	Yes
Protection from overwriting (noclobber)	No	Yes	Yes
Setting to ignore Control-d (ignoreeof)	No	Yes	Yes
Enhanced <code>cd</code>	No	Yes	Yes



**TABLE 1–11** Basic Features of Bourne, C, and Korn Shells *(continued)*

Feature	Bourne	C	Korn
Initialization file separate from <code>.profile</code>	No	Yes	Yes
Logout file	No	Yes	No

## Shell Environment

A shell maintains an environment that includes a set of variables defined by the `login` program, the system initialization file, and the user initialization files. In addition, some variables are defined by default. A shell can have two types of variables:

- **Environment variables** – Variables that are exported to all processes spawned by the shell. Their settings can be seen with the `env` command. A subset of environment variables, like `PATH`, affects the behavior of the shell itself.
- **Shell (local) variables** – Variables that affect only the current shell. In the C shell, a set of these shell variables have a special relationship to a corresponding set of environment variables. These shell variables are `user`, `term`, `home`, and `path`. The value of the environment variable counterpart is initially used to set the shell variable.

In the C shell, you use the lowercase names with the `set` command to set shell variables and use uppercase names with the `setenv` command to set environment variables. If you set a shell variable, the shell sets the corresponding environment variable and vice versa. For example, if you update the `path` shell variable with a new path, the shell also updates the `PATH` environment variable with the new path.

In the Bourne and Korn shells, you use the uppercase names with the `setenv` command to set both shell and environment variables. You also have to use the `export` command to finish setting environment variables. For all shells, you generally refer to shell and environment variables by their uppercase names.

In a user initialization file, you can customize a user's shell environment by changing the values of the predefined variables or by specifying additional variables. Table 1–12 shows how to set environment variables in a user initialization file.

TABLE 1-12 Setting Environment Variables in a User Initialization File

If You Want to Set a User's Environment Variables for The ...	Then Add the Following Line to the User Initialization File ...
C shell	<pre>setenv VARIABLE value</pre> <p>Example:</p> <pre>setenv MAIL /var/mail/ripley</pre>
Bourne or Korn shell	<pre>VARIABLE=value; export VARIABLE</pre> <p>Example:</p> <pre>MAIL=/var/mail/ripley;export MAIL</pre>

Table 1-13 describes environment and shell variables you may want to customize in a user initialization file. For more information about variables used by the different shells, see `sh(1)`, `ksh(1)`, or `csh(1)`.

TABLE 1-13 Shell and Environment Variable Descriptions

Variable	Description
ARCH	Sets the user's system architecture (for example, <code>sun4</code> , <code>i386</code> ). This variable can be set with <code>ARCH = `uname -p`</code> (in Bourne or Korn shells) or <code>setenv ARCH `uname -p`</code> (in C shell). There is no built-in behavior of the shell that depends on this variable. It's just a useful variable for branching within shell scripts.
CALENDAR	Sets the path to the Calendar executables.
CDPATH (or <code>cdpath</code> in the C shell)	Sets a variable used by the <code>cd</code> command. If the target directory of the <code>cd</code> command is specified as a relative path name, the <code>cd</code> command will first look for the target directory in the current directory ( <code>.</code> ). If the target is not found, the path names listed in the <code>CDPATH</code> variable are searched consecutively until the target directory is found and the directory change is completed. If the target directory is not found, the current working directory is left unmodified. For example, the <code>CDPATH</code> variable is set to <code>/home/jean</code> , and two directories exist under <code>/home/jean</code> : <code>bin</code> and <code>rje</code> . If you are in the <code>/home/jean/bin</code> directory and type <code>cd rje</code> , you change directories to <code>/home/jean/rje</code> , even though you do not specify a full path.

**TABLE 1–13** Shell and Environment Variable Descriptions *(continued)*

Variable	Description
DESKSET	Sets the path to the DeskSet™ executables.
history	Sets history for the C shell.
HOME (or home in the C shell)	Sets the path to the user's home directory.
LANG	Sets the locale.
LOGNAME	Defines the name of the user currently logged in. The default value of LOGNAME is automatically set by the login program to the user name specified in the <code>passwd</code> file. You should only need to refer to (not reset) this variable.
LPDEST	Sets the user's default printer.
MAIL	Sets the path to the user's mailbox.
MANPATH	Sets the hierarchies of man pages available.
MANSECTS	Sets the hierarchies of man pages available.
OPENWINHOME	Sets the path to the OpenWindows subsystem.
PATH (or path in the C shell)	<p>Lists, in order, the directories that the shell searches to find the program to run when the user types a command. If the directory is not in the search path, users must type the complete path name of a command.</p> <p>The default PATH is automatically defined and set as specified in <code>.profile</code> (Bourne or Korn shell) or <code>.cshrc</code> (C shell) as part of the login process.</p> <p>The order of the search path is important. When identical commands exist in different locations, the first command found with that name is used. For example, suppose that PATH is defined (in Bourne and Korn shell syntax) as <code>PATH=/bin:/usr/bin:/usr/sbin:\$HOME/bin</code> and a file named <code>sample</code> resides in both <code>/usr/bin</code> and <code>/home/jean/bin</code>. If the user types the command <code>sample</code> without specifying its full path name, the version found in <code>/usr/bin</code> is used.</p>
prompt	Defines the shell prompt for the C shell.
PS1	Defines the shell prompt for the Bourne or Korn shell.

**TABLE 1-13** Shell and Environment Variable Descriptions *(continued)*

Variable	Description
<code>SHELL</code> (or shell in the C shell)	Sets the default shell used by <code>make</code> , <code>vi</code> , and other tools.
<code>TERMINFO</code>	<p>Specifies the path name for an unsupported terminal that has been added to the <code>terminfo</code> file. Use the <code>TERMINFO</code> variable in <code>/etc/profile</code> or <code>/etc/.login</code>.</p> <p>When the <code>TERMINFO</code> environment variable is set, the system first checks the <code>TERMINFO</code> path defined by the user. If it does not find a definition for a terminal in the <code>TERMINFO</code> directory defined by the user, it searches the default directory, <code>/usr/share/lib/terminfo</code>, for a definition. If it does not find a definition in either location, the terminal is identified as “dumb.”</p>
<code>TERM</code> (or term in the C shell)	Defines the terminal. This variable should be reset in <code>/etc/profile</code> or <code>/etc/.login</code> . When the user invokes an editor, the system looks for a file with the same name as the definition of this environment variable. The system searches the directory referenced by <code>TERMINFO</code> to determine the terminal characteristics.
<code>TZ</code>	Sets the time zone, which is used to display dates, for example, in the <code>ls -l</code> command. If <code>TZ</code> is not set in the user’s environment, the system setting is used; otherwise, Greenwich Mean Time is used.

## The PATH Variable

When the user executes a command by using the full path, the shell uses that path to find the command. However, when users specify only a command name, the shell searches the directories for the command in the order specified by the `PATH` variable. If the command is found in one of the directories, the shell executes it.

A default path is set by the system, but most users modify it to add other command directories. Many user problems related to setting up the environment and accessing the right version of a command or a tool can be traced to incorrectly defined paths.

### Guidelines

Here are some guidelines for setting up efficient `PATH` variables:

- If security is not a concern, put the current working directory (`.`) first in the path. However, including the current working directory in the path poses a security risk that you may want to avoid, especially for superuser.

- Keep the search path as short as possible. The shell searches each directory in the path. If a command is not found, long searches can slow down system performance.
- The search path is read from left to right, so you should put directories for commonly used commands at the beginning of the path.
- Make sure directories are not duplicated in the path.
- Avoid searching large directories, if possible. Put large directories at the end of the path.
- Put local directories before NFS™ mounted directories to lessen the chance of “hanging” when the NFS server does not respond and to reduce unnecessary network traffic.

## Examples—Setting a User’s Default Path

The following examples show how to set a user’s default path to include the home directory and other NFS mounted directories (the current working directory is specified first in the path). In a C-shell user initialization file, you would add the following:

```
set path=(. /usr/bin $HOME/bin /net/glr/files1/bin)
```

In a Bourne- or Korn-shell user initialization file, you would add the following:

```
PATH=./usr/bin:/$HOME/bin:/net/glr/files1/bin
export PATH
```

## The Locale Variables

The LANG and LC environment variables specify the locale-specific conversions and conventions for the shell, like timezones, collation orders, and formats of dates, time, currency, and numbers. In addition, you can use the stty command in a user initialization file to set whether the system will support multibyte characters.

LANG sets all possible conversions and conventions for the given locale. If you have special needs, you can set various aspects of localization separately through these LC variables: LC\_COLLATE, LC\_CTYPE, LC\_MESSAGES, LC\_NUMERIC, LC\_MONETARY, and LC\_TIME.

Table 1–14 describes the values for the LANG and LC environment variables.

**TABLE 1-14** Values for LANG and LC Variables

Value	Locale
de	German
fr	French
iso_8859_1	English and European
it	Italian
japanese	Japanese
korean	Korean
sv	Swedish
tchinese	Taiwanese

## Examples—Setting the Locale Using the LANG Variables

The following examples show how to set the locale using the LANG environment variables. In a C-shell user initialization file, you would add the following:

```
setenv LANG DE
```

In a Bourne- or Korn-shell user initialization file, you would add the following:

```
LANG=DE; export LANG
```

## Default File Permissions (umask)

When you create a file or directory, the default file permissions assigned to the file or directory are controlled by the *user mask*. The user mask should be set by the `umask` command in a user initialization file. You can display the current value of the user mask by typing `umask` and pressing Return.

The user mask can be set with a three-digit octal value. The first digit sets permissions for the user; the second sets permissions for group; the third sets permissions for other (also referred to as “world”). Note that if the first digit is zero, it is not displayed. For example, if `umask` is set to 022, 22 is displayed.

To determine the `umask` value you want to set, subtract the value of the permissions you want from 666 (for a file) or 777 (for a directory). The remainder is the value to use with the `umask` command. For example, suppose you want to change the default mode for files to 644 (`rw-r--r--`). The difference between 666 and 644 is 022, which is the value you would use as an argument to the `umask` command.

You can also determine the `umask` value you want to set by using Table 1-15, which shows the file and directory permissions that are created for each of the octal values of `umask`.

**TABLE 1-15** Permissions for `umask` Values

<code>umask</code> Octal Value	File Permissions	Directory Permissions
0	<code>rw-</code>	<code>rwX</code>
1	<code>rw-</code>	<code>rw-</code>
2	<code>r--</code>	<code>r-X</code>
3	<code>r--</code>	<code>r--</code>
4	<code>-w-</code>	<code>-wX</code>
5	<code>-w-</code>	<code>-w-</code>
6	<code>--x</code>	<code>--x</code>
7	<code>---</code> (none)	<code>---</code> (none)

The following line in a user initialization file sets the default file permissions to `rw-rw-rw-`.

```
umask 000
```

## Examples of User and Site Initialization Files

The following sections provide examples of user and site initialization files that you can use to start customizing your own initialization files. Many of the examples use system names and paths that you will have to change for your particular site.

## Example—.profile File

**CODE EXAMPLE 1-1** Example .profile File

```
1 PATH=$PATH:$HOME/bin:/usr/local/bin:/usr/ccs/bin:.
2 MAIL=/var/mail/$LOGNAME
3 NNTPSERVER=server1
4 MANPATH=/usr/share/man:/usr/local/man
5 PRINTER=printer1
6 umask 022
7 export PATH MAIL NNTPSERVER MANPATH PRINTER
```

## Example—.cshrc File

**CODE EXAMPLE 1-2** Example .cshrc File

```
8 set path=($PATH $HOME/bin /usr/local/bin /usr/ccs/bin)
9 setenv MAIL /var/mail/$LOGNAME
10 setenv NNTPSERVER server1
11 setenv PRINTER printer1
12 alias h history
13 umask 022
14 source /net/server2/site-init-files/site.login
```

## Example—Site Initialization File

The following shows an example site initialization file in which a user can choose a particular version of an application.

- 
1. Defines the user's shell search path.
  2. Defines the path to the user's mail file.
  3. Defines the environment variable to the user's Usenet news server.
  4. Defines the user's search path for man pages.
  5. Defines the user's default printer.
  6. Sets the user's default file creation permissions.
  7. Sets the listed environment variables.
  8. Sets the user's shell search path.
  9. Sets the path to the user's mail file.
  10. Sets the user's Usenet news server.
  11. Sets the user's default printer.
  12. Creates an alias for the history command (the user will need to type only `h` to run the history command).



**TABLE 1–16** Example Site Initialization File

```
# @(#)site.login
main:
echo "Application Environment Selection"
echo ""
echo "1. Application, Version 1"
echo "2. Application, Version 2"
echo ""
echo -n "Type 1 or 2 and press Return to set your
application environment: "

set choice = $<

if ( $choice !~ [1-2] ) then
goto main
endif

switch ( $choice )

case "1":
setenv APPHOME /opt/app-v.1
breaksw

case "2":
setenv APPHOME /opt/app-v.2
endsw
```

This site initialization file could be referenced in a user's `.cshrc` file (C shell users only) with the following line:

```
source /net/server2/site-init-files/site.login
```

In this line, the site initialization file is named `site.login` and is located on a server named `server2`. This line also assumes that the automounter is running on the user's system.

---

13. Sets the user's default file creation permissions.

14. Runs the site initialization file shown in "Example—Site Initialization File" on page 30.



## Setting Up and Maintaining User Accounts and Groups (Tasks)

---

This chapter describes the procedures for setting up and maintaining user accounts and groups.

This is a list of the step-by-step instructions in this chapter.

- “How to Customize User Initialization Files” on page 36
- “How to Start Admintool” on page 37
- “How to Add a Group” on page 38
- “How to Add a New User Account” on page 39
- “How to Share a User’s Home Directory” on page 41
- “How to Mount a User’s Home Directory” on page 43
- “How to Modify a Group” on page 45
- “How to Delete a Group” on page 46
- “How to Modify a User Account” on page 46
- “How to Disable a User Account ” on page 48
- “How to Change a User’s Password ” on page 49
- “How to Change Password Aging for a User Account ” on page 50
- “How to Delete a User Account ” on page 51
- “How to Restart Solaris User Registration” on page 54
- “How To Disable User Registration” on page 55

For overview information about Managing User Accounts and Groups, see Chapter 1.

---

## Becoming Superuser (root)

Most administrative tasks such as adding users require that you log in as root (UID=0) first. The root account is also known as the *superuser* account because it's used to make system changes and can override user file protection in emergency situations.

The superuser account should only be used to perform administrative tasks to prevent indiscriminate changes to the system.

You can either log into the system as superuser or use the `su(1M)` command to change to the superuser account.

### ▼ How to Become Superuser (root)

Become superuser by one of the following methods. Both methods require that you know the root password.

- Change to the superuser account by using the `su` command.

```
% su
Password: root_password
#
```

The pound sign (#) is the Bourne shell prompt for the superuser account.

- Log in as superuser on the system console.

```
hostname console: root
Password: root_password
#
```

This method is not enabled by default. You must modify the `/etc/default/login` file to log in as superuser on the system console. See “Securing Systems (Tasks)” in *System Administration Guide, Volume II* for information on modifying this file.

---

## Setting Up User Accounts Task Map

**TABLE 2-1** Task Map: Setting Up User Accounts

Task	Description	For Instructions, Go To
1. Customize User Initialization Files	<i>Optional.</i> Set up user initialization files (.cshrc, .profile, .login), so you can provide new users with consistent environments.	“How to Customize User Initialization Files” on page 36
2. Add a Group	<i>Optional.</i> To help administer users, add groups by using the Groups main window.	“How to Add a Group” on page 38
3. Add a User Account	Add a user account by using Admintool’s Users main window.	“How to Add a New User Account” on page 39
4. Share the User’s Home Directory	Share the user’s home directory, so the directory can be remotely mounted from the user’s system.	“How to Share a User’s Home Directory” on page 41
5. Mount the User’s Home Directory	Manually mount the user’s home directory on the user’s system by using the mount command.	“How to Mount a User’s Home Directory” on page 43

## User Information Data Sheet

You may find it useful to create a form like the one below to gather information about users before adding their accounts.

Item	Description
User Name:	<input type="text"/>
UID:	<input type="text"/>
Primary Group:	<input type="text"/>
Secondary Groups:	<input type="text"/>
Comment:	<input type="text"/>
Default Shell:	<input type="text"/>
Password Status and Aging:	<input type="text"/>

Home Directory Server Name:	
Home Directory Path Name:	
Mounting Method:	
Permissions on Home Directory:	
Mail Server:	
Department Name:	
Department Administrator:	
Manager:	
Employee Name:	
Employee Title:	
Employee Status:	
Employee Number:	
Start Date:	
Add to These Mail Aliases:	
Desktop System Name:	

## ▼ How to Customize User Initialization Files

1. **Become superuser on the system where the users' home directories are created and shared.**
2. **Create a skeleton directory for each type of user.**

```
# mkdir /shared-directory/skel/user-type
```

*shared-directory*

The name of a directory that is available to other systems on the network.

*user-type*

The name of a directory to store initialization files for a type of user.

3. **Copy the default user initialization files into the directories you created for different types of users.**

```
# cp /etc/skel/local.cshrc /shared-directory/skel/user-type/.cshrc
# cp /etc/skel/local.login /shared-directory/skel/user-type/.login
# cp /etc/skel/local.profile /shared-directory/skel/user-type/.profile
```

---

**Note** - You can use the `ls -a` command to list `.` (dot) files.

---

4. **Edit the user initialization files for each user type and customize them based on your site's needs.**

See “Customizing a User's Work Environment” on page 20 for a detailed description on the ways to customize the user initialization files.

5. **Set the permissions for the user initialization files.**

```
# chmod 744 /shared-directory/skel/user-type/*.*
```

## Example—Customizing User Initialization Files

The following example customizes the C-shell user initialization file in the `/export/skel/enduser` directory designated for a particular type of user.

```
# mkdir /export/skel/enduser
# cp /etc/skel/local.cshrc /export/skel/enduser/.cshrc

( Edit .cshrc file—see “Example—.cshrc File ” on page 30 )
# chmod 744 /export/skel/enduser/*.*
```

## ▼ How to Start Admintool

1. **Verify that the following prerequisites are met. To use Admintool, you must:**
  - Have a bit-mapped display monitor. The Admintool software can be used only on a system with a console that is a bit-mapped screen such as a standard display monitor that comes with a Sun workstation.
  - Be running an X Window System, such as the OpenWindows environment.

- Be a member of the sysadmin group (group 14).

If you want to perform administration tasks on a system with an ASCII terminal as the console, use Solaris commands instead. See `useradd(1M)` for more information.


## 2. Start Admintool.

```
$ admintool &
```

The Users main window is displayed.

## Example—Starting Admintool

This is the Users main window, which enables you to manage user account information.



## ▼ How to Add a Group

### 1. Start Admintool, if it's not already running.

See "How to Start Admintool" on page 37 for more information on starting Admintool.

### 2. Choose Groups from the Browse menu.

The Groups window is displayed.

### 3. Select Add from the Edit menu.




The Add window is displayed. If you need information to complete a field, click on the Help button to see field definitions for this window.

4. **Type the name of the new group in the Group Name text box.**
5. **Type the group ID for the new group in the Group ID text box.**  
The group ID should be unique.
6. **(Optional) Type user names in the Members List text box.**  
The list of users will be added to the group. User names must be separated by commas.
7. **Click on OK.**  
The list of groups displayed in the Groups window is updated to include the new group.

## Example—Adding a Group

The following example adds a group named `users` that has a group ID of 101.



## ▼ How to Add a New User Account

1. **(Optional) Fill out the user information data sheet on “User Information Data Sheet” on page 35.**
2. **Start Admintool, if it’s not already running.**  
See “How to Start Admintool” on page 37 for more information.
3. **Choose Add from the Edit menu.**  
The Add User window is displayed.
4. **Fill in the Add User window.**

If you need information to complete a field, click on the Help button to see field definitions for this window.

**5. Click on OK.**

The list of user accounts displayed in the Users main window is updated to include the new user account.

## Where to Go From Here

If you created a user's home directory, you must share the directory so the user's system can remotely mount it. See "How to Share a User's Home Directory" on page 41 for detailed instructions.

If disk space is limited, you can set up a disk quota for the user in the file system containing the user's home directory. See "Managing Quotas (Tasks)" in *System Administration Guide, Volume II* for information on setting disk quotas.

## Example—Adding a New User Account

The following example adds the user `kryten` to the system.

**Admintool: Add User**

**USER IDENTITY**

User Name:

User ID:

Primary Group:

Secondary Groups:

Comment:

Login Shell:

**ACCOUNT SECURITY**

Password:

Min Change:  days

Max Change:  days

Max Inactive:  days

Expiration Date:

(dd/mm/yy)

Warning:  days

**HOME DIRECTORY**

Create Home Dir: ☐

Path:

## ▼ How to Share a User's Home Directory

1. Become superuser on the system that contains the home directory.
2. Verify that the `mountd` daemon is running.

```
# ps -ef | grep mountd
root    176      1  0   May 02 ?           0:19 /usr/lib/nfs/mountd
```

The `/usr/lib/nfs/mountd` line is displayed if the `mountd` daemon is running.

**3. If the `mountd` daemon is not running, start it.**

```
# /etc/init.d/nfs.server start
```

**4. List the file systems that are shared on the system.**

```
# share
```

**5. Determine your next step based on whether the file system containing the user's home directory is already shared.**

If the File System Containing the User's Home Directory Is ...	Then ...
Already shared	Go to the verification step below.
Not shared	Go to Step 6 on page 42

**6. Edit the `/etc/dfs/dfstab` file and add the following line.**

```
share -F nfs /file-system
```

*file-system* Is the file system containing the user's home directory that you need to share. By convention, the file system is `/export/home`.

**7. Share the file systems listed in the `/etc/dfs/dfstab` file.**

```
# shareall -F nfs
```

This command executes all the `share` commands in the `/etc/dfs/dfstab` file, so you do not have to wait to reboot the system.

**8. Verify that a user's home directory is shared, as follows:**

```
# share
```

## Where to Go From Here

If the user's home directory is not located on the user's system, you have to mount the user's home directory from the system where it is located. See "How to Mount a User's Home Directory" on page 43 for detailed instructions.

### Example—Sharing a User's Home Directory

```
# ps -ef | grep mountd
# /etc/init.d/nfs.server start
# share
# vi /etc/dfs/dfstab

(The line share -F nfs /export/home is added.)

# shareall -F nfs
# share
-                /usr/dist                ro    ""
-                /export/home/user-name    rw    ""
```

## ▼ How to Mount a User's Home Directory

1. Make sure that the user's home directory is shared. See "How to Share a User's Home Directory" on page 41 for more information.
2. Log in as superuser on the user's system.
3. Edit the `/etc/vfstab` file and create an entry for the user's home directory.

```
system-name: /export/home/user-name - /export/home/user-name nfs - yes rw
```

<i>system-name</i>	Is the name of the system where the home directory is located.
<code>/export/home/<i>user-name</i></code>	Is the name of the user's home directory that will be shared. By convention, <code>/export/home</code> contains user's home directories; however, this could be a different file system.
-	Are required placeholders in the entry.
<code>/export/home/<i>user-name</i></code>	Is the name of the directory where the user's home directory will be mounted.

See Chapter 28 for more information about adding an entry to the `/etc/vfstab` file.

**4. Create the mount point for the user's home directory.**

```
# mkdir -p /export/home/user-name
```

**5. Mount the user's home directory.**

```
# mountall
```

All entries in the current `vfstab` file (whose `mount` `at` `boot` fields are set to `yes`) are mounted.

**6. Use the `mount` command to verify that the home directory is mounted.**

### Example—Mounting a User's Home Directory

```
# vi /etc/vfstab

(The line  venus:/export/home/ripley - /export/home/ripley
nfs - yes rw is added.)

# mkdir -p /export/home/ripley
# mountall
# mount
/ on /dev/dsk/c0t3d0s0 read/write/setuid/
largefiles on Tue Jun 2 12:37:36 1998
/usr on /dev/dsk/c0t3d0s6 read/write/setuid/
largefiles on Tue Jun 2 12:37:36 1998
/proc on /proc read/write/setuid on Tue Jun 2 12:37:36 1998
/dev/fd on fd read/write/setuid on Tue Jun 2 12:37:38 1998
/opt on /dev/dsk/c0t3d0s5 setuid/read/write/
largefiles on Tue Jun 2 12:37:38 1998
/tmp on swap read/write on Jun 2 12:37:39 1998
/export/home/ripley on venus:/export/home/ripley /read/write/
remote on Jun 2 12:37:40 ...
```

---

## Maintaining User Accounts Task Map

**TABLE 2-2** Task Map: Maintaining User Accounts

Task	Description	For Instructions, Go To
1. Modify a Group	Modify a group's name or the users in a group by choosing Modify from the Edit menu in the Groups window.	"How to Modify a Group" on page 45
2. Delete a Group	Delete a group by choosing Delete from the Edit menu in the Groups window.	"How to Delete a Group" on page 46
3. Modify a User Account	<p><i>Disable a User Account</i></p> <p>If you want to temporarily disable a user account, lock the user account from the Password menu in the Modify window.</p> <p><i>Change a User's Password</i></p> <p>If you want to change a user's password, use the Password menu in the Modify window.</p> <p><i>Change Password Aging</i></p> <p>If you want to force users to change their passwords periodically, change the Password Aging fields in the Modify window (Account Security category).</p>	<p>"How to Disable a User Account " on page 48</p> <p>"How to Change a User's Password " on page 49</p> <p>"How to Change Password Aging for a User Account " on page 50</p>
4. Delete a User Account	Delete a user account by choosing Delete from in the Edit menu in the Users window.	"How to Delete a User Account " on page 51

## ▼ How to Modify a Group

- 1. Start Admintool, if its not already running. Select Groups from the Browse menu.**  
See "How to Start Admintool" on page 37 for more information.
- 2. Select the group entry you want to modify from the Groups window.**
- 3. Choose Modify from the Edit menu.**  
The Modify Group window is displayed containing the selected group entry.
- 4. Modify either the group's name or the users in the group.**


User names must be separated by commas. If you need information to complete a field, click on the Help button to see field definitions for this window.

**5. Click on OK.**

The group information displayed in the Groups window is updated.

## Example—Modifying a Group

The following example adds the users `r2d2`, `holly`, and `kryten` to the `staff` group.



## ▼ How to Delete a Group

1. **Start Admintool, if it's not already running. Select Groups from the Browse menu.**

See "How to Start Admintool" on page 37 for more information.

2. **Select the group entry you want to delete from Groups window.**

3. **Choose Delete from the Edit menu.**

A window is displayed asking you to confirm the deletion.

4. **Click on OK.**

The group entry is deleted from the Groups window.

## ▼ How to Modify a User Account

1. **Start Admintool, if it's not already running. Select Users from the Browse menu.**

See "How to Start Admintool" on page 37 for more information.

2. **Select the user account entry to modify from the Users window.**



**3. Choose Modify User from the Edit menu.**

The Modify window is displayed containing the selected user account entry.

**4. Modify the user account.**

If you need information to complete a field, click on the Help button to see field definitions for this window. You can change any of the Account Security fields, which includes changing a password or changing password aging. See the following tasks for detailed step-by-step instructions:

- “How to Disable a User Account ” on page 48
- “How to Change a User’s Password ” on page 49
- “How to Change Password Aging for a User Account ” on page 50

**5. Click on OK.**

**6. To verify that the modifications were made, double-click on the modified user account entry in the Users window, then click on Cancel to close the window without making any modifications.**

## Example—Modifying a User Account

The following example adds the secondary group membership `lp` to the `rimmer` user account.

**Admintool: Modify User**

**USER IDENTITY**

User Name:

User ID: 1002

Primary Group:

Secondary Groups:

Comment:

Login Shell:  ☐ /bin/csh

**ACCOUNT SECURITY**

Password:  ☐

Min Change:  days

Max Change:  days

Max Inactive:  days

Expiration Date: (dd/mm/yy)  ☐  ☐  ☐

Warning:  days

**HOME DIRECTORY**

Path:

## ▼ How to Disable a User Account

---

**Note** - You can enable the user account by changing the password status to Normal Password or Cleared Until First Login.

---

1. **Start Admintool, if it's not already running. Select Users from the Browse menu, if necessary.**  
See "How to Start Admintool" on page 37 for more information.
2. **Select the user account entry to be disabled.**
3. **Choose Modify from the Edit menu.**  
The Modify Users window is displayed containing the selected user account entry.

4. **Choose Account Is Locked from the Password menu.**  
This selects the locked password status, which disables the user account.
5. **Click on OK.**
6. **Verify that you have disabled the user account by attempting to log in with the disabled user account.**

## Example—Disabling a User Account

The following example disables the `rimmer` user account.

**Admintool: Modify User**

**USER IDENTITY**

User Name:

User ID: 1002

Primary Group:

Secondary Groups:

Comment:

Login Shell:

**ACCOUNT SECURITY**

Password:

Min Change:  days

Max Change:  days

Max Inactive:  days

Expiration Date:

(dd/mm/yy)

Warning:  days

**HOME DIRECTORY**

Path:

## ▼ How to Change a User's Password

1. **Start Admintool, if it's not already running. Select Users from the Browse menu.**

See “How to Start Admintool” on page 37 for more information.

2. **Select the user account entry that needs the password changed.**
3. **Choose Modify from the Edit menu.**  
The Modify User window is displayed containing the selected user account entry.
4. **Choose Normal Password from the Password menu.**
5. **Click on OK.**

### Example—Changing a User’s Password

This is the pop-up window used to change user’s passwords that is available from the Add User or Modify User windows.



## ▼ How to Change Password Aging for a User Account

1. **Start Admintool, if its not already running. Select Users from the Browse menu.**  
See “How to Start Admintool” on page 37 for more information.
2. **Select the user account entry that needs its password aging changed.**
3. **Choose Modify from the Edit menu.**  
The Modify window is displayed containing the selected user account entry.
4. **Change the following fields that affect password aging:**
  - Min Change


- Max Change
- Max Inactive
- Expiration Date
- Warning

If you need information about the password aging fields that are part of the Account Security category, click on the Help button.

**5. Click on OK.**

## Example—Changing Password Aging for a User Account

In the following example, the user must keep a new password for at least one day (Min Change) , and must change the password every 60 days (Max Change). The user must change the password if the account is inactive for more than 10 days (Max Inactive).



## ▼ How to Delete a User Account

1. **Start Admintool, if it's not already running. Select Users from the Browse menu, if necessary.**  
See "How to Start Admintool" on page 37 for more information.
2. **Select the user account entry to remove from the Users window.**
3. **Choose Delete from the Edit menu.**

The Delete window is displayed to confirm the removal of the user account.

4. (Optional) Click on the check box to delete the user's home directory and its contents.
5. Click on OK when you are ready to delete the user account. The user account entry is deleted from the Users main window.

### Example—Deleting a User Account

The account for user `kryten` and the `/export/home/kryten` directory is removed.



---

## Solaris User Registration

Solaris User Registration is a tool for getting information about new Solaris releases, upgrade offers, and promotions. This graphical user interface (GUI) automatically starts when you first log into your desktop. The GUI lets you register now, later, or never. The registration process also provides Sun with the user's Solaris version, survey type, platform, hardware, and locale.

### Accessing Solaris<sup>SM</sup> Solve<sup>SM</sup>

Completing the Solaris User Registration process provides access to Solaris Solve, an exclusive web site that offers valuable Solaris product information and solutions—all in one convenient location. It provides a quick and easy method for getting the most recent information on what's happening around the latest Solaris release. Solaris Solve also provides a preview to additional Sun contract and service opportunities.

Basically, the steps for completing Solaris User Registration and accessing Solaris Solve are:

1. Fill in the electronic Solaris User Registration profile.

2. Submit the profile by email or print the profile to fax or mail.
3. Create your login ID and password to access the Solaris Solve site.

Even if you do not access the Solaris Solve site immediately, we recommend that you create your Solaris Solve login ID and password during the Solaris User Registration process. A Solaris Solve login ID and password should contain 6 to 8 alphanumeric characters without spaces and colons.

4. Access the Solaris Solve site.

---

**Note** - Solaris User Registration is not invoked if the system administrator or user is logged in as superuser.

---

If you choose to register, a copy of the completed form is stored in `$HOME/.solregis/uprops`. If you choose to never register and change your mind later, you can start User Registration by:

- Typing `/usr/dt/bin/solregis` at any command line prompt, or
- Clicking the Registration icon in the Application Manager's desktop tools folder (Common Desktop Environment desktop only)

See `solregis(1)` for more information.

## Troubleshooting Solaris User Registration Problems

This section provides troubleshooting tips for solving Solaris User Registration problems.

The following table describes problems that may occur when you try to register, and actions required to resolve these conflicts.

**TABLE 2-3** Registration Problem Descriptions and Suggested Resolutions

Problem Description	How to Resolve the Problem
The registration form failed to initialize: Web page window displays and requests user see system administrator to resolve problem that prevents registration setup.	Check for missing registration files.
The form could not be emailed: Dialog box displays and requests user see system administrator to resolve problem.	Check to see if email is configured correctly. Also check if CDE is on user's system since it must be present to email completed registration form. Alternatively, users can print the form and fax or mail it.

**TABLE 2-3** Registration Problem Descriptions and Suggested Resolutions *(continued)*

Problem Description	How to Resolve the Problem
The form could not be printed: Dialog box displays and requests user to see system administrator to resolve problem.	Check to see if the printer is configured correctly. Alternatively, the user can email form.
The form could not be saved: Dialog box displays and verifies that registration succeeded; however, the registration information cannot be recalled when updating registration in the future.	Check the user's home directory. Required action depends on the system's configuration.
You forgot your Solaris Solve login ID and password.	Send a mail message describing the problem to <code>SolarisSolve@sun.com</code> or see "How to Restart Solaris User Registration" on page 54
You want to restart the registration process.	"How to Restart Solaris User Registration" on page 54

## ▼ How to Restart Solaris User Registration

Use the following procedure to restart the Solaris User Registration process.

1. **Change to the `$HOME/.solregis` directory.**

```
% cd $HOME/.solregis
```

2. **Remove the `uprops` file.**

```
% rm uprops
```

3. **Restart the registration process.**

```
% /usr/dt/bin/solregis &
```



## ▼ How To Disable User Registration

Table 2-4 shows how to disable User Registration before and after installing Solaris software. Before disabling Solaris User Registration, Sun recommends that system administrators register for their organization.

TABLE 2-4 Ways to Disable User Registration

To Disable User Registration ...	You Can ...	For More Information See ...
Before Solaris software is installed	<ul style="list-style-type: none"><li>■ Deselect the SUNWsregu package (interactive installation)</li><li>■ Modify a custom JumpStart profile to not install the SUNWsregu package</li><li>■ Create and run a finish script that creates a file named <code>solregis</code> in the <code>/etc/default</code> directory on one or more systems with the following line in it: <code>DISABLE=1</code></li></ul>	<i>Solaris Advanced Installation Guide</i>  <code>solregis(1)</code>
After Solaris software is installed	<ul style="list-style-type: none"><li>■ Use the <code>pkgrm</code> command to remove the SUNWsregu package</li><li>■ Add the <code>solregis</code> file in the <code>/etc/default</code> directory (custom JumpStart installation only)</li></ul>	Chapter 17  <i>Solaris Advanced Installation Guide</i>  <code>solregis(1)</code>



## PART II Managing Server and Client Support

---

This part provides instructions for managing server and client support in the Solaris environment. This part contains these chapters.

Chapter 3	Provides a high-level overview about managing server and client support on a network. This chapter describes the different system types for which you can add support and guidelines for choosing a system type to use. It also describes what you can and can't do to manage system support with Solstice Host Manager.
Chapter 4	Provides step-by-step instructions for adding and maintaining server and client support by using Solstice Host Manager.



## Managing Server and Client Support (Overview)

---

This chapter describes managing server and client support on a network, and it provides overview information about each system configuration (referred to as a *system type*) supported in the Solaris environment. This chapter also includes guidelines for selecting the appropriate system type to meet your needs.

This is a list of the overview information in this chapter.

- “Where to Find Server and Client Tasks” on page 60
- “What Are Servers and Clients?” on page 60
- “What Does Support Mean?” on page 60
- “Overview of System Types” on page 61
- “Guidelines for Choosing System Types” on page 63
- “Tools for Managing Server and Client Support” on page 64
- “What You Can Do With Host Manager” on page 65
- “What You Can’t Do With Host Manager” on page 70

For step-by-step instructions about how to add and maintain server and client support, see Chapter 4.

For overview information on setting up a name service policy, see the *Solstice AdminSuite 2.3 Administration Guide*.

---

## Where to Find Server and Client Tasks

Use this reference to find step-by-step instructions for setting up server and client services.

- Chapter 4

---

## What Are Servers and Clients?

Systems on the network can usually be described as one of the following:

- **Server** – A system that provides services to other systems in its network. There are file servers, boot servers, database servers, license servers, print servers, installation servers, and even servers for particular applications. This chapter uses the term server to mean a system that provides file systems and installation software for other systems on the network.
- **Client** – A system that uses remote services from a server. Some clients have limited disk storage capacity, or perhaps none at all, and they have to rely on remote file systems from a server to function. Diskless, AutoClient™ and JavaStation™ systems are examples of this type of client.

Other clients may use remote services (such as installation software) from a server, but they don't rely on a server to function. A standalone system, which has its own hard disk containing the root (/), /usr, and /export/home file systems and swap space, is a good example of this type of client.

---

## What Does Support Mean?

Providing support for a system means providing software and services to help another system function. Support can include:

- Making a system known to the network (i.e., host name and ethernet address information)
- Providing installation services to remotely boot and install a system
- Providing operating system (OS) services to a system with limited or no disk space

## Overview of System Types

System types are basically defined by how they access the root (/) and /usr file systems, including the swap area. For example, standalone and server systems mount these file systems from a local disk, while other clients mount the file systems remotely, relying on servers to provide these services. Table 3-1 lists these and other differences for each system type.

TABLE 3-1 System Type Overview

System Type	Local File Systems	Local Swap?	Remote File Systems	Network Use	Relative Performance
Server	root (/) /usr /home /opt /export/home /export/root	Yes	– none –	high	high
Standalone System	root (/) /usr /export/home	Yes	– none –	low	high
Diskless Client	– none –	No	root (/) swap /usr /home	high	low
JavaStation	– none –	No	/home	low	high
AutoClient System	cached root (/) cached /usr	Yes	/var	low	high

## Servers

A server system has the following file systems:

- The root (/) and /usr file systems, plus swap space
- The /export, /export/swap, and /export/home file systems, which support client systems and provide home directories for users
- The /opt directory or file system for storing application software

Servers can also contain the following software to support other systems:

- Operating system (OS) services for diskless, JavaStation, or AutoClient systems that are running a different release or are a different platform than the server
- Solaris CD image and boot software for networked systems to perform remote installations
- JumpStart™ directory for networked systems to perform custom JumpStart installations

## Standalone Systems

A *networked standalone system* can share information with other systems in the network, but it could continue to function if detached from the network.

A standalone system can function autonomously because it has its own hard disk containing the root (/), /usr, and /export/home file systems and swap space. The standalone system thus has local access to operating system software, executables, virtual memory space, and user-created files.

---

**Note** - A standalone system requires sufficient disk space to hold the four necessary file systems.

---

A *non-networked standalone system* is a standalone system with all the characteristics listed above except it is not connected to a network.

## Diskless Clients

A *diskless client* has no disk and depends on a server for all its software and storage area. A diskless client remotely mounts its root (/), /usr, and /home file systems from a server.

A diskless client generates significant network traffic due to its continual need to procure operating system software and virtual memory space from across the network. A diskless client cannot operate if it is detached from the network or if its server malfunctions.



## JavaStation Client

The JavaStation™ is a client designed for zero administration. This client optimizes Java™; the JavaStation client takes full advantage of the network to deliver everything from Java applications and services to complete, integrated system and network management. The JavaStation has no local administration; booting, administration, and data storage are handled by servers.

## AutoClient Systems

An AutoClient system is nearly identical to a diskless client in terms of installation and administration. It has the following characteristics:

- Requires a minimum of a 100-Mbyte local disk for swapping and for caching its individual root (/) file system and the /usr file system from a server
- Can be set up so that it can continue to access its cache when the server is unavailable
- Relies on a server to access other file systems and software applications
- Contains no permanent data, making it a field replaceable unit (FRU)

---

**Note** - You must obtain a license for each AutoClient system you want to add to your network. See the *Solstice AdminSuite 2.3 Installation and Release Notes* for licensing information.

---

## Guidelines for Choosing System Types

Determining which system types are appropriate for your environment can be done by comparing each type based on the following characteristics:

- Centralized Administration
  - Can the system be treated as a field replaceable unit (FRU)? This means that a broken system can be quickly replaced with a new system without any lengthy backup/restore operations and no loss of system data.
  - Does the system need to be backed up? Large costs in terms of time and resources can be associated with backing up a large number of desktop systems.
  - Can the system's data be modified from a central server?
  - Can the system be installed from a centralized server, quickly and easily without handling the client system's hardware?
- Performance

- Does this configuration perform well in desktop usage?
- Does the addition of systems on a network affect the performance of other systems already on the network?
- Disk Usage
  - How much disk space is required to effectively deploy this configuration?

Table 3-2 describes how each system type scores in terms of each of these categories. A ranking of 1 is most efficient; a ranking of 4 is least efficient.

**TABLE 3-2** Comparison of System Types

System Type	Centralized Administration	Performance	Disk Usage
Standalone System	4	1	4
Diskless Client	1	4	1
AutoClient System	1	2	2
JavaStation Client	1	1	1

## Tools for Managing Server and Client Support

In previous Solaris releases, you may have used Administration Tool to manage server and client support. Starting with the Solaris 2.5 release and compatible versions, you must use the Solstice Host Manager tool, which offers ease of use and provides support for the following name services:

- NIS+ tables
- NIS maps
- Local `/etc` files

---

## What You Can Do With Host Manager

Host Manager is a graphical user interface that enables you to add and maintain server and client support on a network. With a name service like NIS+, you can manage system information in a centralized manner so that important system information, such as host names, does not have to be duplicated on every system in the network.

Host Manager enables you to:

- Add and modify support
- Update system types
- Convert system types
- Add and remove OS services
- Set up remote installation services
- Queue tasks

## Add and Maintain Support

Host Manager enables you to add and modify support for the following Solaris system types:

- Solaris AutoClient systems
- Solaris diskless clients
- Solaris standalone systems
- Solaris OS servers
- JavaStations (modify support only)

Table 3-3 describes the server-client configurations that are supported by the Solstice AdminSuite 2.3 release of Host Manager.

**TABLE 3-3** Supported Server-Client Configurations

If You Have A ...	You Can Add OS Services and Support For ...	For the Following Releases ...
x86 server running the Solaris 2.4 release and compatible versions	SPARC clients <sup>1</sup>	Solaris 2.3 release and compatible versions
	x86 clients	Solaris 2.4 release and compatible versions
SPARC server running the Solaris 2.3 release and compatible versions	SPARC clients <sup>1</sup>	SunOS 4.1 release and compatible versions, Solaris 2.3 release and compatible versions
	x86 clients	Solaris 2.4 release and compatible versions

1. AutoClient systems are only supported on the Solaris 2.4 release and compatible versions.

**Note** - The SunOS 4.1 release and compatible versions are only supported on SPARC systems with the Sun4, Sun4c, and Sun4m platform groups.

## Update System Types

Host Manager initially marks the system types of previously added systems as generic. However, you can choose Update System Types from the File menu to probe previously added systems and attempt to automatically determine their system types. If Host Manager cannot determine the system type (for example, the system is not running the Solaris software) the systems will stay marked as generic.

**Note** - Previously added systems running Solaris 2.5 release or compatible versions must also have the Solstice AdminSuite software installed for Host Manager to automatically update their system type.

The system type information is stored in the `bootparams` file in the local `/etc` files or a name service database. Host Manager will either modify an existing

`bootparams` entry or add a new one such as the following for a Solaris standalone system named `mars`:

```
mars boottype=:st
```

## Convert System Types

Host Manager enables you to convert one system type to another. Table 3–4 shows what conversions you can make.

**TABLE 3–4** System Type Conversions

You Can Convert A ...	To A ...
Standalone System	AutoClient System or OS Server
Dataless System	AutoClient System or OS Server
AutoClient System	Standalone System
Generic System	Standalone System, or AutoClient System, or OS Server

You can add Solaris 7 or compatible OS services during the standalone system to OS server conversion.

## Add OS Services

A Solaris OS server is a server that provides operating system (OS) services to support client systems. By using Host Manager, you can add support for an OS server or convert a standalone system to an OS server.

For each platform group and Solaris release that you want to support, you must add the particular OS service to the OS server. For example, if you want to support SPARC Sun4m systems running the Solaris 7 release, you must add Sun4m/Solaris 7 OS services to the OS server. You would also still need to add OS services to support SPARC Sun4c systems or x86 systems running the Solaris 7 release, because they are different platform groups.

You must have access to the appropriate Solaris CD image to add OS services.

---

**Note** - Although Host Manager enables you to add support for diskless clients running the SunOS 4.0 and compatible releases, you cannot add SunOS 4.0 and compatible OS services using Host Manager. You must use the `install4x` commands to add OS services to an OS server, and then use Host Manager to add support for the SunOS 4.0 and compatible client.

---

## Adding OS Services to a Server When the OS Services Have Been Patched

When adding OS services to an OS server, you may see error messages saying that you have inconsistent versions of the OS running on the server and the OS that you are trying to add. This message occurs when the installed version of the OS has packages that were previously patched and the OS services being added do not have those packages patched (because the patches have been integrated into the packages).

For example, you may have a server that is running the Solaris 7 release or compatible versions; you may also have additional OS services loaded on this server, including the Solaris 2.6 SPARC Sun4m OS services that have been patched. If you try to add the Solaris 2.6 SPARC Sun4c OS services from a CD-ROM to this server, you could get the following error message

```
Error: inconsistent
revision, installed package appears to have been patched resulting
in it being different than the package on your media. You will need
to backout all patches that patch this package before retrying the
add OS service option.
```

## Remove OS Services

OS services can be removed from an OS server using Host Manager. For instance, if you no longer want to support SPARC Sun4m systems running the Solaris 7 or compatible versions, you can remove these OS services from the server using Host Manager.

## Set Up Remote Installation Services

Host Manager enables you to set up systems to provide Solaris installation services for other systems on the network. You can set up the following types of installation services on a system:

- An install server – A system on the network that provides a Solaris CD image (either from a CD-ROM drive or the copy on the hard disk) for other systems to install from.
- A boot server – A system that provides boot information to other systems on the network. The boot server and the install server are usually the same system.
- A profile server – A system that contains Jumpstart files for systems to perform a custom JumpStart installation.

---

**Note** - A boot server and install server are typically the same system. However, if the system to be installed is on a different subnet than the install server, a boot server is required on that subnet.

---

## Queue Tasks

Host Manager enables you to queue tasks such as converting system types and adding OS services. Since these tasks may require several minutes to process, Host Manager enables you to set up tasks to be performed without requiring you to wait for each task to be completed. After setting up the tasks, choose Save Changes from the File menu. Host Manager's progress is displayed in the message bar located at the bottom of the window as each task is processed.

## Set Root Passwords

When adding a Solstice AutoClient or Solaris diskless client using Host Manager, you can now set the root password using the GUI just as you do when setting the group or user password.

## Enable Scripts

When you add a Solstice AutoClient using Host Manager, you have the option to enable scripts to run on the server before or after you add the AutoClient to the server, or run on the client before or after the cache is configured on the AutoClient.

These scripts are those that you have created to customize the addition or deletion of AutoClient systems; these scripts need to be located in the `/opt/SUNWadmd/Scripts` directory in order for the AdminSuite software to read them.

## Add a Multihomed Host

Host Manager enables you to add a multihomed host alias for servers with multiple network interfaces. For instance, if a server has more than one IP address because it is on multiple networks, it is considered a multihomed host. With Host Manager, you can specify more than one IP address for a host to make it a multihomed host.

---

## What You Can't Do With Host Manager

Table 3-5 shows the limitations of Host Manager and their suggested workarounds.

**TABLE 3-5** Host Manager Limitations and Workarounds

Limitation	Workaround
Host Manager cannot automatically recognize all previously added system types.	Use the Update System Type option from the File menu the first time you use Host Manager. This option will probe systems on the network and attempt to identify their system types.
Host Manager can't add SunOS 4.1 or compatible services to an OS server.	Mount a SunOS 4.1 or compatible CD image and add OS services by using the <code>install4x</code> command.
Host Manager can't provide remote installation services for systems running the SunOS 4.1 release or compatible versions.	Install systems running the SunOS 4.1 or compatible versions from the local CD-ROM drive.
Host Manager does not enable you to install patches on existing clients and servers. (However, if you have used the <code>admclientpatch</code> command to set up a patch spool directory, Host Manager will reference this spool directory and add appropriate patches for all new hosts.)	Use the <code>admclientpatch</code> command to set up a patch spool directory and to update existing servers and clients with the latest patches.



---

## Running Host Manager as Superuser

When running host manager as superuser, you will see slightly different behavior. The following list describes the limitations of running host manager as superuser.

- When Host Manager is started as superuser, you will see a dialog box describing the constraints that you will encounter.
- The name service selection dialog is forced to the local host and the text field is not editable.
- When adding a host, the file server is forced to the local host and can not be edited.
- When Remote Install is enabled in the Add, Modify, or Convert windows, the boot server is forced to the local host and can not be edited; also, the Install Server is forced to the local host and can not be edited.



## Managing Server and Client Support (Tasks)

---

This chapter describes how to set up and maintain server and client support using the Solstice Host Manager.

This is a list of the step-by-step instructions in this chapter.

- “How to Start Solstice Host Manager” on page 75
- “How to Update System Types” on page 76
- “How to Set Defaults for Adding Support” on page 77
- “How to Add Support for a Standalone System or OS Server” on page 77
- “How to Convert a System to an OS Server” on page 80
- “How to Add SunOS 4.0 and Compatible OS Services to an OS Server” on page 82
- “How to Add Solaris 7 OS Services to an OS Server” on page 86
- “How to Add Support for an AutoClient System” on page 88
- “How to Add Support for a Diskless Client” on page 90
- “How to Modify Support for a System” on page 94
- “How to Delete Support for a System” on page 94

For overview information about managing server and client support, see Chapter 3. For more information on using Solstice Host Manager, see the *Solstice AdminSuite 2.3 Administration Guide*.

# Adding Server and Client Support Task Map

**TABLE 4-1** Adding Server and Client Support Task Map

Task	Description	For Instructions, Go To
1. Update System Types	<i>Optional.</i> Make sure Host Manager recognizes all the previously added system types.	"How to Update System Types" on page 76
2. Set Defaults for Adding Support	<i>Optional.</i> Before you add support for several clients, set up defaults for the Add window by choosing Set Defaults from the Host Manager's Edit menu.	"How to Set Defaults for Adding Support" on page 77
3. Add Support for a Standalone System	Add support for a standalone system by choosing Add from the Host Manager's Edit menu. You can also convert a AutoClient system or generic system to a standalone system by choosing Convert to Standalone from the Edit menu.	"How to Add Support for a Standalone System or OS Server" on page 77
4. Add Support for an OS Server	<p><i>Add Support for an OS Server</i></p> <p>Add support for an OS server by choosing Add from the Host Manager's Edit menu.</p> <p><i>Convert a Standalone System to an OS Server</i></p> <p>Convert a standalone system to an OS server by choosing Convert from the Host Manager's Edit menu. You can add Solaris 7 OS services during the conversion.</p>	<p>"How to Add Support for a Standalone System or OS Server" on page 77</p> <p>"How to Convert a System to an OS Server" on page 80</p>
5. Add OS Services to an OS Server	<p><i>Add SunOS 4.0 and Compatible OS Services</i></p> <p>If you need to add support for SunOS 4.0 and compatible diskless clients, an OS server must have the appropriate SunOS 4.x services added.</p>	"How to Add SunOS 4.0 and Compatible OS Services to an OS Server" on page 82

**TABLE 4-1** Adding Server and Client Support Task Map *(continued)*

Task	Description	For Instructions, Go To
	<p><i>Add Solaris 7 and Compatible OS Services.</i></p> <p>If you need to add support for Solaris 7 and compatible diskless or AutoClient systems, an OS server must have the appropriate Solaris 7 and compatible services added.</p>	<p>“How to Add Solaris 7 OS Services to an OS Server” on page 86</p>
6. Add Support for Client Systems	<p><i>Add Support for an AutoClient System</i></p> <p>Add support for an AutoClient system by choosing Add from the Host Manager’s Edit menu.</p> <p><i>Add Support for a Diskless Client</i></p> <p>Add support for a diskless client by choosing Add from the Host Manager’s Edit menu.</p>	<p>“How to Add Support for an AutoClient System” on page 88</p> <p>“How to Add Support for a Diskless Client” on page 90</p>

## ▼ How to Start Solstice Host Manager

### 1. Verify that the following prerequisites are met. To use Solstice Host Manager, you must have:

- Solstice AdminSuite installed.
- A bit-mapped display monitor. The Solstice AdminSuite software can be used only on a system with a console that has a bit-mapped screen such as a standard display monitor that comes with a Sun workstation.
- If you want to perform administration tasks on a system with an ASCII terminal as the console, use Solaris commands instead.
- An X Window system installed and running.
- Superuser (root) privilege or membership in the `sysadmin` group (group 14) and the required access privileges for managing the NIS or NIS+ database.

---

**Note** - If your name service is NIS+, you must be a member of the NIS+ admin group.

---

### 2. Start the Solstice Launcher.

```
$ solstice &
```

The Solstice Launcher Menu is displayed.

3. Click on the Host Manager icon.




## Host Manager

The Load window is displayed.

4. Select the name service used in your network.
5. Check that the domain or host name is correct.  
If not, type the domain or host name you need to access.
6. Click on OK.  
The Solstice Host Manager main window is displayed.

### Example—Host Manager Main Window



## ▼ How to Update System Types

This procedure attempts to determine the system types for systems marked as generic.

1. **Start Solstice Host Manager from the Solstice Launcher and select the name service, if not done already.**  
See “How to Start Solstice Host Manager” on page 75 for more information.
2. **Select Update System Types from the File menu on the Solstice Host Manager Window.**  
The Update Systems Types window is displayed.
3. **Click on Update to update the systems marked as generic.**
4. **Verify the system has been converted to generic in the Solstice Host Manager Window.**

## ▼ How to Set Defaults for Adding Support

1. **Start Solstice Host Manager from the Solstice Launcher and select the name service, if not done already.**  
See “How to Start Solstice Host Manager” on page 75 for more information.
2. **Choose Set Defaults from the Edit menu.**  
The Set Defaults window is displayed.
3. **Fill in the Set Defaults window.**  
The defaults you select will be the initial defaults values in the Add window. If you need information to complete a field, click on the Help button to see field definitions for this window.
4. **Click on OK.**

## ▼ How to Add Support for a Standalone System or OS Server

The high-level steps in this procedure are:

- Adding information about the system
  - (Optional) Setting up remote install capabilities for the system
  - (Optional) Installing the system
1. **Start Solstice Host Manager from the Solstice Launcher and select the name service, if not done already.**

See “How to Start Solstice Host Manager” on page 75 for more information.

**2. Select Add from the Edit menu on the Solstice Host Manager Window.**

The Add window is displayed.

**3. Fill in the system information, selecting Solaris Standalone or OS Server as the system type.**

The system information includes all the fields from the host name through the timezone. If you need information to complete a field, click on the Help button to see field definitions for this window.

**4. If you want to set up remote install capabilities for the system, continue to Step 5 on page 78. If not, skip to Step 10 on page 79.**

**5. Click on Enable Remote Install.**

**6. Select an Install Server.**

The Install Server defaults to the current host. Select Other from the Install Server menu to specify another host as the install server.

**7. Click on Set Path to identify the path to the Solaris CD image on the install server.**

If the install server is a remote system, note that it must be minimally set up as a managed system.

If You Are Using ...	And ...	Then Enter the Path ...
The Solaris CD as the Solaris CD image	The Solaris CD is managed by Volume Management	/cdrom/cdrom0 or /cdrom/cdrom0/s0 or /cdrom/cdrom0/s2
	The Solaris CD is not managed by Volume Management	Where you mounted the Solaris CD
A copy of the Solaris CD on the install server's hard disk (by using <code>setup_install_server</code> )		To the Solaris CD image

**8. Select the system's architecture type and OS release from the OS Release menu.**

The architecture type must match the system's architecture and the OS release should match the Solaris release you want to remotely install on the system.

**9. If necessary, specify a boot server or profile server.**



To specify another server other than the default, select Other from the menu. Select a Profile Server from the Profile Server pull-down menu. You must also specify a path to the boot software on the boot server or the custom JumpStart directory on the profile server.

To set up the other components of a custom JumpStart installation and preconfiguring network and system information, see *Solaris Advanced Installation Guide*.

**10. Click on OK on the Add window.**

**11. Select Save Changes from the File menu to add support for the standalone system or OS server.**

The standalone system or OS server is displayed in the Host Manager main window.

**12. Verify the OS server information is correct in the Host Manager main window.**

**13. (Optional) Boot and install the standalone system or OS server.**

For more information about booting and installing, see *Solaris Advanced Installation Guide*.


---

**Note** - If you are installing an OS server, you must allocate space in `/export` and `/export/swap` for the desired number of clients.

---

## Example—Completed Host Manager Add Window for a Standalone System

The following example shows a completed Add window for the standalone system `venus`.



The image shows a 'Host Manager: Add' dialog box with the following fields and options:

- Host Name:** venus
- IP Address:** 129.152.225.2
- Ethernet Address:** 8:0:20:b:40:e9
- System Type:** Solaris Standalone
- Timezone Region:** United States
- Timezone:** Mountain
- Remote Install:** ☐ Enable Remote Install
- Install Server:** krypton ☐ Set Path...
- OS Release:** ☐
- Boot Server:** none ☐
- Profile Server:** none ☐

Buttons at the bottom: OK, Apply, Reset, Cancel, Help.

## Where to Go From Here

If you want to add OS services after you install an OS server, see “How to Add Solaris 7 OS Services to an OS Server” on page 86.

## ▼ How to Convert a System to an OS Server

1. **Start Solstice Host Manager from the Solstice Launcher and select the name service, if not done already.**  
See “How to Start Solstice Host Manager” on page 75 for more information.
2. **Select a host entry from Solstice Host Manager’s main window.**  
You can convert a standalone system and generic system to an OS server.
3. **Select Convert to OS Server from the Edit Menu.**

The Convert window is displayed, and the selected system is displayed in the host name field.

**4. Click on the Add button in the OS Services window to add services.**

**5. Click on Set Path to identify the path to the Solaris CD image from which to add the client services.**

The Install Server defaults to the current host. Select Other from the Install Server menu to specify another host as the install server. Note that a remote system must be minimally set up as a managed system.

If You Are Using ...	And ...	Then Enter the Path ...
The Solaris CD as the Solaris CD image	The Solaris CD is managed by Volume Management	/cdrom/cdrom0/s0 or /cdrom/cdrom0/s2 on SPARC platforms, /cdrom/cdrom0 on x86 platforms
	The Solaris CD is not managed by Volume Management	Where you mounted the Solaris CD
A copy of the Solaris CD on the Install Server's hard disk (by using <code>setup_install_server</code> )		Where you specified <code>setup_install_server</code> to copy the Solaris CD

**6. Specify the type of services you want to add and click on Add.**

The OS service is added to the OS Services list and marked with a plus sign (+), which means it will be added when you save changes. You can use the Delete button to delete an OS service from the list before you save changes.


**7. Click on OK on the Convert window.**

**8. Select Save Changes from the File menu to convert the system to an OS Server.**

The converted system is displayed as an OS server in the Host Manager main window.

**9. Verify the host type has been updated in the Host Manager main window.**

## Example—Completed Host Manager Convert Window



## ▼ How to Add SunOS 4.0 and Compatible OS Services to an OS Server

**Note** - You cannot add SunOS 4.0 and compatible services to x86 OS servers.

The high-level steps in this procedure are:

- Determining the OS server to which you want to add SunOS 4.0 and compatible OS services for diskless clients
  - Installing the required SunOS 4.0 and compatible release software (install4x command)
1. **Log in as superuser on the OS server to which you want to add SunOS 4.0 and compatible OS services for diskless clients.**

2. **Insert the Solstice AdminSuite 2.3 CD into your CD-ROM drive.**  
This step assumes that your system is running Volume Management.

3. **Change directory to the location of the software.**

```
# cd /cdrom/Solstice_sysmgt_2.3/4.x
```

4. **Install the SunOS 4.0 and compatible heterogeneous install software.**

```
# pkgadd -d `pwd` SUNWhinst
```

**5. Eject the Solstice AdminSuite 2.3 CD.**

```
# cd
# eject cd
```

**6. Insert the SunOS 4.0 or similar release CD into your CD-ROM drive.**

This step assumes that your system is running Volume Management, and the CD-ROM drive is directly attached to the server. Volume Management automatically mounts the CD directory on /cdrom/volume1/s0.

**7. Start the SunOS 4.0/4.1 release software installation program.**

```
# /usr/sbin/install4x -m /cdrom/volume1/s0 -e /export
```

The main menu is displayed.

```
*** 4.1* Install Main Menu ***
Choose an Architecture (then select modules to load):

Modules
                                         Loaded   Selected
[a] sun4.sun4c.sunos.4.1.2              0         0
[b] sun4.sun4c.sunos.4.1.2              0         0
[c] sun4.sun4m.sunos.4.1.2              0         0

    or begin the loading process for all selected modules:

[L] Load selected modules

or abort without loading any modules:

[Q] Quit without loading

                                         +-----+
                                         | Disk Usage: |
                                         |   0K Selected |
                                         | 53634K Free  |
                                         +-----+

Type any bracketed letter to select that function.

Type ? for help.
```

**8. On the main menu, specify the architecture you want to support by typing the associated character that is shown in brackets.**

The Module Selection menu is displayed.

```
Select sun4.sun4c.sunos.4.1.2 modules:
+[a] R proto root.....240K | [o] User_Diag.....6352K
+[b] R usr.....26240K | [p] Manual.....7456K
+[c] R Kvm.....4832K |+[q] D TLI..... 48K
+[d] R Install.....936K | [r] D RFS..... 912K
[e] D Networking.....1040K | [s] D Debugging.....2928K
[f] D System_V.....4008K | [t] SunView_Programmers...1840K
[g] D Sys.....5288K | [u] Shlib_Custom.....1376K
[h] C SunView_Users.....2664K | [v] Graphics.....1784K
[i] SunView_Demo.....512K |+[w] uucp.....608K+
[j] Text.....712K |+[x] Games..... 3136K
[k] Demo.....4264K | [y] Versatec.....5960K
[l] C OpenWindows_Users...25936K | [z] Security.....312K
[m] C OpenWindows_Demo....4288K | [A] OpenWindows_Programmers.10200K
[n] C OpenWindows_Fonts ...7840K |

Module      + = already loaded      R = Required      C= Common
Legend:    ** = selected for loading  D = Desirable    Others are optional
Select [a-A] or a Quick-Pick Option:

[1] All Required Modules  [4] All Optional Modules  | Disk Usage: |
[2] All Desirable Modules[5] All Modules  | 0K Selected |
[3] All Common Modules   | 53634K Free |
or [D] (done) to return to the main screen  +-----+
```

### 9. Select modules to load by typing the associated character that is shown in brackets.

The Module Selection screen readily enables you to pick groups of modules to be loaded. When you enter a 1, it marks all required modules for loading. When you enter a 2, it marks all recommended modules. When you enter a 3, it marks all commonly loaded modules. When you enter a 4, it marks all optional modules. When you enter a 5, it marks all modules shown on the Module Selection screen.

### 10. Return to the main menu by typing D.

The main menu is displayed.

```
*** 4.1* Install Main Menu ***

Choose an Architecture (then select modules to load):

Modules
Loaded  Selected
[a] sun4.sun4c.sunos.4.1.2      0      4
[b] sun4.sun4c.sunos.4.1.2      0      3
[c] sun4.sun4m.sunos.4.1.2      0      1
```

(continued)

(Continuation)

```
or begin the loading process for all selected modules:

[L] Load selected modules

or abort without loading any modules:

[Q] Quit without loading
```

Disk Usage:
0K Selected
53634K Free

```
Type any bracketed letter to select that function.
Type ? for help.
```

**11. Type L to install the software.**

The modules you previously selected are installed.

```
Installing module 'proto root' [size: 248K]
      in directory /export/exec/proto.root.sunos.4.1.2 ...

Updating server databases ...

Press any key to continue:
```

**12. After the modules are installed, press any key to return to the main menu.**

The loaded modules are displayed in the main menu.

**13. If you want to add support for other architectures, repeat Step 8 on page 83 through Step 11 on page 85. Otherwise, type Q to exit.**

---

**Note** - There is no command-line equivalent for adding SunOS 4.0 or compatible services to an OS server.

---

**14. Verify the SunOS 4.0 or compatible services have been added by listing the contents of the /export/SunOS\_4.x directory.**

## Where to Go From Here

If you want to add SunOS 4.0 or similar support for a diskless client, see “How to Add Support for a Diskless Client” on page 90.

## ▼ How to Add Solaris 7 OS Services to an OS Server

---

**Note** - The name of this release is Solaris 7 but code and path or package path names may use Solaris 2.7 or SunOS 5.7. Always follow the code or path as it is written.

---

1. **Start Solstice Host Manager from the Solstice Launcher and select the name service, if not done already.**

See “How to Start Solstice Host Manager” on page 75 for more information.

2. **Select an OS server to modify from the Host Manager main window.**

3. **Select Modify from the Edit menu on the Solstice Host Manager Window.**  
The Modify window is displayed.

4. **Click on the Add button in the OS Services window to add services.**

5. **Click on Set Path to identify the path to the Solaris CD image from which to add the client services.**

The Install Server defaults to the current host. Select Other from the Install Server menu to specify another host as the install server. Note that a remote system must be minimally set up as a managed system.

If You Are Using ...	And ...	Then Enter the Path ...
The Solaris CD as the Solaris CD image	The Solaris CD is managed by Volume Management	/cdrom/cdrom0/s0 or /cdrom/cdrom0/s2 on SPARC platforms, /cdrom/cdrom0 on x86 platforms
	The Solaris CD is not managed by Volume Management	Where you mounted the Solaris CD
A copy of the Solaris CD on the Install Server's hard disk (by using <code>setup_install_server</code> )		Where you specified <code>setup_install_server</code> to copy the Solaris CD

6. **Specify the type of services you want to add and click on Add.**

The OS service is added to the OS Services list and marked with a plus sign (+), which means it will be added when you save changes. You can use the Delete button to delete an OS service from the list before you save changes.



7. Click on OK on the Add window.
8. Select Save Changes from the File menu to add services.
9. Verify that the OS services directories are available by listing the contents of the `/export/Solaris_2.7` directory.

### Example—Completed Add OS Services Window

The following example adds the Solaris 2.7 SPARC sun4m service to the OS server venus.

The image shows a dialog box titled "Host Manager: Convert". It contains several configuration fields and buttons. The "Host Name" field is set to "venus". The "System Type" is "Solaris OS Server". The "Timezone Region" is "United States" and the "Timezone" is "Mountain". The "Remote Install" checkbox is checked, labeled "Enable Remote Install". The "Install Server" is "krypton" with a "Set Path..." button next to it. The "OS Release" is "sparc sun4c Solaris 2.7". The "Boot Server" and "Profile Server" are both set to "none". The "OS Services" list contains one entry: "+ sparc sun4m Solaris 2.7". Below this list are "Add..." and "Delete" buttons. At the bottom of the dialog are "OK", "Reset", "Cancel", and "Help" buttons.

Host Name:	venus
System Type:	Solaris OS Server
Timezone Region:	United States
Timezone:	Mountain
Remote Install:	<input checked="" type="checkbox"/> Enable Remote Install
Install Server:	krypton <input data-bbox="802 1087 911 1121" type="button" value="Set Path..."/>
OS Release:	sparc sun4c Solaris 2.7
Boot Server:	none
Profile Server:	none
OS Services:	+ sparc sun4m Solaris 2.7

## ▼ How to Add Support for an AutoClient System

---

**Note** - This procedure assumes that the AutoClient server is already set up as an OS server and is already installed with the kernel architectures of the AutoClient system(s) to be added. For information on adding an OS Server or converting an existing system to an OS Server, see the online help or the *Solstice AdminSuite 2.3 Administration Guide*.

---

1. **Start Host Manager from the Solstice Launcher and select the name service, if not done already.**

See "How to Start Solstice Host Manager" on page 75 for more information.

2. **Choose Add from the Edit menu. The Add window is displayed. Note that the default system type is Solaris Standalone.**

3. **Choose Solstice AutoClient from the System Type menu.**

The Add window for a Solstice AutoClient system is displayed.

4. **Fill in the system information for the AutoClient system.**

5. **Click on OK after entering the required information.**

If you have not enabled licensing for the Solstice AutoClient feature, you will see a message saying that the software was unable to check out a license. For information on enabling licensing, see Solstice AutoClient 2.1 Installation and Product Notes.

The AutoClient system becomes part of the list of AutoClient systems to add, and it is displayed on the Host Manager main window with a plus sign (+) next to it. The + means that the system is a "pending add."

6. **Repeat Step 2 through Step 5 to add subsequent AutoClient systems to your "batch" of pending changes.**

The "Total Changes Pending" status will be incremented each time you add a system.

7. **Choose Save Changes from the File menu when you are ready to confirm addition of all the AutoClient systems listed in the window.**

The Saving Changes message window appears. All of the AutoClient systems are added when you choose Save Changes from the File menu.

Adding each client takes several minutes, depending on server speed, current load, and the number and type of patches that will be automatically added.

As each AutoClient system is successfully added (as shown in the Saving Changes window), its corresponding entry no longer appears as a pending add in the Host Manager main window (that is, the + no longer appears next to the host name).



---

**Caution** - For the AutoClient system to work properly, it needs superuser access to its `/export/root` directory. If Host Manager displays a message that the `/export` directory is already shared and has different share options than required, you need to allow superuser access to the client root area before the AutoClient system will function properly. The access mode for the client root is normally `rw=clientname, root=clientname`.

If Host Manager displays a message that the `/usr` directory is already shared, it is because it tried to share `/usr` read-only. If you have it shared with read-write permissions, then `/usr` is set up correctly, and you do not have to make any modifications.

---

**8. Boot your AutoClient system(s) from the network.**

For more information about booting your AutoClient systems, see *Solstice AutoClient 2.1 Administration Guide*.

**9. Provide system configuration information for the AutoClient system during the initial boot process, if prompted.**

**10. Create a superuser password when prompted.**

## Example—Completed Host Manager Add Window for an AutoClient System

The following example shows a completed Add window for the Solstice AutoClient system `mars`.

**Host Manager: Add**

Host Name:

IP Address:

Ethernet Address:

System Type:

Timezone Region:

Timezone:

File Server:

OS Release:

Root Path:

Swap Size:  megabytes

Disk Config:

Disconnectable: ☐ Enable Disconnectability

Script Features: ☐ Enable Scripts ...

## ▼ How to Add Support for a Diskless Client

The high-level steps in this procedure are:

- Adding system information about the diskless client
- Selecting OS services for the diskless client
- Booting the diskless client

---

**Note** - This procedure assumes the system providing the services (the file server) has already been configured as an OS server.

---

1. **Start Solstice Host Manager from the Solstice Launcher and select the name service, if not done already.**

See “How to Start Solstice Host Manager” on page 75 for more information.

**2. Select Add from the Edit menu on the Solstice Host Manager main window.**

The Add window is displayed.

**3. Fill in the system information, selecting Solaris Diskless as the system type.**

The system information includes all the fields from the host name through the time zone. If you need information to complete a field, click on the Help button to see field definitions for this window.

**4. Select a File Server.**

The File Server defaults to the current host. Select Other from the Install Server menu to specify another host as the install server.

**5. Select the client's architecture type and the OS release from the OS Release menu.**

The architecture type must match the diskless client's architecture, and the OS release should match the Solaris release you want the diskless client to run.

**6. Identify the system's root path, swap path, and swap size.**

**7. Click on OK on the Add window.**

**8. Select Save Changes from the File menu to add support for the diskless client.**

The diskless client is displayed in the Host Manager main window. It takes several minutes to add the diskless client support, particularly to create the system's root and swap areas and apply any applicable patches with the `admclientpatch` command.



---

**Caution** - For the diskless client to work properly, it needs superuser access to its `/export/root` directory. If Host Manager displays a message that the `/export` directory is already shared and has different share options than required, you need to allow superuser access to the client root area before the diskless client will function properly. The access mode for the client root is normally `rw=clientname, root=clientname`.

If Host Manager displays a message that the `/usr` directory is already shared, it is because it tried to share `/usr` read-only. If you have it shared with read-write permissions, then `/usr` is set up correctly, and you do not have to make any modifications.

---

**9. Verify that the system has been added as a diskless client in the Host Manager Main Window.**

**10. Boot the diskless client.**

**11. Provide the following system configuration information for the diskless client during the initial boot process, if prompted.**

- Geographic region
- Time zone
- Date and time

**12. Create a superuser password when prompted.**

### **Example—Completed Host Manager Add Window for a Diskless Client**

The following example shows a completed Add window for the diskless client `neptune`.

**Host Manager: Add**

Host Name:

IP Address:

Ethernet Address:

System Type:

Timezone Region:

Timezone:

File Server:

OS Release:

Root Path:

Swap Path:

Swap Size:  megabytes

Terminal Type:

---

## Maintaining Server and Client Support Task Map

**TABLE 4-2** Maintaining Server and Client Support Task Map

<b>Task</b>	<b>Description</b>	<b>For Instructions, Go To</b>
1. Modify Support for a System	Modify support for a system by choosing Modify from the Host Manager's Edit menu.	"How to Modify Support for a System" on page 94
2. Delete Support for a System	Delete support for a system by choosing Delete from the Host Manager's Edit menu.	"How to Delete Support for a System" on page 94

## ▼ How to Modify Support for a System

1. **Start Host Manager from the Solstice Launcher and select the name service, if not done already.**  
See "How to Start Solstice Host Manager" on page 75 for more information.
2. **Select a system entry to modify from the Host Manager main window.**
3. **Choose Modify from the Edit menu.**  
The Modify window contains the selected system entry.
4. **Modify support for the system.**  
If you need information to change a field, click on the Help button to see field definitions for this window.
5. **Click on OK on the Modify window.**
6. **Select Save Changes from the File menu to modify support for the system.**
7. **Verify that the system entry has been modified in the Host Manager main window.**

## ▼ How to Delete Support for a System

1. **Start Solstice Host Manager from the Solstice Launcher and select the name service, if not done already.**  
See "How to Start Solstice Host Manager" on page 75 for more information.
2. **Select a system entry to delete from the Solstice Host Manager main window.**



3. **Select Delete from the Edit menu.**  
A window is displayed asking you to confirm the deletion.
4. **Click on OK.**
5. **Select Save Changes from the File menu to delete support for the system.**  
The system entry is deleted from the Host Manager main window.
6. **Verify that the system entry is deleted from the Host Manager main window.**

## Using the Host Manager Command-Line Interface to Automate Setup Tasks

Using the Host Manager command-line equivalents allows you to automate many of the setup tasks associated with creating new diskless and AutoClient systems. This automation is similar to what can be done when using the JumpStart product to install Solaris on standalone systems. By writing your own shell scripts and using the command-line equivalents, you can automatically customize the client environment in one operation.

Table 4-3 summarizes the equivalent Host Manager commands that can be used instead of the Solstice AdminSuite to perform administration tasks.

**TABLE 4-3** Solstice AdminSuite Command Line Equivalents

The Command ...	Is Used To ...	See /opt/SUNWadm/2.x/ man/...
<code>admhostmod -x type=<i>type</i> <i>host</i></code>	Update system types marked as generic	<code>admhostmod</code>
<code>admhostadd -D -x [fileserv=<i>server</i>] [-x root=<i>directory</i>] [-x swap=<i>swap_file</i>] [-x swapsize=<i>size</i>] [-x os=<i>version</i>] [-x ns=NIS+ NIS NONE] [-x domain=<i>domain</i>] rhost=<i>host</i>]</code>	Set up defaults for adding client support	<code>admhostadd</code>

**TABLE 4-3** Solstice AdminSuite Command Line Equivalents *(continued)*

The Command ...	Is Used To ...	See /opt/SUNWadm/2.x/ man/...
<code>admhostadd -i <i>ip_address</i> -e <i>ethernet_addr</i> [-x type= <i>type</i>] [-x tz=<i>timezone</i>] [-x install=Y N ] [-x installpath=<i>server</i>:/ <i>path</i>] <i>host</i></code>	Add a system and enable a network installation (optional)	<code>admhostadd</code>
<code>admhostmod -x type=OS_SERVER <i>host</i></code>	Convert a standalone system to an OS server	<code>admhostmod</code>
<code>admhostmod -x mediapath=<i>server</i>:/<i>path</i> -x platform=<i>platform</i> <i>host</i></code>	Add OS services to an OS server	<code>admhostmod</code>
<code>admhostdel [ -x ns=NIS+ NIS NONE ]  [ -x domain=<i>domain</i> rhost=<i>host</i> ... ]<i>host</i> ...</code>	Delete an existing system or OS server	<code>admhostdel</code>

## PART III Shutting Down and Booting a System

---

This part provides instructions for shutting down and booting systems running the Solaris release. This part contains these chapters.

Chapter 5	Provides an overview and guidelines for shutting down and booting a system.
Chapter 6	Provides information about run levels and boot files.
Chapter 7	Provides step-by-step procedures for shutting down a system.
Chapter 8	Provides step-by-step procedures for booting a SPARC system.
Chapter 9	Provides step-by-step procedures for booting an x86 system.
Chapter 10	Provides a high-level overview of the boot process including a description of the platform-specific hardware used to boot SPARC and x86 systems.



## Shutting Down and Booting a System (Overview)

---

This chapter provides guidelines for shutting down and booting a system. The Solaris software environment is designed to run continuously so that electronic mail and network resources are available to users. Occasionally, it is necessary to shut down or reboot a system because of a system configuration change, a scheduled maintenance event, or a power outage.

This is a list of overview information in this chapter.

- “What’s New in Shutting Down and Booting a System?” on page 99
- “Where to Find Shutting Down and Booting Tasks” on page 100
- “Terminology” on page 100
- “Guidelines for Shutting Down a System” on page 101
- “Guidelines for Booting a System” on page 101
- “Performing a Reconfiguration Boot” on page 102
- “When to Shut Down a System” on page 102
- “When to Boot a System” on page 104

---

### What’s New in Shutting Down and Booting a System?

This section describes new features related to shutting down and booting a system in the Solaris 7 release.

## Bringing a System to Run Level S (Single-User Mode)

Bug ID 1154696 has been fixed in the Solaris 7 release. This means that you can cleanly bring your system down to run level S (or single-user mode) by using the `shutdown -s` or the `init -s` command. The `inittab` file and the `rc` scripts in the `/etc/init.d` directory and the `/etc/rcn.d` directories have been modified to ensure system run level transitions are made cleanly and efficiently.

## Booting a System Running the 32-bit or 64-bit Solaris 7 Operating Environment

See “Troubleshooting 64-bit Solaris Boot Problems” on page 633 for information on booting a system running the 32-bit or 64-bit Solaris 7 operating environment.

---

## Where to Find Shutting Down and Booting Tasks

Use these references to find step-by-step instructions for shutting down and booting a system.

- Chapter 7
- Chapter 8
- Chapter 9

---

## Terminology

This section describes the terminology used in shutting down and booting a system.

- **Run levels and init states** – A *run level* is a letter or digit representing a system state in which a particular set of system services are available. The system is always running in one of a set of well-defined run levels. Run levels are also referred to as *init states* because the `init` process is used to perform transitions between run levels. System administrators use the `init(1M)` command to initiate a run-level transition. This book refers to init states as run levels.
- **Boot Types** – A *boot type* describes how a system is booted. Different boot types include:

- Interactive boot – You are prompted to provide information about how the system is booted, such as the kernel and device path name.
- Reconfiguration boot – The system is reconfigured to support newly added hardware or new pseudo devices.
- Recovery boot – The system is hung or an invalid entry is prohibiting the system from booting successfully or from allowing users to log in.

---

## Guidelines for Shutting Down a System

Keep the following in mind when shutting down a system:

- Use the `init` and `shutdown` commands to shut down a system. Both commands perform a clean system shutdown, which means all system processes and services are terminated normally.
- Use the `shutdown` command to shut down a server, because logged-in users and systems mounting resources from the server are notified before the server is shut down. Additional notification of system shutdowns via electronic mail is also recommended so that users can be prepared for system downtime.
- You need superuser privileges to use the `shutdown` or `init` command to shut down a system.
- Both `shutdown` and `init` commands take a run level as an argument. The three most common run levels are:
  - Run level 3 – Means that all system resources are available and users can log in. By default, booting a system brings it to run level 3, which is used for normal day-to-day operations. Also known as multiuser level with NFS resources shared.
  - Run level 6 – Stops the operating system and reboots to the state defined by the `initdefault` entry in the `/etc/inittab` file.
  - Run level 0 – Means the operating system is shut down and it is safe to turn off power. Bringing a system to run level 0 is needed whenever the system is moved or hardware is added or removed.
  - Run levels are fully described in Chapter 6.

---

## Guidelines for Booting a System

Keep the following in mind when booting a system:

- After a system is shut down, it is booted by using the `boot` command at the PROM level on a SPARC system or by using the `boot` command at the Primary Boot Subsystem Menu on an Intel system.
- A system can be rebooted by turning the power off and then back on. This is not a clean shutdown because system services and processes are terminated abruptly. However, turning a system's power off and back is an alternative for emergency situations.
- SPARC and x86 systems use different hardware components for booting. These differences are described in Chapter 10.

## Performing a Reconfiguration Boot

Perform a reconfiguration boot when adding new hardware to the system or configuring support for pseudo devices, such as increasing the number of pseudo devices (ptys). Table 5-1 to determine which reconfiguration procedure to use.

**TABLE 5-1** Reconfiguration Procedures

If You Are Reconfiguring the System To ...	See ...
Add a secondary disk	Chapter 23 or Chapter 24
Add some other peripheral device	"How to Add a Peripheral Device" on page 293
Change the number of pseudo devices	"Examining and Changing System Information (Tasks)" in <i>System Administration Guide, Volume II</i>

## When to Shut Down a System

Table 5-2 provides a list of system administration tasks and the type of shut down needed to initiate the task.



**TABLE 5-2** Shutting Down a System

If You Are ...	Change to This Run Level ...	See ...
Turning off system power due to anticipated power outage	Run level 0, where it is safe to turn off power	Chapter 7
Changing kernel parameters in the <code>/etc/system</code> file	Run level 6 (reboot the system)	Chapter 7
Performing file system maintenance, such as backing up or restoring system data	Run level S (single-user mode)	Chapter 7
Repairing a system configuration file such as <code>/etc/system</code>	See “When to Boot a System” on page 104	N/A
Changing pseudo device parameters in the <code>/etc/system</code> file	Reconfiguration boot	“Tuning Kernel Parameters (Tasks)” in <i>System Administration Guide, Volume II</i>
Adding or removing hardware from the system	Reconfiguration boot (plus turning off power when adding or removing hardware)	“SPARC: How to Connect a Secondary Disk and Boot” on page 355
Repairing an important system file which is causing system boot failure	See “When to Boot a System” on page 104	N/A
Booting the kernel debugger ( <code>kadb</code> ) to track down a system problem	Run level 0, if possible	Chapter 7
Recovering from a hung system and you want to force a crash dump	See “When to Boot a System” on page 104	N/A

See Chapter 7 for examples of shutting down a server or standalone system.

## When to Boot a System

Table 5-3 provides a list of system administration tasks and the corresponding boot type used to complete the task.

**TABLE 5-3** Booting a System

If You Are Rebooting the System After ...	Use This Boot Type ...	See SPARC Procedure ...	See x86 Procedure ...
Turning off system power due to anticipated power outage	Turn system power back on	Chapter 7	Chapter 7
Changing kernel parameters in the <code>/etc/system</code> file	Reboot the system to run level 3 (multiuser mode with NFS resources shared)	“SPARC: How to Boot a System to Run Level 3 (Multiuser State)” on page 134	“x86: How to Boot a System to Run Level 3 (Multiuser State)” on page 146
Performing file system maintenance, such as performing a backup or restoring system data	Use Control-d from run level S to bring the system back to run level 3	“SPARC: How to Boot a System to Run Level S (Single-User State)” on page 135	“x86: How to Boot a System to Run Level S (Single-User State)” on page 147
Repairing a system configuration file such as <code>/etc/system</code>	Interactive boot	“SPARC: How to Boot a System Interactively” on page 136	“x86: How to Boot a System Interactively” on page 149
Changing pseudo device parameters in the <code>/etc/system</code> file	Reconfiguration boot	“Tuning Kernel Parameters (Tasks)” in <i>System Administration Guide, Volume II</i>	“Tuning Kernel Parameters (Tasks)” in <i>System Administration Guide, Volume II</i>

**TABLE 5-3** Booting a System *(continued)*

If You Are Rebooting the System After ...	Use This Boot Type ...	See SPARC Procedure ...	See x86 Procedure ...
Adding or removing hardware from the system	Reconfiguration boot (plus turning on system power after adding or removing hardware)	“SPARC: How to Connect a Secondary Disk and Boot” on page 355	Chapter 24
Booting the kernel debugger (kadb) to track down a system problem	Booting kadb	“SPARC: How to Boot the System Using the Kernel Debugger (kadb)” on page 142	“x86: How to Force a Crash Dump and Reboot the System” on page 155
Repairing an important system file which is causing system boot failure	Recovery boot	“x86: How to Boot a System for Recovery Purposes” on page 151	“x86: How to Boot a System for Recovery Purposes” on page 151
Recovering from a hung system and you want to force a crash dump	Recovery boot	See example on “x86: How to Force a Crash Dump and Reboot the System” on page 155	See example on “x86: How to Force a Crash Dump and Reboot the System” on page 155

See Chapter 8 or Chapter 9 for examples of booting a system.



## Run Levels and Boot Files (Tasks)

---

This chapter provides guidelines for shutting down and booting a system and information about run levels and boot files.

This is a list of the step-by-step instructions in this chapter.

- “How to Determine a System’s Run Level” on page 108
- “How to Use a Run Control Script to Stop or Start a Service” on page 113
- “How to Add a Run Control Script” on page 114
- “How to Disable a Run Control Script” on page 115

This is a list of overview information in this chapter.

- “Run Levels” on page 107
- “The `/etc/inittab` File” on page 109
- “Run Control Scripts” on page 112
- “Run Control Script Summaries” on page 116

---

## Run Levels

A system’s *run level* (also known as an init state) defines what services and resources are available to users. A system can be in only one run level at a time.

The Solaris software environment has eight run levels, which are described in Table 6–1. The default run level is specified in the `/etc/inittab` file as run level 3.

TABLE 6-1 Solaris Run Levels

Run Level	Init State	Type	Use This Level ...
0	Power-down state	Power-down	To shut down the operating system so that it is safe to turn off power to the system.
s or S	Single-user state	Single-user	To run as a single user with all file systems mounted and accessible.
1	Administrative state	Single-user	To access all available file systems with user logins allowed.
2	Multuser state	Multuser	For normal operations. Multiple users can access the system and the entire file system. All daemons are running except for the NFS server daemons.
3	Multuser with NFS resources shared	Multuser	For normal operations with NFS resource-sharing available.
4	Alternative multuser state		This level is currently unavailable.
5	Power-down state	Power-down	To shut down the operating system so that it is safe to turn off power to the system. If possible, automatically turn off system power on systems that support this feature.
6	Reboot state	Reboot	To shut down the system to run level 0, and then reboot to multuser state (or whatever level is the default in the <code>inittab</code> file).

## ▼ How to Determine a System's Run Level

Display run level information by using the `who -r` command to determine a system's run level.

```
$ who -r
```

Use the `who -r` command to determine a system's current run level for any level except run level 0.

## Example—Determining a System’s Run Level

```
$ who -r
.      run-level 3  Jun 10 09:56      3      0  S
$
```

run level 3	Identifies the current run level.
Jun 10 09:56	Identifies the date of last run level change.
3	Is the current run level.
0	Identifies the number of times at this run level since the last reboot.
S	Identifies the previous run level.

---

## The /etc/inittab File

When you boot the system or change run levels with the `init` or `shutdown` command, the `init` daemon starts processes by reading information from the `/etc/inittab` file. This file defines three important items for the `init` process:

- The system’s default run level
- What processes to start, monitor, and restart if they terminate
- What actions to be taken when the system enters a new run level

Each entry in the `/etc/inittab` file has the following fields:

*id: rstate: action: process*

Table 6-2 describes the fields in an `inittab` entry.

**TABLE 6-2** Fields in the `inittab` File

Field	Description
<i>id</i>	A unique identifier for the entry.
<i>rstate</i>	A list of run levels to which this entry applies.
<i>action</i>	How the process specified in the process field is to be run. Possible values include: <code>initdefault</code> , <code>sysinit</code> , <code>boot</code> , <code>bootwait</code> , <code>wait</code> , and <code>respawn</code> .
<i>process</i>	The command to execute.

## Example—Default `inittab` File

The following example shows a default `inittab` file:

```
ap::sysinit:/sbin/autopush -f /etc/iu.ap
ap::sysinit:/sbin/soconfig -f /etc/sock2path
fs::sysinit:/sbin/rcS sysinit      >/dev/console 2<>/dev/console </dev/
console
is:3:initdefault:
p3:s1234:powerfail:/usr/sbin/shutdown -y -i5 -g0 >/dev/console 2<>/dev/
console
sS:s:wait:/sbin/rcS                >/dev/console 2<>/dev/console </dev/
console
s0:0:wait:/sbin/rc0                >/dev/console 2<>/dev/console </dev/
console
s1:1:respawn:/sbin/rc1             >/dev/console 2<>/dev/console </dev/
console
s2:23:wait:/sbin/rc2              >/dev/console 2<>/dev/console </dev/
console
s3:3:wait:/sbin/rc3               >/dev/console 2<>/dev/console </dev/
console
s5:5:wait:/sbin/rc5               >/dev/console 2<>/dev/console </dev/
console
s6:6:wait:/sbin/rc6               >/dev/console 2<>/dev/console </dev/
console
fw:0:wait:/sbin/uadmin 2 0         >/dev/console 2<>/dev/console </dev/
console
of:5:wait:/sbin/uadmin 2 6         >/dev/console 2<>/dev/console </dev/
console
rb:6:wait:/sbin/uadmin 2 1         >/dev/console 2<>/dev/console </dev/
console
sc:234:respawn:/usr/lib/saf/sac -t 300
```

(continued)



(Continuation)

```
co:234:respawn:/usr/lib/saf/  
ttypmon -g -h -p "`uname -n` console login: " -T sun  
-d /dev/console -l console -m ldterm,ttcompat
```

## What Happens When the System Is Brought to Run Level 3

1. The `init` process is started and reads the `/etc/default/init` file to set any environment variables. By default, only the `TIMEZONE` variable is set.
2. Then `init` reads the `inittab` file to do the following:
  - a. Identify the `initdefault` entry, which defines the default run level (3).
  - b. Execute any process entries that have `sysinit` in the action field so that any special initializations can take place before users login.
  - c. Execute any process entries that have 3 in the `rstate` field, which matches the default run level, 3.

See `init(1M)` for a detailed description of how the `init` process uses the `inittab` file.

Table 6–3 describes the key words used for run level 3's action field.

TABLE 6–3 Run Level 3 Action Key Word Descriptions

Key Word	Starts the Specified Process ...
<code>powerfail</code>	Only when the system receives a power fail signal.
<code>wait</code>	And waits for its termination.
<code>respawn</code>	If it does not exist. If the process already exists, continue scanning the <code>inittab</code> file.

Table 6–4 describes the processes (or commands) executed at run level 3.

**TABLE 6-4** Run Level 3 Command Descriptions

Command or Script Name	Description
<code>/usr/sbin/shutdown</code>	Shuts down the system. The <code>init</code> process runs the <code>shutdown</code> command only if the system has received a <code>powerfail</code> signal.
<code>/sbin/rcS</code>	Mounts and checks root ( <code>/</code> ), <code>/usr</code> , <code>/var</code> , and <code>/var/adm</code> file systems.
<code>/sbin/rc2</code>	Starts the standard system processes, bringing the system up into run level 2 (multiuser mode).
<code>/sbin/rc3</code>	Starts NFS resource sharing for run level 3.
<code>/usr/lib/saf/sac -t 30</code>	Starts the port monitors and network access for UUCP. This process is restarted if it fails.
<code>/usr/lib/saf/ttymon -g -h -p " `uname -n` console login: " -T <i>terminal_type</i> -d /dev/ console -l console</code>	Starts the <code>ttymon</code> process that monitors the console for login requests. This process is restarted if it fails.  The <i>terminal_type</i> on a SPARC system is <code>sun</code>  The <i>terminal_type</i> on a x86 system is <code>AT386</code>

## Run Control Scripts

The Solaris software environment provides a detailed series of run control (`rc`) scripts to control run level changes. Each run level has an associated `rc` script located in the `/sbin` directory:

- `rc0`
- `rc1`
- `rc2`
- `rc3`
- `rc5`
- `rc6`
- `rcS`

For each `rc` script in the `/sbin` directory, there is a corresponding directory named `/etc/rcn.d` that contains scripts to perform various actions for that run level. For example, `/etc/rc2.d` contains files used to start and stop processes for run level 2.

# <b>ls /etc/rc2.d</b>		
K20spc@	S70uucp*	S80lp*
K60nfs.server*	S71rpc*	S80spc@
K76snmpdx*	S71sysid.sys*	S85power*
K77dmi*	S72autoinstall*	S88sendmail*
README	S72inetsvc*	S88utmpd*
S01MOUNTFSYS*	S73nfs.client*	S89bdconfig@
S05RMTMPFILES*	S74autofs*	S91leoconfig*
S20syssetup*	S74syslog*	S92rtvc-config*
S21perf*	S74xntpd*	S92volmgt*
S30sysid.net*	S75cron*	S93cacheos.finish*
S47asppp*	S76nscd*	S99audit*
S69inet*	S80PRESERVE*	S99dtlogin*

The `/etc/rcn.d` scripts are always run in ASCII sort order. The scripts have names of the form:

`[KS][0-9][0-9]*`

Files beginning with `K` are run to terminate (kill) a system process. Files beginning with `S` are run to start a system process.

Run control scripts are also located in the `/etc/init.d` directory. These files are linked to corresponding run control scripts in the `/etc/rcn.d` directories.

The actions of each run control script are summarized in Table 6–5.

## Using a Run Control Script to Stop or Start Services

One advantage of having individual scripts for each run level is that you can run scripts in the `/etc/init.d` directory individually to turn off functionality without changing a system’s run level.

### ▼ How to Use a Run Control Script to Stop or Start a Service

1. **Become superuser.**
2. **Turn off functionality.**

```
# /etc/init.d/filename stop
```

### 3. Restart functionality.

```
# /etc/init.d/filename start
```

### 4. Use the `pgrep` command to verify whether the service has been stopped or started.

```
# pgrep -f service
```

## Example—Using a Run Control Script to Stop or Start a Service

Turn off NFS server functionality by typing:

```
# /etc/init.d/nfs.server stop
# pgrep -f nfs
#
```

Restart the NFS services by typing:

```
# /etc/init.d/nfs.server start
# pgrep -f nfs
141
143
245
247
# pgrep -f nfs -d, | xargs ps -fp
root 141 1 40 Jul 31 ? 0:00 /usr/lib/nfs/statd
root 143 1 80 Jul 31 ? 0:01 /usr/lib/nfs/lockd
root 245 1 34 Jul 31 ? 0:00 /usr/lib/nfs/nfsd -a 16
root 247 1 80 Jul 31 ? 0:02 /usr/lib/nfs/mountd
```

## Adding a Run Control Script

If you want to add a run control script to start and stop a service, copy the script into the `/etc/init.d` directory and create links in the `rcn.d` directory you want the service to start and stop.

See the `README` file in each `/etc/rcn.d` directory for more information on naming run control scripts. The procedure below describes how to add a run control script.

### ▼ How to Add a Run Control Script

#### 1. Become superuser.

**2. Add the script to the `/etc/init.d` directory.**

```
# cp filename /etc/init.d
# chmod 0744 /etc/init.d/filename
# chown root:sys /etc/init.d/filename
```

**3. Create links to the appropriate `rcn.d` directory.**

```
# cd /etc/init.d
# ln filename /etc/rc2.d/Snnfilename
# ln filename /etc/rcn.d/Knnfilename
```

**4. Use the `ls` command to verify that the script has links in the specified directories.**

```
# ls /etc/init.d/ /etc/rc2.d/ /etc/rcn.d/
```

## Example—Adding a Run Control Script

```
# cp xyz /etc/init.d
# cd /etc/init.d
# ln xyz /etc/rc2.d/S100xyz
# ln xyz /etc/rc0.d/K100xyz
# ls /etc/init.d /etc/rc2.d /etc/rc0.d
```

## Disabling a Run Control Script

Disable a run control script by renaming it with a dot (.) at the beginning of the new file name. Files that begin with a dot are not executed. If you copy a file by adding a suffix to it, both files will be run.

### ▼ How to Disable a Run Control Script

**1. Become superuser.**

2. Rename the script by adding an underscore ( `_` ) to the beginning of the new file.

```
# cd /etc/rcn.d
# mv filename _filename
```

3. Verify the script has been renamed.

```
# ls
# _filename
```

### Example—Disabling a Run Control Script

The following example changes the `S100datainit` script name but saves the original script.

```
# cd /etc/rc2.d
# mv S100datainit _S100datainit
```

---

## Run Control Script Summaries

TABLE 6-5 The `/sbin/rc0` Script

Script Name	Description
<code>/sbin/rc0</code>	Performs the following tasks: <ul style="list-style-type: none"><li>■ Stops system services and daemons</li><li>■ Terminates all running processes</li><li>■ Unmounts all file systems</li></ul>

**TABLE 6-5** The `/sbin/rc0` Script (continued)

**TABLE 6-6** The `/sbin/rc1` Script

Script Name	Description
<code>/sbin/rc1</code>	<p>Runs the <code>/etc/rc1.d</code> scripts to perform the following tasks:</p> <ul style="list-style-type: none"> <li>■ Stops system services and daemons</li> <li>■ Terminates all running processes</li> <li>■ Unmounts all file systems</li> <li>■ Brings the system up in single-user mode</li> </ul>

**TABLE 6-7** The `/sbin/rc2` Script

Script Name	Description
<code>/sbin/rc2</code>	<p>Runs the <code>/etc/rc2.d</code> scripts to perform the following tasks:</p> <ul style="list-style-type: none"> <li>■ Mounts all local file systems</li> <li>■ Enables disk quotas if at least one file system was mounted with the <code>quota</code> option</li> <li>■ Saves editor temporary files in <code>/usr/preserve</code></li> <li>■ Removes any files in the <code>/tmp</code> directory</li> <li>■ Configures system accounting</li> <li>■ Configures default router</li> <li>■ Sets NIS domain and <code>ifconfig</code> netmask</li> <li>■ Reboots the system from the installation media or a boot server if either <code>.PREINSTALL</code> or <code>AUTOINSTALL</code> exists</li> <li>■ Starts <code>inetd</code> and <code>rpcbind</code> and <code>named</code>, if appropriate</li> <li>■ Starts Kerberos client-side daemon, <code>kerbd</code></li> <li>■ Starts NIS daemons (<code>ypbind</code>) and NIS+ daemons (<code>rpc.nisd</code>), depending on whether the system is configured for NIS or NIS+, and whether the system is a client or a server</li> <li>■ Starts <code>keyserv</code>, <code>statd</code>, <code>lockd</code>, <code>xntpd</code>, and <code>utmpd</code></li> <li>■ Mounts all NFS entries</li> <li>■ Starts <code>nscd</code> (name service cache daemon)</li> <li>■ Starts <code>automount</code>, <code>cron</code>, LP print service, <code>sendmail</code>, <code>utmpd</code>, and <code>vold</code> daemons</li> </ul>

**Note** - Many of the system services and applications that are started at run level 2 depend on what software is installed on the system.

**TABLE 6-8** The `/sbin/rc3` Script

Script Name	Description
<code>/sbin/rc3</code>	<p>Runs the <code>/etc/rc3.d</code> scripts to perform the following tasks:</p> <ul style="list-style-type: none"><li>■ Cleans up <code>sharetab</code></li><li>■ Starts <code>nfsd</code></li><li>■ Starts <code>mountd</code></li><li>■ If the system is a boot server, starts <code>rarpd</code>, <code>rpc.bootparamd</code>, and <code>rpld</code></li><li>■ Starts <code>snmpdx</code> (Solstice™ Enterprise™ Agent™ process ).</li></ul>

**TABLE 6-9** The `/sbin/rc5` and `/sbin/rc6` Scripts

Script Name	Description
<code>/sbin/rc5</code> and <code>/sbin/rc6</code>	<p>Runs the <code>/etc/rc0.d/K*</code> scripts to perform the following tasks:</p> <ul style="list-style-type: none"><li>■ Kills all active processes</li><li>■ Unmounts the file systems</li></ul>

**TABLE 6-10** The `/sbin/rcS` Script

Script Name	Description
<code>/sbin/rcS</code>	<p>Runs the <code>/etc/rcS.d</code> scripts to bring the system up to run level S. The following tasks are performed from these scripts:</p> <ul style="list-style-type: none"><li>■ Establishes a minimal network</li><li>■ Mounts <code>/usr</code>, if necessary</li><li>■ Sets the system name</li><li>■ Checks the root (<code>/</code>) and <code>/usr</code> file systems</li><li>■ Mounts pseudo file systems (<code>/proc</code> and <code>/dev/fd</code>)</li><li>■ Rebuilds the device entries for reconfiguration boots</li><li>■ Checks and mounts other file systems to be mounted in single-user mode</li></ul>



## Shutting Down a System (Tasks)

---

This chapter describes the procedures for shutting down systems. This is a list of the step-by-step instructions in this chapter.

- “How to Determine Who Is Logged in to a System” on page 121
- “How to Shut Down a Server” on page 122
- “How to Shut Down a Standalone System” on page 125
- “How to Turn Off Power to All Devices” on page 127

This is a list of the overview information in this chapter.

- “When to Shut Down the System” on page 119
- “How to Shut Down a System” on page 120
- “When to Turn Off Power to Devices” on page 121
- “Notifying Users of System Down Time” on page 121

For overview information about the available run levels, see Chapter 6.

---

## When to Shut Down the System

The Solaris system software is designed to be left running continuously so that the electronic mail and network software can work correctly. However, some system administration tasks and emergency situations require that the system is shut down to a level where it is safe to remove power or brought to an intermediate level, where not all system services are available, such as:

- Adding or removing hardware
- Preparing for an expected power outage

- Performing file system maintenance, such as a backup

See Chapter 5 for a complete list of system administration tasks requiring a system shutdown.

## How to Shut Down a System

Using the `init` and `shutdown` commands are the primary ways to shut down a system. Both commands perform a *clean shutdown* of the system, which means all file system changes are written to the disk, and all system services, processes, and the operating system are terminated normally.

Using a system's stop key sequence or turning a system off and then on are not clean shutdowns because system services are terminated abruptly. However, is it sometimes necessary to use these actions in emergency situations. See Chapter 8 or Chapter 9 for instructions on system recovery techniques.

Table 7-1 describes the various shutdown commands and provides recommendations for using them.

**TABLE 7-1** Shutdown Commands

Command	Description	This Command Is ...
<code>shutdown</code>	An executable shell script that calls the <code>init</code> program to shutdown the system. The system is brought to run level S by default.	Recommended for servers running at run level 3 because users are notified of the impending shut down as are the systems that are mounting resources from the server being shut down.
<code>init</code>	An executable that kills all active process and syncs the disks before changing run levels.	Recommended for standalone systems when other users will not be affected. It provides a faster system shutdown because users are not notified of the impending shutdown.
<code>reboot</code>	An executable that syncs the disks and passes booting instructions to the <code>uadmin</code> system call, which, in turn, stops the processor.	Not recommended; use the <code>init</code> command instead.
<code>halt</code>	An executable that syncs the disks and stops the processor.	Not recommended because it doesn't execute the <code>/etc/rc0</code> script, which stops all processes, syncs the disks, and unmounts any remaining file systems.

---

**Note** - The `/usr/sbin/shutdown` command, not the `/usr/ucb/shutdown` command, is used in this chapter and throughout this book.

---

## When to Turn Off Power to Devices

Turning off power to all system devices is necessary when you need to:

- Replace or add hardware
- Move the system from one location to another
- Prepare for an expected power outage or natural disaster like an approaching electrical storm

All system devices include the CPU, the monitor, and external devices such as disks, tapes, and printers.

The steps for turning off power to all devices are performed in addition to shutting down the system.

## Notifying Users of System Down Time

When the `shutdown` command is initiated, it will notify all logged-in users and all systems that are mounting resources from it of the impending shutdown with a warning and then a final message.

This is why the `shutdown` command is recommended over the `init` command when used on a server. When using either command, you may want to give users more notice by sending a mail message about any scheduled system shutdown.

Use the `who(1)` command to determine which users on the system need to be notified. This command is also useful for determining a system's current run level, which is described on "How to Determine a System's Run Level" on page 108.

### ▼ How to Determine Who Is Logged in to a System

1. Log into the system to be shut down.
2. Display logged-in users with the `who` command.

```
$ who
```

## Example—Determining Who Is Logged in to a System

The following example displays the output of the `who` command.

```
$ who
1holly2      console  May  7 07:30
3kryten     pts/0    May  7 07:35 (starbug)
4lister     pts/1    May  7 07:40 (bluemidget)
```

## ▼ How to Shut Down a Server

1. **Become superuser.**
2. **Find out if users are logged into the system.**

```
# who
```

A list of all logged-in users is displayed. You may want to send mail or broadcast a message to let users know that the system is being shut down.

3. **Shut down the system by using the `shutdown(1M)` command.**

```
# shutdown -iinit-state -ggrace-period -y
```

`-iinit-state`

Brings the system to an init state different from the default of S. The choices are 0, 1, 2, 5, and 6.

`-ggrace-period`

Indicates a time (in seconds) before the system is shut down. The default is 60 seconds.

`-y`

Continues to shut down the system without intervention; otherwise, you are prompted to continue the shutdown process after 60 seconds.

4. **If you are asked for confirmation, type `y`.**

```
Do you want to continue? (y or n): y
```

If you used the `shutdown -y` command, you will not be prompted to continue.

1. Identifies the username of the logged-in user.
2. Identifies the terminal line of the logged-in user.
3. Identifies the date and time the user logged in.
4. (Optional) Identifies the host name if a user is logged in from a remote system.

5. Type the superuser password, if prompted.

```
Type Ctrl-d to proceed with normal startup,  
(or give root password for system maintenance): xxxx
```

6. After you have finished the system administration tasks, press Control-d to return to the default run system level.

7. Use the following table to verify the system is at the run level specified in the shutdown command.

If the System Was Brought To ...	The SPARC System Prompt Should Be ...	The x86 System Prompt Should Be ...
Run level S (single-user state)	#	#
Run level 0 (power-down state)	ok or >	type any key to continue
Run level 3 (multiuser state with remote resources shared)	<i>hostname</i> console login:	<i>hostname</i> console login:

## Example—Bringing a SPARC System to Run Level S (Server)

In the following example, the shutdown is used to bring a SPARC system to run level S (single-user state) in 3 minutes.

```
# who  
root      console      Jun 10 14:15  
# shutdown -g180 -y  
  
Shutdown started.      Wed Jun 10 14:15:25 MDT 1998  
  
Broadcast Message from root (console) on mars Wed Jun 10 14:15:26...  
The system mars will be shut down in 3 minutes  
.  
.  
.  
Broadcast Message from root (console) on mars Wed Jun 10 14:17:58...
```

(continued)

(Continuation)

```
The system mars will be shut down in 30 seconds
.
.
.
INIT: New run level: S
The system is coming down for administration. Please wait.
Unmounting remote filesystems: /vol nfs done.
Print services stopped.
syslogd: going down on signal 15
Killing user processes: done.

INIT: SINGLE USER MODE

Type Ctrl-d to proceed with normal startup,
(or give root password for system maintenance): xxx
Entering System Maintenance Mode ...
#
```

## Example—Bringing a SPARC System to Run Level 0 (Server)

In the following example, the `shutdown` command is used to bring a SPARC system to run level 0 in 5 minutes without requiring additional confirmation.

```
# who
kryten      console      Jun 10 14:22
rimmer      pts/1              Jun 10 14:23      (starbug)
pmorph      pts/2              Jun 10 14:24      (bluemidget)
Send mail message to logged-in users
# shutdown -i0 -g300 -y
Shutdown started.      Wed Jun 10 14:30:32 MDT 1998
Broadcast Message from root (console) on pluto Wed Jun 10 14:30:32...
The system will be shut down in 5 minutes
.
.
.
INIT: New run level: 0
The system is coming down. Please wait.
.
.
.
The system is down.
syncing file systems... [11] [9] [5] done
Program terminated
Type help for more information
ok
```

See “How to Turn Off Power to All Devices” on page 127 if you are bringing the system to run level 0 to turn off power to all devices.

## Example—Rebooting a SPARC System to Run Level 3 (Server)

In the following example, the `shutdown` command is used to reboot a SPARC system to run level 3 in 2 minutes without requiring additional confirmation.

```
# who
kryten      console      Jun 10 14:35
rimmer      pts/1              Jun 10 14:40      (starbug)
pmorph      pts/2              Jun 10 14:45      (bluemidget)
Send mail message to logged-in users
# shutdown -i6 -g120 -y
Shutdown started.      Wed Jun 10 14:34:26 MDT 1998
Broadcast Message from root (console) on pluto Wed Jun 10 14:34:26 MDT 1998
The system will be shut down in 1 minute
Changing to init state 6 - please wait
#
INIT: New run level: 6
The system is coming down.  Please wait.
.
.
.
The system is down.
syncing file systems... [11] [9] [5] done
rebooting...
.
.
.
pluto console login:
```

## Where to Go From Here

Regardless of the reason for shutting down the system, you'll probably want to return to run level 3 where all file resources are available and users can log in. See Chapter 8 or Chapter 9 for instructions on bringing a system back to a multiuser state.

## ▼ How to Shut Down a Standalone System

1. Become superuser.
2. Shut down the system by using the `init(1M)` command.

```
# init run-level
```

*run-level*

Identifies the new run level.

3. Use the following table to verify the system is at the run level specified in the `init` command.

If the System Was Brought To ...	The SPARC System Prompt Should Be ...	The x86 System Prompt Should Be ...
Run level S (single-user state)	#	#
Run level 2 (multiuser state)	#	#
Run level 0 (power-down state)	ok or >	type any key to continue
Run level 3 (multiuser state with remote resources shared)	<i>hostname</i> console login:	<i>hostname</i> console login:

## Example—Bringing an x86 System to Run Level 0 (Standalone)

In the following example, the `init` command is used to bring an x86 standalone system to the level where it is safe to turn off power.

```
# init 0
#
INIT: New run level: 0
The system is coming down. Please wait.
.
.
.
The system is down.
syncing file systems... [11] [10] [3] done
Type any key to continue
```

See “How to Turn Off Power to All Devices” on page 127 if you are bringing the system to run level 0 to turn off power to all devices.

## Example—Bringing a SPARC System to Run Level S (Standalone)

In the following example, the `init` is used to bring a SPARC standalone system to run level S (single-user state).

```
# init s
#
INIT: New run level: S
The system is coming down for administration. Please wait.
Unmounting remote filesystems: /vol nfs done.
```



(Continuation)

```
Print services stopped.
syslogd: going down on signal 15
Killing user processes: done.
INIT: SINGLE USER MODE

Type Ctrl-d to proceed with normal startup,
(or give root password for system maintenance): xxx
Entering System Maintenance Mode

#
```

Where to Go From Here

Regardless of the reason for shutting down the system, you'll probably want to return to run level 3 where all file resources are available and users can log in. See Chapter 8 or Chapter 9 for instructions on bringing a system back to a multiuser state.

▼ How to Turn Off Power to All Devices

- 1. Use the following table to determine which procedure to use for shutting down the system.

If You Are Shutting Down a Server ...	If You Are Shutting Down a Standalone System ...
See "How to Shut Down a Server" on page 122.	See "How to Shut Down a Standalone System" on page 125.

- 2. Turn off power to all devices after the system is shutdown. If necessary, also unplug the power cables.
- 3. After power can be restored, use the following steps to turn on the system and devices.
  - a. Plug in the power cables.
  - b. Turn on the monitor.
  - c. Turn on disk drives, tape drives, and printers.
  - d. Turn on the CPU.

The system brought to run level 3 after the CPU is turned on.



## Booting a SPARC System (Tasks)

---

This chapter describes procedures for using the OpenBoot™ PROM monitor and procedures for booting a SPARC system to different run levels.

This is a list of the step-by-step instructions in this chapter.

- “SPARC: How to Switch to the ok Prompt” on page 130
- “SPARC: How to Find the PROM Release for a System” on page 130
- “SPARC: How to Change the Default Boot Device” on page 130
- “SPARC: How to Reset the System” on page 132
- “SPARC: How to Boot a System to Run Level 3 (Multiuser State)” on page 134
- “SPARC: How to Boot a System to Run Level S (Single-User State)” on page 135
- “SPARC: How to Boot a System Interactively” on page 136
- “SPARC: How to Boot a System for Recovery Purposes” on page 138
- “SPARC: How to Stop the System for Recovery Purposes” on page 140
- “SPARC: How to Force a Crash Dump and Reboot the System” on page 141
- “SPARC: How to Boot the System Using the Kernel Debugger (kadb)” on page 142

For overview information about the boot process, see Chapter 10.

---

## SPARC: Using the Boot PROM

System administrators typically use the PROM level to boot a system but occasionally may need to change the way the system works, such as setting which device to boot from or running hardware diagnostics, before the system is brought to a multiuser state.

Changing the default boot device is necessary when you want to add a new drive to the system either permanently or temporarily, or if you convert a standalone system to a diskless client that needs to boot from the network.

See `monitor(1M)` or `eeprom(1M)` for a complete list of PROM commands.

## ▼ SPARC: How to Switch to the `ok` Prompt

When the system is halted, the PROM monitor prompt is either the greater than sign (`>`) or `ok`.

Switch from the `>` prompt to the `ok` prompt on SPARC systems by typing the following command.

```
> n
ok
```

All examples in this section use the `ok` prompt.

## ▼ SPARC: How to Find the PROM Release for a System

Display a system's PROM release level with the `banner` command.

```
ok banner
SPARCstation 2, Type 4 Keyboard
ROM Rev. 2.2, 16 MB memory installed, Serial #nnnnnnn
Ethernet address 8:0:20:f:fd:6c HostID nnnnnnnnn
```

Hardware configuration information, including the release number of the PROM, is displayed. The PROM release level is indicated by the ROM Rev. number.

## ▼ SPARC: How to Change the Default Boot Device

Use this procedure when you need to change the default boot device.

1. **Become superuser.**
2. **Halt the system by using the `init(1M)` command.**

```
# init 0
```

The `>` PROM prompt is displayed.

3. **If the `>` PROM prompt is displayed, type `n` and press Return.**

```
> n
ok
```

The `ok` PROM prompt is displayed.

**4. Change the `boot-device` setting by using the `setenv` command.**

```
ok setenv boot-device disk[n]
```

`boot-device`                      Identifies the parameter for setting the device from which to boot.

`disk[n]`                          Identifies the `boot-device` value and in this case, *n* is the disk number.

Use the `probe-scsi-all` command if you need help identifying the disk number.

**5. Verify the default boot device change by using the `printenv` command.**

```
ok printenv boot-device
```

**6. Save the new `boot-device` value by using the `reset` command.**

```
ok reset
```

The `boot-device` setting is written to the PROM.

## SPARC: Example—Changing the Default Boot Device

```
# init 0
#
INIT: New run level: 0
.
.
.
The system is down.
syncing file systems... [11] [10] [5] done
Program terminated
Type help for more information
ok setenv boot-device disk
```

(continued)

(Continuation)

```
boot-device =          disk
ok printenv boot-device
boot-device          disk          disk
ok reset
SPARCstation 10 (1 X 390Z50), No Keyboard
ROM Rev. 2.14, 32 MB memory installed, Serial #3383708.
Ethernet address 8:0:20:1f:33:9f, Host ID: 7233a19e.
Boot device: /iommu/sbus/espdma@f,400000/esp@f,800000/
sd@3,0 File and args: kadb -v
.
.
.
pluto console login:
```

## ▼ SPARC: How to Reset the System

Run the `reset` command from the `ok` prompt.

```
ok reset
```

The self-test program, which runs diagnostic tests on the hardware, is executed and the system is rebooted.

---

## Booting a SPARC System

Table 8–1 describes the boot scenarios covered in this chapter.

**TABLE 8-1** Boot Type Descriptions

Booting the System ...	Is Usually Done ...	See ...
To run level 3 (multiuser state with NFS resources shared)	After halting the system or performing some system hardware maintenance task. This is the default boot level where all resources are available and users can log into the system.	“Example—Booting a System to Run Level 3 (Multiuser State)” on page 134
To run level S (single-user state)	After performing some system maintenance task such as backing up a file system. At this level only local file systems are mounted and users cannot log into the system.	“SPARC: Example—Booting a System to Run Level S (Single-User State)” on page 135
Interactively	After making temporary changes to a system file or the kernel for testing purposes. This type of boot allows you to recover easily if there are problems with the system file or kernel by supplying an alternative pathname to these files when prompted. Use the default settings for the other system prompts.	“SPARC: Example—Booting a System Interactively” on page 137
From local CD-ROM or the network for recovery purposes	To repair an important system file that is preventing the system from booting successfully. This type of boot is also used for installing (or upgrading) a new release of the operating system.	“SPARC: Example—Booting a System for Recovery Purposes” on page 139
Using kadb	To troubleshoot system problems by running the kernel debugger.	“SPARC: Example—Booting the System Using the Kernel Debugger (kadb)” on page 143

If a system is turned off, turning it on starts the multiuser boot sequence. The following procedures show how to boot to different run levels from the `ok` PROM prompt.

Use the `who -r` command to verify that the system is brought to the specified run level.

See Chapter 6 for a description of run levels.

## ▼ SPARC: How to Boot a System to Run Level 3 (Multiuser State)

### 1. Boot to run level 3 by using the `boot(1M)` command.

```
ok boot
```

The automatic boot procedure displays a series of startup messages, and brings the system to run level 3.

### 2. Verify the system boots to run level 3.

The login prompt is displayed when the boot process has finished successfully.

```
hostname console login:
```

## Example—Booting a System to Run Level 3 (Multiuser State)

The following example displays the messages from booting a system to run level 3.

```
ok boot
Resetting ...
SPARCstation 10 (1 X 390Z50), Keyboard Present
ROM Rev. 2.14, 32 MB memory installed, Serial #number.
Ethernet address #number, Host ID: number.

Boot device: /iommu/sbus/espdma@f,400000/esp@f,800000/sd@3,0
File and args:
SunOS Release 5.7 Version generic [UNIX(R) System V Release 4.0]
Copyright (c) 1983-1998, Sun Microsystems, Inc.
configuring network interfaces: le0.
Hostname: venus
The system is coming up. Please wait.
add net default: gateway 129.152.75.248
NIS domainname is solar.com
starting rpc services: rpcbind keyserver ypbind done.
Setting netmask of le0 to 255.255.255.0
Setting default interface for multicast: add net 224.0.0.0: gateway venus
syslog service starting.
Print services started.
volume management starting.
The system is ready.

venus console login:
```

(continued)



(Continuation)

## ▼ SPARC: How to Boot a System to Run Level S (Single-User State)

1. Boot the system to run level S by using the `boot -s` command.

```
ok boot -s
```

2. Enter the superuser password when the following message is displayed.

```
INIT: SINGLE USER MODE
Type Ctrl-d to proceed with normal startup,
(or give root password for system maintenance): xxx
```

3. Use the `who -r` command to verify that the system is at run level S.

```
# who -r
.      run-level 3   Jun 10 15:27      3      0
```

4. To bring the system up to multiuser state after the system maintenance task is performed, press Control-d.

## SPARC: Example—Booting a System to Run Level S (Single-User State)

The following example displays a system booted to run level S.

```

ok boot -s
.
.
.
SunOS Release 5.7 Version [UNIX(R) System V Release 4.0]
Copyright (c) 1983-1998, Sun Microsystems, Inc.
configuring network interfaces: le0.
Hostname: mars
INIT: SINGLE USER MODE
Type Ctrl-d to proceed with normal startup,
(or give root password for system maintenance): xxx
Sun Microsystems Inc.   SunOS 5.7 August 1998
# who -r
.           run-level S  Jun 10 15:34      S      0  ?
(Perform some maintenance task)
# Press <Control-d>

```

## ▼ SPARC: How to Boot a System Interactively

1. Boot the system interactively by using the `boot -a` command.

```
ok boot -a
```

2. Answer the system prompts as described in Table 8-2.

TABLE 8-2 Interactive Boot Procedure Steps

If the System Displays ...	Do the Following ...
Enter filename [kernel/unix]:	Provide the name of another kernel to use for booting.  Or, press Return to use the default kernel (/platform/'uname -m'/kernel/unix).
Name of default directory for modules [/platform/'uname -m'/kernel/kernel /usr/kernel]:	Provide an alternate path for the modules directory and press Return.  Or, press Return to use the default modules directory path.

**TABLE 8–2** Interactive Boot Procedure Steps *(continued)*

If the System Displays ...	Do the Following ...
Name of system file [/etc/system]:	Provide the name of an alternate system file and press Return. Enter /dev/null as the file if your /etc/system file has been damaged.  Or, press Return to use the default /etc/system file.
root filesystem type [ufs]:	Press Return to use the default root file system type: UFS for local disk booting or NFS for diskless clients.
Enter physical name of root device [physical_device_name]:	Provide an alternate device name and press Return.  Or, press Return to use the default physical name of the root device.

3. If you are not prompted to answer the questions in Table 8–2, verify that you entered the `boot -a` command correctly.

## SPARC: Example—Booting a System Interactively

In the following example, the default choices shown in square brackets [ ] are accepted.

```
ok boot -a
.
.
.
Resetting ...
Rebooting with command: -a
Boot device: /iommu/sbus/espdma@f,400000/esp@f,800000/sd@3,0
File and args: -a
Enter filename [kernel/unix]: Return
Enter default directory for modules
[/platform/SUNW,SPARCstation-10/kernel /platform/sun4m/kernel /kernel /usr/
kernel]:
Return
SunOS Release 5.7 Version generic [UNIX(R) System V Release 4.0]
Copyright (c) 1983-1998, Sun Microsystems, Inc.
Name of system file [etc/system]: Return
```

(continued)

(Continuation)

```
root filesystem type [ufs]: Return
Enter physical name of root device
[/iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000
/sd@3,0:a]: Return
configuring network interfaces: le0.
Hostname: earth
The system is coming up. Please wait.
.
.
.
The system is ready.
earth console login:
```

## ▼ SPARC: How to Boot a System for Recovery Purposes

This procedure is needed when an important file, such as `/etc/passwd`, has an invalid entry and is causing the boot process to fail.

If you need help identifying a system's device names, refer to Chapter 20.

1. Follow the instructions below depending on whether you are booting from the Solaris installation CD or the network.

If You Are Booting From ...	Then ...
Solaris installation CD	<ol style="list-style-type: none"><li>1. Insert the Solaris installation CD into the CD caddy.</li><li>2. Insert the CD caddy into the CD-ROM drive.</li><li>3. Boot from the installation CD in single-user mode:  ok <code>boot cdrom -s</code></li></ol>
The network and an installation server or remote CD drive are available	Use the following command:  ok <code>boot net -s</code>

2. Mount the file system that has the file with an invalid entry.

```
# mount /dev/dsk/device-name /a
```

**3. Change to the newly mounted directory.**

```
# cd /a/directory
```

**4. Set the terminal type.**

```
# TERM=sun  
# export TERM
```

**5. Remove the invalid entry from the file using an editor.**

```
# vi filename
```

**6. Change to the root (/) directory.**

```
# cd /
```

**7. Unmount the /a directory.**

```
# umount /a
```

**8. Reboot the system.**

```
# init 6
```

**9. Verify the system boots to run level 3.**

The login prompt is displayed when the boot process has finished successfully.

```
hostname console login:
```

## SPARC: Example—Booting a System for Recovery Purposes

The following example shows how to repair an important system file (in this case, /etc/passwd) after booting from a local CD-ROM.

```
ok boot cdrom -s
# mount /dev/dsk/c0t3d0s0 /a
# cd /a/etc
# TERM=sun
# export TERM
# vi passwd
(Remove invalid entry)
# cd /
# umount /a
# init 6
```

## ▼ SPARC: How to Stop the System for Recovery Purposes

The specific stop key sequence depends on your keyboard type. For example, you can press Stop-a or L1-a. On terminals, press the Break key.

**1. Type the abort key sequence for your system.**

The monitor displays the `ok` PROM prompt.

```
ok
```

**2. Use the `sync` command to synchronize the disks.**

```
ok sync
```

**3. When you see the `syncing file systems...` message, press the abort key sequence for your system again.**

**4. Type the appropriate `boot(1M)` command to start the boot process.**

**5. Verify the system is booted to the specified run level.**

```
# who -r
.      run-level 3  May  2 07:39      3      0  S
```

## SPARC: Example—Stopping the System for Recovery Purposes

```
Press <Stop-a>
ok sync
syncing file systems...
Press <Stop-a>
ok boot
```

## SPARC: Forcing a Crash Dump and Rebooting the System

Saving crash dumps of the operating system is sometimes necessary for troubleshooting purposes. The `savecore` feature and how it is set up is described in “Managing System Crash Information” in *System Administration Guide, Volume II*. This section only describes how to reboot the system when the `savecore` feature is enabled.

### ▼ SPARC: How to Force a Crash Dump and Reboot the System

1. **Type the stop key sequence for your system. The specific stop key sequence depends on your keyboard type. For example, you can press Stop-a or L1-a. On terminals, press the Break key.**

The monitor displays the `ok` PROM prompt.

2. **Use the `sync` command at the `ok` prompt to synchronize the disk and write the crash dump.**

```
> n
ok sync
```

After the crash dump is written to disk, the system will continue to reboot.

3. **Verify the system boots to run level 3.**

The login prompt is displayed when the boot process has finished successfully.

```
hostname console login:
```

## SPARC: Example—Forcing a Crash Dump and Rebooting the System

```
Press <Stop-a>  
ok sync
```

### ▼ SPARC: How to Boot the System Using the Kernel Debugger (kadb)

1. Type the stop key sequence for your system. The specific stop key sequence depends on your keyboard type. For example, you can press Stop-A or L1-A. On terminals, press the Break key.

The monitor displays the ok PROM prompt.

2. Use the `sync` command at the `ok` prompt to synchronize the disk and write the crash dump.

```
> n  
ok sync
```

3. When you see the `syncing file systems...` message, press the abort key sequence for your system again.

4. Boot the system using the kernel debugger.

```
ok boot kadb
```

5. Identify `kadb` booting messages to verify the system is booted using the kernel debugger.

```
Rebooting with command: kadb  
Boot device: /iommu/sbus/espdma@4,800000/esp@4,8800000/sd@3,0  
.  
.
```



(Continuation)

```
.
```

## SPARC: Example—Booting the System Using the Kernel Debugger (kadb)

```
Press <Stop-a>  
ok sync  
syncing file systems...  
Press <Stop-a>  
ok boot kadb
```



## Booting a System (Tasks)

---

This chapter describes the procedures for booting an x86 system.

This is a list of the step-by-step instructions in this chapter.

- “x86: How to Boot a System to Run Level 3 (Multiuser State)” on page 146
- “x86: How to Boot a System to Run Level S (Single-User State)” on page 147
- “x86: How to Boot a System Interactively” on page 149
- “x86: How to Boot a System for Recovery Purposes” on page 151
- “x86: How to Stop the System for Recovery Purposes” on page 154
- “x86: How to Force a Crash Dump and Reboot the System” on page 155

For overview information about the boot process, see Chapter 10.

---

## Booting an x86 System

Table 9–1 describes the boot types covered in this chapter.

**TABLE 9-1** Boot Type Descriptions

Booting the System ...	Is Usually Done ...	See an Example On ...
To run level 3 (multiuser state)	After shutting down the system or performing some system hardware maintenance task. This is the default boot level where all resources are available and users can log into the system.	"x86: Example—Booting a System to Run Level 3 (Multiuser State)" on page 147
To run level S (single-user state)	After performing some system maintenance task such as backing up a file system. At this level only some file systems are mounted and users cannot log into the system.	"x86: Example—Booting a System to Run Level S (Single-User State)" on page 148
Interactively	After making temporary changes to the system file or the kernel for testing purposes. This type of boot allows you to recover easily if there are problems with the system file or kernel by supplying an alternative pathname to these files when prompted. Use the default settings for the other system prompts.	"x86: Example—Booting a System Interactively" on page 150
From local CD-ROM or the network for recovery purposes	To repair an important system file that is preventing the system from booting successfully. This type of boot is also used for installing (or upgrading) a new release of the operating system.	"x86: Example—Booting a System for Recovery Purposes" on page 153
Using <code>kadb</code>	To troubleshoot system problems by using the kernel debugger and saving core dumps of the operating system.	"x86: How to Force a Crash Dump and Reboot the System" on page 155

The following procedures use the reset button to restart the system. If your system does not have a reset button, use the on/off switch to restart the system. You might be able to press the Control-Alt-Del keys to interrupt system operation, depending upon the state of the system.

## ▼ x86: How to Boot a System to Run Level 3 (Multiuser State)

- 1. Press any key to reboot the system if the system displays the**  
Type any key to reboot prompt. You can also use the reset button at this prompt. If the system is shut down, turn the system on with the power (on/off) switch.

The Current Boot Parameters menu is displayed after a few minutes.

**2. Type `b` to boot the system to run level 3. Press Return.**

If you do not make a selection within 5 seconds, the system is automatically booted to run level 3. See

**3. Verify the system boots to run level 3.**

The login prompt is displayed when the boot process has finished successfully.

```
hostname console login:
```

## x86: Example—Booting a System to Run Level 3 (Multiuser State)

```
Type any key to reboot
.
.
.

<<< Current Boot Parameters >>>
Boot path: /eisa/eha@1,4000/sd@0,0:a
Boot args:

Type    b [file-name] [boot-flags] <ENTER>    to boot with options
or      i <ENTER>                               to enter boot interpreter
or      <ENTER>                                to boot with defaults

<<< timeout in 5 seconds >>>

Select (b)oot or (i)nterpreter: b
.
.
.
venus console login:
```

## ▼ x86: How to Boot a System to Run Level S (Single-User State)

**1. Press any key to reboot the system if the system displays the**

**Type any key to reboot prompt. You can also use the reset button at this prompt. If the system is shut down, turn the system on with the power (on/off) switch.**

The Current Boot Parameters menu is displayed after a few minutes.

2. Type **b -s** to boot the system to run level S. Press Return.

If you do not make a selection within 5 seconds, the system is automatically booted to run level 3.

3. Type the superuser password, if prompted.

4. Verify the system is at run level S by using the `who -r` command.

```
# who -r
.          run-level S  Nov 10 13:59      S    0  3
```

5. Perform the maintenance task that needed the run level change to S.

6. Press Control-d to bring the system back to run level 3.

## x86: Example—Booting a System to Run Level S (Single-User State)

```
Type any key to reboot
.
.
.

<<< Current Boot Parameters >>>
Boot path: /eisa/eha@1,4000/sd@0,0:a
Boot args:

Type    b [file-name] [boot-flags] <ENTER>    to boot with options
or      i <ENTER>                               to enter boot interpreter
or      <ENTER>                                to boot with defaults

<<< timeout in 5 seconds >>>

Select (b)oot or (i)nterpreter: b -s
.
.
.
INIT: SINGLE USER MODE

Type Ctrl-d to proceed with normal startup,
(or give root password for system maintenance): xxx
Entering System Maintenance Mode
.
.
```

(continued)

```
# who -r
.      run-level S  Aug  4 13:11      S      0  3
(Perform some maintenance task)
# Press <Control-d>
```

▼ x86: How to Boot a System Interactively

- 1. **Press any key to reboot the system if the system displays the Type any key to reboot prompt. You can also use the reset button at this prompt. If the system is shut down, turn the system on with the power (on/off) switch.**  
The Current Boot Parameters menu is displayed after a few minutes.
- 2. **Type b -a to boot the system interactively.**  
If you do not make a selection within 5 seconds, the system is automatically booted to run level 3.
- 3. **Answer the system prompts as described in Table 9-2.**

TABLE 9-2 Interactive Boot Procedure Steps

If the System Displays ...	Do the Following ...
Type any key to reboot	<p>Press any key to reboot the system if the system displays the Type any key to reboot prompt. You can also use the reset button at this prompt. If the system is shut down, turn the system on with the power (on/off) switch.</p> <p>The Primary Boot Subsystem menu is displayed after a few minutes.</p>
The Primary Boot Subsystem menu	Select the Active Solaris slice as the boot device. Press Return. If you do not make a selection within 30 seconds, the active boot slice is selected automatically.
Select (b)oot or (i)nterpreter:	Type b -a and press Return.

TABLE 9-2 Interactive Boot Procedure Steps (continued)

If the System Displays ...	Do the Following ...
Enter default directory for modules: [/platform/i86pc/kernel /kernel /usr/kernel]:	Provide an alternate path for the modules directory and press Return, or press Return to use the default modules directory path.
Name of system file [etc/system]:	Provide the name of an alternate system file and press Return, or press Return to use the default /etc/system file. Enter /dev/null as the file if your /etc/system file has been damaged.
root filesystem type [ufs]:	Press Return to use the default root file system type: UFS for local disk booting or NFS for diskless clients.
Enter physical name of root device [physical_device_name]:	Provide an alternate device name and press Return, or press Return to use the default physical name of the root device bootpath.

## x86: Example—Booting a System Interactively

In the following example, the default choices (shown in square brackets [ ]) are accepted.

```
Type any key to reboot
.
.
.

<<< Current Boot Parameters >>>
Boot path: /eisa/eha@1,4000/sd@0,0:a
Boot args:

Type      b [file-name] [boot-flags] <ENTER>      to boot with options
or        i <ENTER>                                to enter boot interpreter
or        <ENTER>                                  to boot with defaults

<<< timeout in 5 seconds >>>>
Select (b)oot or (i)nterpreter: b -a
Enter default directory for modules [/platform/i86pc/kernel
```

(continued)



(Continuation)

```
/kernel /usr/kernel]: Return
Name of system file [etc/system]: Return
(Copyright notice)
root filesystem type [ufs]: Return
Enter physical name of root device
[/eisa/dpt@5c88,0/cmdk@0,0:a]: Return
Configuring network interfaces: smc0
Hostname: venus
(fsck messages)
The system is coming up. Please wait
(More messages)
venus console login:
```

## ▼ x86: How to Boot a System for Recovery Purposes

Recovering from an invalid `/etc/passwd` file is used as an example of how to boot a system for recovery purposes.

Substitute the device name of the file system to be repaired for the *devicename* variable identified in the procedures below. If you need help identifying a system's device names, refer to Chapter 20.

Follow the instructions below depending on whether you are booting from the Solaris 2 installation CD or the network.

1. **Boot from the Solaris 2 installation CD (or the network) to single-user mode using steps a-f.**
  - If you are booting from the network, skip steps a and b.
  - a. **Insert the Solaris 2 installation CD into the CD caddy.**
  - b. **Insert the CD caddy into the CD-ROM drive.**
  - c. **(Optional) Insert the Configuration Assistant/Boot Diskette into the primary diskette drive (DOS drive A) if the disk you are booting from doesn't contain the Solaris 2.6 Intel Platform Edition or compatible versions.**
  - d. **Press any key to reboot the system if the system displays the**  
Type any key to reboot **prompt. You can also use the reset button at this prompt. If the system is shut down, turn the system on with the power (on/off) switch.**
  - e. **Press the F2 key (F2\_Continue) at the Solaris Device Configuration Assistant screen.**  
Device identification is performed and a screen that displays the identified devices appears.

- f. **Press the F2 key (F2\_Continue) at the Identified Devices screen.**  
Bootable drivers are loaded.
- g. **Select the CD-ROM drive or net(work) as the boot device from the Boot Solaris screen. Then press the F2 key (F2\_Continue).**  
The Solaris boot option screen is displayed.
- h. **Type `b -s` at the `Select the type of installation:` prompt.**  
After a few minutes, the single-user mode `#` prompt is displayed.

**2. Mount the root (/) file system that has the invalid `passwd` file.**

```
# mount /dev/dsk/devicename /a
```

**3. Change to the newly mounted `etc` directory.**

```
# cd /a/etc
```

**4. Set the terminal type.**

```
# TERM=AT386  
# export TERM
```

**5. Make the necessary change to the `passwd` file using an editor.**

```
# vi passwd
```

**6. Change to the root (/) directory.**

```
# cd /
```

**7. Unmount the `/a` directory.**

```
# umount /a
```

## 8. Reboot the system.

```
# init 6
```

## 9. Verify the system boots to run level 3.

The login prompt is displayed when the boot process has finished successfully.

```
hostname console login:
```

## x86: Example—Booting a System for Recovery Purposes

```
Type any key to reboot

SunOS Secondary Boot version 3.00

Solaris Intel Platform Edition Booting System

Running Configuration Assistant...
Autobooting from bootpath: /eisa/eha@1,4000/sd@0,0:a

If the system hardware has changed, or to boot from a different
device, interrupt the autoboot process by pressing ESC.

Press ESCape to interrupt autoboot in 5 seconds.
.
.
.
Boot Solaris

Select one of the identified devices to boot the Solaris kernel and
choose Continue.

To perform optional features, such as modifying the autoboot and property
settings, choose Boot Tasks.

An asterisk (*) indicates the current default boot device.

> To make a selection use the arrow keys, and press Enter to mark it [X].

[ ] DISK: Target 0, IMPRIMIS 94241-7 0888
    on Adaptec 1740/1742 SCSI controller in EISA Slot 4
[ ] CD : Target 2, TOSHIBA CD-ROM XM-3501TA 3054
    on Adaptec 1740/1742 SCSI controller in EISA Slot 4
[ ] NET : SMC EtherCard Elite32C Ethernet adapter
    in EISA Slot 6
```

(continued)

(Continuation)

```
F2_Continue F3_Back F4_Boot Tasks F6_Help
.
.
.
<<< Current Boot Parameters >>>
Boot path: /eisa/smceu@0,0
Boot args: kernel/unix -r

Select the type of installation you want to perform:

1 Solaris Interactive
2 Custom JumpStart
3 Solaris Web Start

Enter the number of your choice followed by <ENTER> the key.

If you enter anything else, or if you wait for 30 seconds,
an interactive installation will be started.

Select type of installation:
Select (b)oot or (i)nterpreter: b -s
# mount /dev/dsk/c0t3d0s0 /a
# cd /a/etc
# TERM=AT386
# export TERM
# vi passwd
(Remove invalid entry)
# cd /
# umount /a
# init 6
```

## ▼ x86: How to Stop the System for Recovery Purposes

If possible, attempt to stop the system by using one of the following commands:

- If the system is running, become superuser and issue the `init 0` to stop the system. Press any key to reboot the system after the Type any key to reboot prompt appears.
- If the system is running, become superuser and issue the `init 6` to reboot the system.

If the system doesn't respond to any input from the mouse or keyboard, press the reset key, if it exists, to reboot the system. Or, use the power (on/off) switch to reboot the system.

## x86: Forcing a Crash Dump and Rebooting the System

Saving core dumps of the operating system is sometimes necessary for troubleshooting purposes. The `savecore` feature and how it is set up is described in “Managing System Crash Information” in *System Administration Guide, Volume II*. This section only describes how to reboot the system when the `savecore` feature is enabled.

### ▼ x86: How to Force a Crash Dump and Reboot the System

The system must be booted with the kernel debugger option, `kadb`, to get to the `kadb[0]:` prompt and force the crash dump.

---

**x86 platform only** - You must be in text mode to enter the kernel debugger (`kadb`), so exit any window system (CDE or Open Windows) first.

---

#### 1. Press Control-Alt-d.

```
kadb[0]:
```

The `kadb[0]:` prompt is displayed.

#### 2. Type the following commands at the `kadb[0]:` prompt.

```
Press <Control-Alt-d>
kadb[0]: vfs_syncall/W ffffffff
kadb[0]: 0>eip
kadb[0]: :c
kadb[0]: :c
kadb[0]: :c
```

After the first `:c` is typed, the system panics, so you need to type `:c` again. The system panics again, so type `:c` a third time to force the crash dump and reboot the system.

After the crash dump is written to disk, the system will continue to reboot.

3. **Verify the system has rebooted by logging in at the console login prompt.**

## The Boot Process (Reference)

---

This chapter describes the hardware used for booting on SPARC and x86 systems and a conceptual overview of the boot process on each platform.

This is a list of overview information in this chapter.

- “SPARC: The Boot PROM” on page 157
- “SPARC: The Boot Process” on page 158
- “SPARC: The Boot Process Details” on page 158
- “x86: The PC BIOS” on page 159
- “x86: Boot Subsystems” on page 160
- “x86: The Boot Process” on page 165
- “x86: The Boot Process Details” on page 166

For instructions on booting a system, see Chapter 8 or Chapter 9.

---

## SPARC: The Boot PROM

Each SPARC system has a PROM (programmable read-only memory) chip with a program called the *monitor*. The monitor controls the operation of the system before the kernel is available. When a system is turned on, the monitor runs a quick self-test procedure that checks things such as the hardware and memory on the system. If no errors are found, the system begins the automatic boot process.

---

**SPARC platform only** - Some older systems may require PROM upgrades before they will work with the Solaris system software. Contact your local service provider for more information.

---

# SPARC: The Boot Process

TABLE 10-1 SPARC: The Boot Process

Boot PROM Phase	<div>The boot PROM runs self-test diagnostics.</div> <div>The boot PROM loads the <code>bootblock</code> program.</div>
Boot Programs Phase	<div>The boot block program loads the <code>ufsboot</code> program.</div> <div>After the <code>ufsboot</code> program is loaded, it loads the kernel.</div>
Kernel Initialization Phase	<div>The kernel initializes itself and loads the modules needed to mount the root (<code>/</code>) file system.</div> <div>The kernel starts the <code>init</code> process.</div>
<code>init</code> Phase	<div>The <code>init</code> process starts the run control scripts.</div>

# SPARC: The Boot Process Details

Table 10-2 describes the SPARC boot process illustrated above.



TABLE 10-2 Description of SPARC Boot Process

Boot Phase	Description
Boot PROM	<ol style="list-style-type: none"> <li>1. The PROM displays system identification information and then runs self-test diagnostics to verify the system's hardware and memory.</li> <li>2. Then the PROM loads the primary boot program, <code>bootblk</code>, whose purpose is to load the secondary boot program located in the <code>ufs</code> file system from the default boot device.</li> </ol>
Boot Programs	<ol style="list-style-type: none"> <li>3. The <code>bootblk</code> program finds and executes the secondary boot program, <code>ufsboot</code>, and loads it into memory.</li> <li>4. After <code>ufsboot</code> program is loaded, the <code>ufsboot</code> program loads the kernel.</li> </ol>
Kernel Initialization	<ol style="list-style-type: none"> <li>5. The kernel initializes itself and begins loading modules, using <code>ufsboot</code> to read the files. When the kernel has loaded enough modules to mount the root file system, it unmaps the <code>ufsboot</code> program and continues, using its own resources.</li> <li>6. The kernel creates a user process and starts the <code>/sbin/init</code> process, which starts other processes by reading the <code>/etc/inittab</code> file.</li> </ol>
<code>init</code>	<ol style="list-style-type: none"> <li>7. The <code>/sbin/init</code> process starts the run control (<code>rc</code>) scripts, which execute a series of other scripts. These scripts (<code>/sbin/rc*</code>) check and mount file systems, start various processes, and perform system maintenance tasks.</li> </ol>

## x86: The PC BIOS

Before the kernel is started, the system is controlled by the read-only-memory (ROM) Basic Input/Output System (BIOS), the firmware interface on a PC.

Hardware adapters can have an onboard BIOS that displays the physical characteristics of the device and can be used to access the device.

During the startup sequence, the PC BIOS checks for the presence of any adapter BIOS and if found, loads and executes each one. Each individual adapter's BIOS runs self-test diagnostics and displays device information.

## x86: Boot Subsystems

At three times during the Solaris boot process, you can make the following choices about a booting system:

- **Primary Boot Subsystem (Partition Boot Menu)** —This first menu appears if multiple bootable `fdisk` partitions exist on the disk. The menu enables you to boot from one of the `fdisk` partitions. By default, the active partition will be booted if no action is taken.

Note that if you choose to boot a non-Solaris partition, the next two menus will not be reached.

- **Interrupt the Autoboot Process**—If the autoboot process is interrupted, you can access the Configuration Assistant.

The Configuration Assistant enables you to boot the Solaris system from a different boot device, configure new or misconfigured hardware, or perform other device- or boot-related tasks.

- **Current Boot Parameters Menu**—Two forms of this menu exist, one for a normal Solaris boot and one for a Solaris installation boot:
  - The normal Current Boot Parameters menu enables you to boot the Solaris system with options or enter the boot interpreter.
  - The install Current Boot Parameters menu enables you to select the type of installation to be performed or customize the boot.

Table 10-3 summarizes the purpose of the primary x86 boot interfaces. See the sections that follow for a detailed description and example of each boot subsystem.

**TABLE 10-3** Boot Subsystems

Boot Subsystem	Purpose
Primary Boot Subsystem	This menu appears if the disk you are booting from contains more than one <code>fdisk</code> partition, in addition to the Solaris <code>fdisk</code> partition.
Secondary Boot Subsystem	This menu appears each time you boot the Solaris release. The Solaris release is booted automatically unless you choose to run the Solaris Device Configuration Assistant by interrupting the autoboot process.

**TABLE 10-3** Boot Subsystems *(continued)*

Boot Subsystem	Purpose
Solaris Device Configuration Assistant/Boot Diskette	There are two ways to access the Solaris Device Configuration Assistant menus: <ol style="list-style-type: none"> <li>1. Use the Solaris Device Configuration Assistant Boot Diskette to boot the system.</li> <li>2. Interrupt the autoboot process when booting Solaris from an installed disk.</li> </ol>
Current Boot Parameters Menu	This menu appears when you boot from a disk with the Solaris operating environment installed or if you want to install the Solaris release from the Solaris installation CD or the network. In either case, this menu presents a list of boot options.

During the boot process, the boot subsystem menus allow you to customize boot choices. If the system receives no response during the time-out periods, it continues to boot automatically using default selections. You can stop the boot process when each boot subsystem menu is displayed or you can let it continue automatically.

The following section provides examples of each subsystem screen.

## x86: Booting Solaris

During the device identification phase, the Configuration Assistant:

- Scans for devices installed on the system
- Displays the identified devices
- Enables you to perform optional tasks such as selecting a keyboard type and editing devices and their resources

During the Boot phase, the system:

- Displays a list of devices from which to boot. The device marked with an asterisk (\*) is the default boot device.
- Enables you to perform optional tasks, such as editing autoboot and property settings.

Examples of device identification during each phase are provided below. Device output varies based on your system configuration.

## x86: Menus Displayed During the Device Identification Phase

Several menus are displayed as the Configuration Assistant attempts to identify devices on the system.

### x86: Configuration Assistant Menu

This menu appears each time you run the Configuration Assistant.

```
Solaris Device Configuration Assistant

The Solaris(TM) (Intel Platform Edition) Device Configuration Assistant
scans to identify system hardware, lists identified devices, and can
boot the Solaris software from a specified device. This program must be
used to install the Solaris operating environment, add a Driver Update,
or change the hardware on the system.

> To perform a full scan to identify all system hardware, choose Continue.

> To diagnose possible full scan failures, choose Specific Scan.

> To add new or updated device drivers, choose Driver Update.

About navigation...
- The mouse cannot be used.
- If the keyboard does not have function keys or they do not respond,
  press ESC. The legend at the bottom of the screen will change to
  show the ESC keys to use for navigation.
- The F2 key performs the default action.

F2_Continue  F3_Specific Scan  F4_Driver Update  F6_Help
```

### *x86: Bus Enumeration Menu*

The Bus Enumeration menu appears briefly while the Configuration Assistant gathers hardware configuration data for devices that can be detected automatically.

```
Bus Enumeration

Determining bus types and gathering hardware configuration data ...

Please wait ...
```

## *x86: Scanning Devices Menu*

The Scanning Devices menu appears while the Configuration Assistant manually scans for devices that can only be detected with special drivers.

```
Scanning Devices

The system is being scanned to identify system hardware.

If the scanning stalls, press the system's reset button. When the
system reboots, choose Specific Scan or Help.

Scanning: Floppy disk controller

#####
|      |      |      |      |      |
0      20     40     60     80     100

Please wait ...
```

## *x86: Identified Devices Menu*

The Identified Devices menu displays which devices have been identified on the system. From here, you can continue to the "Boot Solaris" menu or perform optional tasks, such as set a keyboard configuration, view and edit devices, set up a serial console, and save and delete configurations.

```
Identified Devices

The following devices have been identified on this system. To identify
devices not on this list or to modify device characteristics, such as
keyboard configuration, choose Device Tasks. Platform types may be
included in this list.

EISA: Adaptec 1740/1742 SCSI controller
EISA: Motherboard
EISA: SMC EtherCard Elite32C Ethernet adapter
ISA: Floppy disk controller
ISA: Game port (Joy stick)
ISA: PCMCIA controller
ISA: Parallel port
ISA: Serial port
ISA: System keyboard (US-English)
ISA: VGA w/ 8514/A compatible graphics adapter

F2_Continue  F3_Back   F4_Device Tasks  F6_Help
```

(continued)

(Continuation)

## x86: Menus Displayed During the Boot Phase

During this phase, you can determine the way in which the system is booted.

### x86: Boot Solaris Menu

The Boot Solaris menu allows you to select the device from which to boot the Solaris release. You can also perform optional tasks, such as view and edit autoboot and property settings. Once a boot device is selected and you choose Continue, the Solaris kernel will begin to boot.

```
Boot Solaris

Select one of the identified devices to boot the Solaris kernel and
choose Continue.

To perform optional features, such as modifying the autoboot and property
settings, choose Boot Tasks.

An asterisk (*) indicates the current default boot device.

> To make a selection use the arrow keys, and press Enter to mark it [X].

[ ] DISK: Target 0, IMPRIMIS 94241-7    0888
    on Adaptec 1740/1742 SCSI controller in EISA Slot 4
[ ] CD  : Target 2, TOSHIBA  CD-ROM XM-3501TA 3054
    on Adaptec 1740/1742 SCSI controller in EISA Slot 4
[ ] NET : SMC EtherCard Elite32C Ethernet adapter
    in EISA Slot 6

F2_Continue  F3_Back    F4_Boot Tasks  F6_Help
```

### x86: Solaris Boot Options Menu

This menu appears each time you boot Solaris from the local disk. Let the five-second timeout elapse if you want to boot the default Solaris kernel. If you want to boot with different options, select an appropriate option before the timeout period elapses.

```
<<< Current Boot Parameters >>>
Boot path: /eisa/eha@1,4000/sd@0,0:a
Boot args:

Type      b [file-name] [boot-flags] <ENTER>      to boot with options
or        i <ENTER>                                to enter boot interpreter
or        <ENTER>                                  to boot with defaults

<<< timeout in 5 seconds >>>

Select (b)oot or (i)nterpreter:
```

# x86: The Boot Process

TABLE 10-4 x86: The Boot Process

BIOS Phase	The PC BIOS loads and executes any hardware device's BIOS.
	The BIOS boot program loads and executes the master boot record, mboot.
Boot Programs Phase	mboot loads pboot, the Solaris boot partition, boot program.
	pboot loads bootblk, the primary boot program.
	bootblk reads the fdisk table to locate the default boot partition. The Primary Boot Subsystem menu is displayed at this time.
	bootblk loads the secondary boot program, boot.bin or ufsboot. You can press the ESC key to enter the Configuration Assistant Menu at this point.

TABLE 10-4 x86: The Boot Process (continued)

	The secondary boot program, <code>boot.bin</code> or <code>ufsboot</code> , reads the <code>/etc/bootrc</code> script, which loads the kernel. The Solaris Boot options menu is displayed at this time.
Kernel Initialization Phase	The kernel initializes itself and loads the modules needed to mount the root ( <code>/</code> ) file system. The kernel starts the <code>init</code> process.
init Phase	The <code>init</code> process starts the run control scripts.

# x86: The Boot Process Details

Table 10-5 describes the x86 boot process illustrated above.

TABLE 10-5 Description of x86 Boot Process

Boot Phase	Description
BIOS	<p>1. When the system is turned on, the PC BIOS runs self-test diagnostics to verify the system's hardware and memory. The system begins to boot automatically if no errors are found. If errors are found, error messages are displayed describing recovery options.</p> <p>Additional hardware devices' BIOS are run at this time.</p> <p>2. The BIOS boot program tries to read the first physical sector from the boot device—either a diskette or hard drive. This first disk sector on the boot device contains the master boot record <code>mboot</code>, which is loaded and executed. If no <code>mboot</code> file is found, an error message is displayed.</p>



**TABLE 10-5** Description of x86 Boot Process *(continued)*

Boot Phase	Description
Boot Programs	<p>3. <code>mboot</code>, which contains disk information needed to find the active partition and the location of the Solaris boot program, <code>pboot</code>, loads and executes <code>pboot</code>.</p> <p>4. <code>pboot</code> loads <code>bootblk</code>, the primary boot program, whose purpose is to load the secondary boot program located in the <code>ufs</code> file system.</p> <p>5. If there is more than one bootable partition, <code>bootblk</code> reads the <code>fdisk</code> table to locate the default boot partition, and builds and displays a menu of available partitions. You have a 30-second timeout interval to select an alternate partition from which to boot. This step only occurs if there is more than one bootable partition present on the system.</p> <p>6. <code>bootblk</code> finds and executes the secondary boot program, <code>boot.bin</code> or <code>ufsboot</code>, in the root file system. You have a 5-second timeout interval to interrupt the autoboot to start the Configuration Assistant.</p> <p>7. The secondary boot program, <code>boot.bin</code> or <code>ufsboot</code>, starts a command interpreter that executes the <code>/etc/bootrc</code> script, which provides a menu of choices for booting the system. The default action is to load and execute the kernel. You have a 5-second timeout interval to specify a boot option or start the boot interpreter.</p>
Kernel Initialization	<p>8. The kernel initializes itself and begins loading modules, using the secondary boot program (<code>boot.bin</code> or <code>ufsboot</code>) to read the files. When the kernel has loaded enough modules to mount the root file system, it unmaps the secondary boot program and continues, using its own resources.</p> <p>9. The kernel creates a user process and starts the <code>/sbin/init</code> process, which starts other processes by reading the <code>/etc/inittab</code> file.</p>
init	<p>10. The <code>/sbin/init</code> process starts the run control (<code>rc</code>) scripts, which execute a series of other scripts. These scripts (<code>/sbin/rc*</code>) check and mount file systems, start various processes, and perform system maintenance tasks.</p>



## PART **IV** Managing Removable Media

---

This part provides instructions for using removable media in the Solaris environment. This part contains these chapters.

Chapter 11	Provides general information about using CDs and diskettes, including a comparison of automatic and manual mounting.
Chapter 12	Provides step-by-step instructions for using CDs from the command line, plus instructions for starting and stopping Volume Management.
Chapter 13	Provides step-by-step instructions for formatting and using diskettes from the command line.
Chapter 14	Provides step-by-step instructions for formatting and using PCMCIA memory cards from the command line.
Chapter 15	Provides a high-level description of how the Solaris environment creates special mount points and symbolic links to provide easy access to diskettes and CDs.



## Guidelines for Using CDs and Diskettes (Overview)

---

This chapter provides general guidelines for using diskettes and CDs in the Solaris environment.

This is a list of overview information in this chapter.

- “Where to Find Managing Removable Media Tasks” on page 171
- “Features and Benefits” on page 172
- “Comparison of Automatic and Manual Mounting” on page 172
- “What You Can Do With Diskettes and CDs” on page 173

---

## Where to Find Managing Removable Media Tasks

Use these references to find step-by-step instructions for managing removable media.

- Chapter 12
- Chapter 13
- Chapter 14

For information on using removable media with File Manager in the OpenWindows environment or the Common Desktop Environment, see:

- *OpenWindows User's Guide*
- *Solaris Common Desktop Environment: User's Guide*

---

## Features and Benefits

The Solaris environment gives users and software developers a standard interface for dealing with diskettes and CDs. Referred to as Volume Management, this interface provides three major benefits:

- By automatically mounting diskettes and CDs, it simplifies their use. (For a comparison between manual and automatic mounting, see Table 11–1.)
- It enables you to access diskettes and CDs without having to become superuser.
- It allows you to give other systems on the network automatic access to any diskettes and CDs you insert into your system (see Chapter 12 and Chapter 13).

---

## Comparison of Automatic and Manual Mounting

Table 11–1 compares the steps involved in manual mounting (without Volume Management) and automatic mounting (with Volume Management).

**TABLE 11–1** Comparison of Manual and Automatic Mounting

Steps	Manual Mounting	Automatic Mounting
1	Insert media.	Insert media.
2	Become superuser.	For diskettes, use the <code>volcheck</code> command.
3	Determine the location of the media device.	<i>Volume Management automatically performs many of tasks previously required to manually mount and work with CDs and diskettes.</i>
4	Create a mount point.	
5	Make sure you are not in the mount point directory.	
6	Mount the device using the proper <code>mount</code> options.	

**TABLE 11-1** Comparison of Manual and Automatic Mounting *(continued)*

Steps	Manual Mounting	Automatic Mounting
7	Exit the superuser account.	
8	Work with files on media.	Work with files on media.
9	Become superuser.	
10	Unmount the media device.	
11	Eject media.	Eject media.
12	Exit the superuser account.	

## What You Can Do With Diskettes and CDs

Essentially Volume Management enables you to access diskettes and CDs just as manual mounting does, but more easily and without the need for superuser access. To make diskettes and CDs easier to work with, they are mounted in easy-to-remember locations.

**TABLE 11-2** How to Access Data on Diskettes and CDs

To Access ...	Insert ...	And Find The Files In ...
Files on a diskette	The diskette and enter volcheck	/vol/dev/aliases/floppy0
Raw data on a diskette	The diskette and enter volcheck	/vol/dev/aliases/floppy0
Files on a CD	The CD and wait for a few seconds	/cdrom/cdrom0

If your system has more than one diskette or CD-ROM drive, see Table 11-3 for their access points.

**TABLE 11-3** Where to Access Diskettes and CDs

Media Device	Access File Systems On...	Access Raw Data On...
First diskette drive	/floppy/floppy0	/vol/dev/aliases/floppy0
Second diskette drive	/floppy/floppy1	/vol/dev/aliases/floppy1
First CD-ROM drive	/cdrom/cdrom0	/vol/dev/aliases/cdrom0
Second CD-ROM drive	/cdrom/cdrom1	/vol/dev/aliases/cdrom1



## Using CDs From the Command Line (Tasks)

---

This chapter describes all the tasks required to use CDs in the Solaris environment from the command line. This is a list of the step-by-step instructions in this chapter.

- “How to Load a CD” on page 177
- “How to Examine the Contents of a CD” on page 177
- “How to Copy Information From a CD” on page 177
- “How to Find Out If a CD Is Still in Use” on page 178
- “How to Eject a CD” on page 179
- “How to Access CDs on Other Systems” on page 180
- “How to Make Local CDs Available to Other Systems” on page 181
- “How to Configure a System to Play Musical CDs” on page 184
- “How to Prepare a System for a New CD-ROM Drive” on page 185
- “How to Stop Volume Management” on page 186
- “How to Restart Volume Management” on page 186

---

## Using CDs Task Map

**TABLE 12-1** Task Map: Using CDs

Task	Description	For Instructions, Go To
1. Load the CD	Insert the CD into the CD-ROM drive.	"How to Load a CD" on page 177
2. Examine Its Contents	<i>Optional.</i> To examine the contents of the CD, look in the appropriate directory under / <code>cdrom</code> .	"How to Examine the Contents of a CD" on page 177
3. Copy Files or Directories	<i>Optional.</i> Copy files or directories from the CD as you would from any other location in the file system.	"How to Copy Information From a CD" on page 177
4. Is CD Still in Use?	<i>Optional.</i> Before ejecting the CD, find out if it is still in use.	"How to Find Out If a CD Is Still in Use" on page 178
5. Eject the CD	When you finish, eject the CD from the CD-ROM drive.	"How to Eject a CD" on page 179

## Using CD Names

When working with CDs, you can identify them by name or with a designator from Table 12-2 below. For brevity, task descriptions use `cdrom0`, but you can replace this with either the CD name or a different designator.

**TABLE 12-2** How to Identify CDs

CD	Alternate Name
First CD-ROM drive	<code>cdrom0</code>
Second CD-ROM drive	<code>cdrom1</code>
Third CD-ROM drive	<code>cdrom2</code>

## ▼ How to Load a CD

Insert the CD. Shortly after the light stops flashing (about five to ten seconds), the CD is mounted to `/cdrom`. To verify that the CD is mounted, perform the task “How to Examine the Contents of a CD” on page 177.

---

**Note** - Most CDs are formatted to the ISO 9660 standard, which is portable, so most CDs can be mounted by Volume Management. However, as described in Chapter 15, UFS CDs are not portable between architectures, so they must be used on the architecture for which they were designed. If you are having trouble mounting a CD, particularly if it is an installation CD, make sure its UFS file system is appropriate for your system’s architecture (check the label on the CD).

---

## ▼ How to Examine the Contents of a CD

Use the `ls -L` command to view the contents of `/cdrom` directory.

```
$ ls -L [-l] /cdrom/cdrom0
```

-L	Includes symbolic links in the output.
-l	Long format. Includes permissions and owners in the output.

### Example—Examining the Contents of a CD

The following example lists the contents of the CD loaded into the first CD-ROM directory, `/cdrom/cdrom0`.

```
$ ls -L -l /cdrom/cdrom0
dr-xr-xr-x  2  root   sys   2048  Dec 31  1993  tools
dr-xr-xr-x  2  root   sys   2048  Dec 31  1993  graphics
```

## ▼ How to Copy Information From a CD

You can access a CD’s files and directories just like any other file system. The only significant restrictions are ownership and permissions. For instance, if you copy a file from a CD into your file system, you’ll be the owner, but you won’t have write permissions (because the file never had them on the CD); you’ll have to change the permissions yourself.

### 1. Make sure the CD is mounted.

```
$ ls /cdrom
```

The `ls` command displays the contents of a mounted CD. If no contents are displayed, see “How to Load a CD” on page 177.

## 2. Copy the files or directories.

To Copy ...	Use ...
A file	<code>cp</code>
A directory	<code>cp -r</code>

## Example—Copying Information From a CD

The following example uses `cp` to copy a single file from the `/cdrom/solstice_sysmgt_2_3` directory into the system’s working directory (denoted by the `.`).

```
$ cp /cdrom/solstice_sysmgt_2_3/README .
$ ls -l
-r--r--r--  1 pmorph  users      4618 May  9 08:09 README
```

Note that when a file or directory is copied from a CD into your file system, you become its owner, but it retains the permissions it had on the CD:

```
-r--r--r--
```

To overwrite it, you’ll need to change the permissions with the `chmod` command. See “Securing Files (Tasks)” in *System Administration Guide, Volume II* for more information on using the `chmod` command.

## ▼ How to Find Out If a CD Is Still in Use

### 1. Become superuser.

### 2. Enter the `fuser(1M)` command.

The `fuser` command lists the processes that are currently accessing the CD that you specify.

```
# fuser -u [-k] /cdrom/cdrom0
```

<code>-u</code>	Displays the user of the CD.
<code>-k</code>	Kills the process accessing the CD.

The `fuser` command may not always identify all the killed processes. To be sure, run it again with the `-u` option.

## Example—Finding Out If a CD Is Still in Use

In the following example, the processes `6400c` and `6399c` are accessing the `/cdrom/cdrom0` directory, and the process owners are `root` and `smith`, respectively.

```
# fuser -u /cdrom/cdrom0
/cdrom/cdrom0: 6400c(root) 6399c(smith)
```

You can kill the processes individually (as superuser), or you can use the `fuser` command with the `-k` option, which kills all the processes accessing that file system, as shown in the following example.

```
# fuser -u -k /cdrom/cdrom0
/cdrom/cdrom0: 6400c(root)Killed 6399c(smith)Killed
```

## ▼ How to Eject a CD

### 1. Make sure the CD is not being used.

Remember, a CD is “being used” if a shell or an application is accessing any of its files or directories. If you are not sure whether you have found all users of a CD (a shell hidden behind a desktop tool may be accessing it), use the `fuser` command, as described in “How to Find Out If a CD Is Still in Use” on page 178.

### 2. Eject the CD.

```
# eject cdrom0
```

## ▼ How to Access CDs on Other Systems

You can access a CD on another system by mounting it manually into your file system—provided the other system has shared its CD-ROM according to the instructions in “How to Make Local CDs Available to Other Systems” on page 181.

1. **Select an existing directory to serve as the mount point or create one.**

```
$ mkdir directory
```

*directory*

The name of the directory that you create to serve as a mount point for the other system's CD.

2. **Find the name of the CD you want to mount.**

When you manually mount a remote CD, you cannot use the `cdrom0` or `cdrom1` variables available with your local CDs. You must use the exact CD name. To find it, use the `ls` command on the remote system's `/cdrom` directory. If the automounter is running, you can simply `cd` to the system whose CD you want to mount and then use the `ls` command. If the automounter is not running, you'll have to use another method, such as logging in remotely.

3. **As superuser, mount the CD.**

```
# mount -F nfs -o ro system-name:/cdrom/cd-name local-mount-point
```

*system-name*

The name of the system whose CD you will mount.

*cd-name*

The name of the CD you want to mount.

*local-mount-point*

The local directory onto which you will mount the remote CD.

4. **Log out as superuser.**
5. **Verify that the CD is mounted by using the `ls` command to list the contents of the mount point.**

```
$ ls /cdrom
```

## Example—Accessing CDs on Other Systems

**Note** - The name of this release is Solaris 7 but code and path or package path names may use Solaris 2.7 or SunOS 5.7. Always follow the code or path as it is written.

This example mounts the CD named `Solaris_2.7_sparc` from the remote system `mars` onto the `/cdrom` directory of the local system.

```
$ cd /net/mars
$ ls /cdrom
cdrom0      Solaris_2.7_sparc
$ su
Password: password
# mount -F nfs ro mars:/cdrom/Solaris_2.7_sparc /cdrom
# exit
$ ls /cdrom
Solaris_2.7_sparc
```

## ▼ How to Make Local CDs Available to Other Systems

You can configure your system to share its CD-ROM drives; in other words, make any CDs in those drives available to other systems. (This does not apply to musical CDs.) Once your CD-ROM drives are shared, other systems can access the CDs they contain simply by mounting them, as described in “How to Access CDs on Other Systems” on page 180.

1. Become superuser.
2. Find out whether the NFS daemon (`nfsd`) is running.

```
# ps -ef | grep nfsd
root 14533    1 17 10:46:55 ?        0:00 /usr/lib/nfs/nfsd -a 16
root 14656   289  7 14:06:02 pts/3  0:00 grep nfsd
```

If the daemon is running, a line for `/usr/lib/nfs/nfsd` will appear, as shown above. If the daemon is not running, only the `grep nfsd` line will appear.

3. Select an option from the following table.

If ...	Then ...
nfsd is running	Go to Step 8 on page 182
nfsd is <i>not</i> running	Continue with Step 4 on page 182

**4. Create a dummy directory for nfsd to share.**

```
# mkdir /dummy-dir
```

*dummy-dir*

Can be any directory name; for example, *dummy*. This directory will not contain any files. Its only purpose is to “wake up” the NFS daemon so that it notices your shared CD-ROM.

**5. Add the following entry into /etc/dfs/dfstab.**

```
share -F nfs -o ro [-d comment] /dummy-dir
```

When you start the NFS daemon, it will see this entry, “wake up,” and notice the shared CD-ROM drive. Note that the comment (preceded by *-d*) is optional.

**6. Start the NFS daemon.**

```
# /etc/init.d/nfs.server start
```

**7. Verify that the NFS daemon is indeed running.**

```
# ps -ef | grep nfsd
root 14533      1 17 10:46:55 ?        0:00 /usr/lib/nfs/nfsd -a 16
root 14656    289  7 14:06:02 pts/3  0:00 /grep nfsd
```

**8. Eject any CD currently in the drive.**

```
# eject cdrom0
```



**9. Assign root write permissions to `/etc/rmmount.conf`.**

```
# chmod 644 /etc/rmmount.conf
```

**10. Add the following lines to `/etc/rmmount.conf`.**

```
# File System Sharing  
share cdrom*
```

These lines share any CD loaded into your system's CD-ROM drive. You can, however, limit sharing to a particular CD or series of CDs, as described in **share(1M)**.

**11. Remove write permissions from `/etc/rmmount.conf`.**

```
# chmod 444 /etc/rmmount.conf
```

This step returns the file to its default permissions.

**12. Load a CD.**

The CD you now load, and all subsequent CDs, will be available to other systems. Remember to wait until the light on the drive stops blinking before you verify this task.

To access the CD, the remote user must mount it by name, according to the instructions in "How to Access CDs on Other Systems" on page 180.

**13. Verify that the CD is indeed available to other systems by using the `share` command.**

If the CD is available, its share configuration will be displayed. (The shared dummy directory will also be displayed.)

```
# share  
- /dummy ro "dummy dir to wake up NFS daemon"  
- /Solaris_2.7_sparc ro ""
```

## Example—Making Local CDs Available to Other Systems

The following example makes any CD loaded into the local system's CD-ROM drive available to other systems on the network.

```
# ps -ef | grep nfsd
  root 10127  9986  0 08:25:01 pts/2    0:00 grep nfsd
  root 10118      1  0 08:24:39 ?        0:00 /usr/lib/nfs/nfsd -a
# mkdir /dummy
# vi /etc/dfs/dfstab
(Add the following line:)
share -F nfs -o ro /dummy
# eject cdrom0
# chmod 644 /etc/rmmount.conf
# vi /etc/rmmount
(Add the following line to the File System Sharing section.)
share cdrom*
# chmod 444 /etc/rmmount.conf
(Load a CD.)
# share
-      /dummy ro ""
-      /cdrom/solaris_2_6_sparc/s5   ro   ""
-      /cdrom/solaris_2_6_sparc/s4   ro   ""
-      /cdrom/solaris_2_6_sparc/s3   ro   ""
-      /cdrom/solaris_2_6_sparc/s2   ro   ""
-      /cdrom/solaris_2_6_sparc/s1   ro   ""
-      /cdrom/solaris_2_6_sparc/s0   ro   ""
```

## ▼ How to Configure a System to Play Musical CDs

You can play musical CDs from a CD-ROM attached to your Solaris system. You'll need to access Workman, which is public domain software, and you must attach external speakers or headphones independently to the CD-ROM drive; speakers attached to the system hardware will not work.

Once you configure your system, you can play a musical CD simply by inserting it into the CD-ROM drive. The Workman control panel is automatically displayed on your desktop.

### 1. Become superuser.

### 2. Edit `/etc/rmmount.conf`.

Add the following line under `# Actions`, before the `cdrom` action, as shown in the example below.

```
# Actions
```

(Continuation)

```
action cdrom action_workman.so path/workman workman-options
```

*path*

The directory in which you have placed the Workman software.

*workman-options*

The options allowed by the Workman software

## Example—Configuring a System to Play Musical CDs

This example shows an `/etc/rmmount.conf` file modified to support the Workman software.

```
# @(#)rmmount.conf 1.3      96/05/10 SMI
#
# Removable Media Mounter configuration file.
#
# File system identification
ident hsfs ident_hsfs.so cdrom
ident ufs ident_ufs.so cdrom floppy rm SCSI pcmem
ident pcfs ident_pcfs.so floppy rm SCSI pcmem

# Actions
action cdrom action_workman.so /usr/dist/exe/workman
action cdrom action_filemgr.so
action floppy action_filemgr.so
action rm SCSI action_filemgr.so

# File System Sharing
share cdrom*
share floppy*
```

## ▼ How to Prepare a System for a New CD-ROM Drive

On a system that is properly booted with the `boot -r` command, Volume Management will automatically recognize a new CD-ROM drive. However, to make sure Volume Management always recognizes a new drive, create the `/reconfigure` file.

1. **Become superuser.**
2. **Create a file called `/reconfigure`.**

```
# touch /reconfigure
```

The `/reconfigure` file makes the Solaris environment check for the presence of any newly installed peripheral devices when you power on or boot your system. After that, Volume Management locates the new device and automatically manages it for you.

---

## Configuring Volume Management

Occasionally, you may want to manage diskettes or CDs without the help of Volume Management. This section describes how to stop and restart Volume Management.

### ▼ How to Stop Volume Management

1. **Make sure no diskettes or CDs are being used.**

If you are not sure whether you have found all users of the diskette or CD, use the `fuser` command, as described in “How to Find Out If a CD Is Still in Use” on page 178.

2. **Become superuser.**
3. **Enter the `volmgt stop` command.**

```
# /etc/init.d/volmgt stop
#
```

### ▼ How to Restart Volume Management

1. **Become superuser.**
2. **Enter the `volmgt start` command.**

```
# /etc/init.d/volmgt start  
volume management starting.
```



## Formatting and Using Diskettes From the Command Line (Tasks)

---

This chapter describes all the tasks required to format and use diskettes from the command line in the Solaris environment. This is a list of the step-by-step instructions in this chapter.

- “How to Format a UFS Diskette” on page 193
- “How to Place a UFS File System on a Diskette” on page 196
- “How to Format a DOS Diskette” on page 197
- “How to Load a Diskette” on page 200
- “How to Examine the Contents of a Diskette” on page 202
- “How to Copy or Move Information From a Diskette” on page 202
- “How to Copy or Move Information to a Diskette” on page 204
- “How to Find Out If a Diskette Is Still in Use” on page 205
- “How to Eject a Diskette” on page 206
- “How to Access Diskettes on Other Systems” on page 206
- “How to Make Local Diskettes Available to Other Systems” on page 208

---

## Formatting Diskettes Task Map

**TABLE 13–1** Task Map: Formatting Diskettes

Task	Description	For Instructions, Go To
1. Load Unformatted Diskette	Insert the diskette into the drive and enter the <code>volcheck</code> command.	“How to Load a Diskette” on page 200
2. Format the Diskette	Format the diskette for UFS.  Format the diskette for DOS.	“How to Format a UFS Diskette” on page 193  “How to Format a DOS Diskette” on page 197
3. Add a UFS File System	<i>UFS Only. Optional.</i> To use the diskette for files, add a UFS file system. To use for characters, skip this step.	“How to Place a UFS File System on a Diskette” on page 196
4. Eject the Diskette	When finished formatting, always eject the diskette, even if you are going to use it again right away.	“How to Eject a Diskette” on page 206

## Using Diskette Names

When working with diskettes, you can identify them by name or with a designator from Table 13–2. For brevity, task descriptions use `floppy0`, but you can replace this with either the diskette name or a different designator.

**TABLE 13–2** How to Identify Diskettes

Diskette	Alternate Name
First diskette drive	<code>floppy0</code>
Second diskette drive	<code>floppy1</code>
Third diskette drive	<code>floppy2</code>



---

**Note** - Diskettes that are not named (that is, they have no “label”) are assigned the default name of `noname`.

---

## Hardware Considerations

A Solaris system can format diskettes for use on both Solaris and DOS systems. However, the hardware platform imposes some limitations. They are summarized in the table below.

Solaris on this Platform ...	Can Format Diskettes For ...
Solaris on SPARC	Solaris on SPARC (UFS) MS-DOS or NEC-DOS (PCFS)
Solaris on x86	Solaris on x86 (UFS) MS-DOS or NEC-DOS (PCFS)

Diskettes formatted for UFS are restricted to the hardware platform on which they were formatted. In other words, a UFS diskette formatted on a SPARC platform cannot be used for UFS on an x86 platform, nor can a diskette formatted on an x86 platform be used on a SPARC platform. This is because the SPARC and x86 UFS formats are different. SPARC uses little-endian bit coding, x86 uses big-endian.

A complete format for SunOS file systems consists of the basic “bit” formatting plus the structure to support a SunOS file system. A complete format for a DOS file system consists of the basic “bit” formatting plus the structure to support either an MS-DOS or an NEC-DOS file system. The procedures required to prepare a diskette for each type of file system are different. Therefore, before you format a diskette, consider which procedure to follow. See “Formatting Diskettes Task Map” on page 189.

On a Solaris system (either SPARC or x86), you can format diskettes of seven different densities (provided you have the appropriate drive).

Diskette Size	Diskette Density	Capacity
3.5”	Extended Density	2.88 Mbytes
3.5”	High Density (HD)	1.44 Mbytes
3.5”	Medium Density (DD)	1.2 Mbytes
3.5”	Low Density	720 Kbytes

Diskette Size	Diskette Density	Capacity
5.25"	High Density (HD)	1.2 Mbytes
5.25"	Medium Density (DD)	720 Kbytes
5.25"	Low Density	360 Kbytes

By default, the diskette drive formats a diskette to a like density. In other words, a 1.44 Mbyte drive attempts to format a diskette for 1.44 Mbytes, whether the diskette is in fact a 1.44 Mbyte diskette or not—unless you instruct it otherwise. You can tell a 1.44 Mbyte drive to format a diskette to, for instance, 720 Kbytes. You cannot, however, instruct a 720 Kbyte drive to format a diskette to 1.44 Mbyte. In other words, a diskette can be formatted to its capacity or lower, and a drive can format to its capacity or lower.

To instruct a drive to format a diskette to a non-default density, use the `fdformat` command as instructed in the following tasks, but use the appropriate density option from Table 13-3, below.

**TABLE 13-3** Density Options

To Format a Diskette With This Density ...	In a Drive With This Default Density ...	Use This Density Option to the <code>fdformat</code> Command ...
2.88 Mbytes	2.88 Mbytes	<code>-E</code>
1.44 Mbytes	2.88 Mbytes	<code>-H</code>
1.44 Mbytes	1.44 Mbytes	<code>none</code>
1.2 Mbytes	1.44 Mbytes	<code>-t nec -M</code>
720 Kbytes	1.44 Mbytes	<code>-D</code> or <code>-t dos -D</code>
1.2 Mbytes	1.2 Mbytes	<code>none</code>
720 Kbytes	1.2 Mbytes	<code>-D</code>
720 Kbytes	720 Kbytes	<code>none</code>
360 Kbytes	720 Kbytes	<code>-D</code>

To view all the options to the `fdformat` command, either see `fdformat(1)` or enter `fdformat -z`. The `-z` option displays all the options to the command.

If you don't know the default density of your drive, begin the formatting process with the default setting (that is, no density options) and observe the configuration message. It will look something like this:

```
Formatting 1.44 M in /vol/dev/rdiskette0/unformatted
Press return to start formatting floppy.
```

The confirmation message indicates the drive's default density. For instance, in the example above, the default density of the drive is 1.44 Mbytes. If the density is not what you expected, use Control-c to escape the formatting process and start over.

## ▼ How to Format a UFS Diskette

As mentioned in “Hardware Considerations” on page 191, a UFS diskette formatted on a SPARC platform can only be used on another SPARC platform, and a UFS diskette formatted on an x86 platform can only be used on an x86 platform running Solaris.



---

**Caution** - Formatting a diskette erases any pre-existing content.

---

### 1. Quit File Manager.

File Manager automatically displays a formatting window when you insert an unformatted diskette. Unfortunately, File Manager formatting is unreliable. To avoid the window, quit from File Manager. If you prefer to keep File Manager open, quit the formatting window when it appears.

### 2. Make sure the diskette is write-enabled.

On both 3.5-inch and 5.25 inch diskettes, write-protection is controlled by a small tab in either the lower left or lower right corner. If you can see through the square hole behind the tab, the diskette is write-protected. If the hole is covered by the tab, the diskette is write-enabled. (If you need to eject the diskette to examine it, simply type `eject floppy` in a shell.)

### 3. Insert the diskette.

Make sure the diskette is completely inserted.

### 4. Invoke formatting.

```
$ fdformat -v -U [density-options convenience-options]
```

<code>-v</code>	Verifies whether the diskette was formatted correctly.
<code>-U</code>	Unmounts the diskette if it is mounted.
<i>density-options</i>	If the drive density is 1.44 Mbytes, <i>density-options</i> are:
<code>—none—</code>	Formats a 1.44 Mbyte diskette.
<code>-D</code>	Formats a 720 Kbyte diskette.
	A complete list of <i>density-options</i> appears in Table 13-3.
<i>convenience-options</i>	
<code>-e</code>	Ejects the diskette when done formatting.
<code>-f</code>	Forces formatting without asking for confirmation.
<code>-b label</code>	Names the diskette. <i>label</i> must be eight characters or less, upper or lower case.
<code>-z</code>	Lists all the options to the <code>fdformat</code> command, but does not format the diskette.

---

**Note** - If you try to format a 720 Kbyte (DD) diskette for 1.44 Mbytes, `fdformat` will not stop you unless you include the `-v` option. With the `-v` option, `fdformat` will format the diskette, but the verification will catch the error and notify you with the following message:  
`fdformat: check diskette density, I/O error`

---

The `fdformat` command displays a confirmation message (unless you used the `-f` option), indicating the type of formatting to be performed:

```
Formatting 1.44 M in /vol/dev/rdiskette0/unformatted
Press return to start formatting floppy.
```

**5. Select one of the options in the table below.**



## ▼ How to Place a UFS File System on a Diskette

Even though the procedure for adding a UFS file system is the same for UFS diskettes formatted on x86 platforms and SPARC platforms, a UFS diskette formatted on a SPARC platform can only be used on another SPARC platform, and a UFS diskette formatted on an x86 platform can only be used on an x86 platform running Solaris.

### 1. Format the diskette for a UFS file system.

Use “How to Format a UFS Diskette” on page 193.

### 2. Create a SunOS file system on the diskette.

```
$ /usr/sbin/newfs -v /vol/dev/aliases/floppy0
```

`-v` Prints status messages.

`/vol/dev/aliases/floppy0` Indicates the location of the floppy.

The **newfs(1M)** command displays a message asking you to confirm the creation of the file system.

### 3. Confirm the creation of the file system.

```
newfs: construct a new file system
/vol/dev/aliases/floppy0:(y/n)? y
```

A status message is displayed, indicating the particulars of the file system and the diskette's formatting.

The diskette is now ready to be used on a SPARC platform. However, before Volume Management recognizes it, you must run the **volrmmount** command, as described in the following steps.

### 4. Invoke the **volrmmount** command using the **-i** option to notify Volume Management that the diskette is inserted.

```
$ volrmmount -i floppy0
```

### 5. Verify that the UFS file system is on the diskette by using the **ls** command on the **/floppy** directory.

If the floppy0 subdirectory appears, the diskette has a UFS file system and has been mounted properly.

```
$ ls /floppy
floppy0
```

## Example—Placing a UFS File System on a Diskette

```
$ volcheck -v
media was found
$ /usr/sbin/newfs -v /vol/dev/aliases/floppy0
newfs: construct a new file system /vol/dev/aliases/floppy0: (y/n)? y
mkfs -F ufs /vol/dev/aliases/floppy0 2880 18 2 8192 1024 16 10 5 2048
t 0 -1 8 15
/vol/dev/aliases/floppy0: 2880 sectors in 80 cylinders of 2 tracks,
18 sectors
      1.4MB in 5 cyl groups (16 c/g, 0.28MB/g, 128 i/g)
super-block backups (for fsck -F ufs -o b=#) at:
 32, 640, 1184, 1792, 2336,
$ volrmount -i floppy0
$ ls /floppy
floppy0
```

## ▼ How to Format a DOS Diskette

You can format a DOS diskette on a SPARC or x86 Solaris platform. The steps are similar, except that instead of a SunOS file system being placed on the diskette, a DOS file system, either MS-DOS or NEC-DOS, is put on the file system.



---

**Caution** - Formatting a diskette erases any pre-existing content.

---

### 1. Quit File Manager.

File Manager automatically displays a formatting window when you insert an unformatted diskette. Unfortunately, File Manager formatting is unreliable. To avoid the window, quit from File Manager. If you prefer to keep File Manager open, quit the formatting window when it appears.

### 2. Make sure the diskette is not write-protected.

On both 3.5-inch and 5.25 inch diskettes, write-protection is controlled by a small tab in either the lower left or lower right corner. If you can see through the square hole behind the tab, the diskette is write-protected. If the hole is covered

by the tab, the diskette is write-enabled. (If you need to eject the diskette to examine it, simply type `eject floppy` in a shell.)

### 3. Insert the diskette.

Make sure the diskette is completely inserted. It must drop down into the drive.

### 4. Invoke formatting.

```
$ fdformat -v -U [density-options convenience-options]
```

<code>-v</code>	Verifies whether the diskette was formatted correctly.
<code>-U</code>	Unmounts the diskette if it is mounted.
<i>density-options</i>	If the drive density is 1.44 Mbytes, <i>density-options</i> are:
<code>-d</code>	Formats at 1.44 Mbytes for MS-DOS.
<code>-d -D</code>	Formats at 720 Kbytes for MS-DOS.
<code>-t nec -M</code>	Formats at 1.2 Mbytes for NEC-DOS.
	A complete list of <i>density-options</i> appears in Table 13-3.
<i>convenience-options</i>	
<code>-e</code>	Ejects the diskette when done formatting.
<code>-f</code>	Does not ask for confirmation before formatting.
<code>-b <i>label</i></code>	Name for the diskette. <i>label</i> must be eight characters or less, upper or lower case.
<code>-z</code>	Lists all the options to the <code>fdformat</code> command, but does not format the diskette.

---

**Note** - If you try to format a 720 Kbyte (DD) diskette for 1.44 Mbytes, `fdformat` will not stop you unless you include the `-v` option. With the `-v` option, `fdformat` will format the diskette, but the verification will catch the error and notify you with the following message:

```
fdformat: check diskette density, I/O error
```

---



The `fdformat` command displays a confirmation message, indicating the type of formatting to be performed:

```
Formatting 1.44 M in /vol/dev/rdiskette0/unformatted
Press return to start formatting floppy.
```

**5. Select one of the options in the table below.**

To ...	Press ...
Confirm the type of formatting	Return (unless you used the <code>-f</code> option in the previous step, in which case no confirmation is necessary).
Cancel formatting	Control-c.

As the formatting progresses, a series of dots is displayed. As the verification progresses, a series of V's appears beneath the dots. When the series stops, the formatting is complete and the diskette is ready for use on a DOS system.

6. Run the `volrmount(1)` command using the `-i` option to notify Volume Management that the diskette is inserted.

```
$ volrmmount -i floppy0
```

Volume Management mounts the diskette under `/floppy/floppy0`.

### Example—Formatting a DOS Diskette

The following example formats a 1.44 Mbyte MS-DOS diskette and assigns the diskette the name `myfiles`:

[illegible]

# Using Diskettes Task Map

TABLE 13-4 Task Map: Using Diskettes

Task	Description	For Instructions, Go To
1. Load the Diskette	Insert the diskette into its drive and enter the <code>volcheck</code> command.	"How to Load a Diskette" on page 200
2. Examine Its Contents	<i>Optional.</i> To examine the contents of the diskette, look in the appropriate directory under <code>/diskette</code> .	"How to Examine the Contents of a Diskette" on page 202
3. Exchange Files	<i>Optional.</i> Copy files or directories between the diskette and your file system.	"How to Copy or Move Information From a Diskette" on page 202  "How to Copy or Move Information to a Diskette" on page 204
4. Is Diskette Still in Use?	<i>Optional.</i> Before ejecting the diskette, find out if the diskette is still in use.	"How to Find Out If a Diskette Is Still in Use" on page 205
5. Eject the Diskette	When you finish, eject the diskette from its drive.	"How to Eject a Diskette" on page 206

## ▼ How to Load a Diskette

### 1. Make sure the diskette is formatted.

If you aren't sure, insert it and check the status messages in the console, as described in Step 3 on page 201. If you need to format the diskette, go to "How to Format a UFS Diskette" on page 193 or "How to Format a DOS Diskette" on page 197.

### 2. Insert the diskette.

Make sure the diskette is completely inserted. It must drop down into the drive. If the drive has a door, close it.

### 3. Notify Volume Management.

```
$ volcheck -v
media was found
```

Two status messages are possible:

media was found

Volume Management detected the diskette and will attempt to mount it in the `/floppy` directory.

If the diskette is formatted properly, no error messages appear in the console.

If the diskette is not formatted, the “media was found” message is still displayed, but the following error messages appear in the Console:

```
fd0: unformatted diskette or no diskette in
the drive
```

```
fd0: read failed (40 1 0)
```

```
fd0: bad format
```

You must format the diskette before Volume Management can mount it. Instructions are provided on “How to Format a UFS Diskette” on page 193 (for UFS) and “How to Format a DOS Diskette” on page 197 (for DOS).

no media was found

Volume Management did not detect a diskette. Make sure the diskette is inserted properly and run **volcheck**(1) again. If unsuccessful, check the diskette; it could be damaged. You can also try to mount the diskette manually.

### 4. Verify that the diskette was mounted by listing its contents.

```
$ ls /floppy
floppy0 myfiles
```

As described earlier, `floppy0` is a symbolic link to the actual name of the diskette; in this case, `myfiles`. If the diskette has no name but is formatted correctly, the system will refer to it as `unnamed_floppy`.

If nothing appears under the `/floppy` directory, the diskette was either not mounted or is not formatted properly. To find out, run the `mount` command and look for the line that begins with `/floppy` (usually at the end of the listing):

```
/floppy/name on /vol/dev/diskette0/name ...
```

If the line does not appear, the diskette was not mounted. Check the Console for error messages.

## ▼ How to Examine the Contents of a Diskette

Use the `ls -L` command because some directories under `/floppy` are symbolic links.

```
$ ls -L [-l] floppy0
```

`-L`

Includes symbolic links in the output

`-l`

Long format. Includes permissions and owners in the output.

### Example—Examining the Contents of a Diskette

The following example lists the contents of the diskette in the first floppy drive, identified by `floppy0`.

```
$ ls -L -l /floppy/floppy0
-rwxrwxrwx 1 smith staff 362284 Nov 16 20:54 text.doc
-rwxrwxrwx 1 smith staff 24562 Nov 16 12:20 art.gif
```

## ▼ How to Copy or Move Information From a Diskette

Once you have inserted a diskette, you can access its files and directories just as you would those of any other file system. The only significant restrictions are ownership and permissions. For instance, if you are not the owner of a file on a diskette, you

won't be able to overwrite that file on the diskette. Or, if you copy a file into your file system, you'll be the owner, but that file won't have write permissions (because it never had them on the diskette); you'll have to change the permissions yourself.

**1. Make sure the diskette is formatted and mounted.**

```
$ ls /floppy
floppy0  diskette-name
```

If the diskette is properly formatted and mounted, its name and the symbolic link will appear under `/floppy`.

If nothing appears under the `/floppy` directory, the diskette is not mounted. See “How to Load a Diskette” on page 200. The diskette might also need to be formatted. See “How to Format a UFS Diskette” on page 193 or “How to Format a DOS Diskette” on page 197.

**2. Copy the files or directories.**

To Copy ...	Use ...
A file	<code>cp</code>
A directory	<code>cp -r</code>

**3. Verify the copy or move operation by using the `ls` command.**

## Examples—Copying or Moving Information from a Diskette

The first example, below, moves a file (`readme.doc`) from the diskette to the current directory (indicated by the “.” symbol). The second example copies a file (`readme2.doc`) from the diskette to the current directory. The third example copies a directory (`morefiles`) and everything below it from the diskette to the current directory.

```
$ mv /floppy/floppy0/readme.doc .
$ cp /floppy/floppy0/readme2.doc .
$ cp -r /floppy/floppy0/morefiles .
```

## ▼ How to Copy or Move Information to a Diskette

### 1. Make sure the diskette is not write-protected.

On both 3.5-inch and 5.25 inch diskettes, write-protection is controlled by a small tab in either the lower left or lower right corner. If you can see through the square hole behind the tab, the diskette is write-protected. If the hole is covered by the tab, the diskette is write-enabled.

### 2. Make sure the diskette is formatted and mounted.

```
$ ls /floppy
floppy0  diskette-name
```

If the diskette is properly formatted and mounted, its name and the symbolic link, `floppy0`, will appear under `/floppy`.

If nothing appears under the `/floppy` directory, the diskette is not mounted. See “How to Load a Diskette” on page 200. The diskette might also need to be formatted. See “How to Format a UFS Diskette” on page 193 or “How to Format a DOS Diskette” on page 197.

### 3. Move or copy the files or directories.

To ...	Use ...
Copy a file	<code>cp</code>
Copy a directory	<code>cp -r</code>
Move a file or directory	<code>mv</code>

### 4. Verify a move or copy operation by using the `ls` command.

## Examples—Copying or Moving Information to a Diskette

The first example, below, moves a file (`readme.doc`) from the current directory to the diskette loaded into the first floppy drive (indicated by `/floppy/floppy0`). The second example copies a file (`readme2.doc`) from the current directory to the diskette loaded into the second floppy drive (indicated by `/floppy/floppy1`). The

third example copies a directory (morefiles) and its contents from the /home/smith/directory to the diskette loaded into the first floppy drive.

```
$ mv readme.doc /floppy/floppy0
$ cp readme2.doc /floppy/floppy1
$ cp -r /home/smith/morefiles /floppy/floppy0
```

## ▼ How to Find Out If a Diskette Is Still in Use

### 1. Become superuser.

### 2. Invoke the `fuser` command.

The `fuser` command lists the processes that are currently accessing the CD that you specify.

```
# fuser -u [-k] floppy0
```

`-u` Displays the user of the diskette.

`-k` Kills the process accessing the diskette.

## Example—Finding Out If a Diskette Is Still In Use

In the following example, the processes `6400c` and `6399c` are accessing the `/floppy/floppy0` directory, and the process owners are `root` and `smith`, respectively.

```
# fuser -u /floppy/floppy0
/floppy/floppy0: 6400c(root) 6399c(smith)
```

You can kill the processes individually (as superuser), or you can use the `fuser` command with the `-k` option, which kills all the processes accessing that file system. The `fuser` command may not always identify all the killed processes. To be sure, run it again with the `-u` option.

```
# fuser -u -k /floppy/floppy0
/floppy/floppy0: 6400c(root)Killed 6399c(smith)Killed
```

## ▼ How to Eject a Diskette

### 1. Make sure the diskette is not being used.

Remember, a diskette is “being used” if a shell or an application is accessing any of its files or directories.

If you are not sure whether you have found all users of a diskette (a renegade shell hidden behind a desktop tool may be accessing it), use the `fuser` command, as described in “How to Find Out If a Diskette Is Still in Use” on page 205.

### 2. Eject the diskette.

```
# eject floppy0
```

On a SPARC platform the floppy is physically ejected from its drive, but on an x86 platform you’ll have to eject the diskette by hand. If you are running Windows, look for an onscreen message that says you can now eject the diskette. If the diskette is still in use, the following message appears:

```
/vol/dev/rdiskette0/noname: Device busy
```

In this case, return to Step 1 and make sure no one is using the diskette, then eject it again.

If the diskette jams, eject it manually by inserting an unfolded paper clip about an inch into the small hole in the front of the drive.

## ▼ How to Access Diskettes on Other Systems

You can access a diskette on another system by mounting it manually into your file system—provided the other system has shared its diskette drive according to the instructions in “How to Make Local Diskettes Available to Other Systems” on page 208.

### 1. Select an existing directory to serve as the mount point or create one.

```
$ mkdir directory
```

*directory*

Is the name of the directory that you create to serve as a mount point for the other system’s diskette.



## 2. Find the name of the diskette you want to mount.

When you manually mount a remote diskette, you cannot use the `floppy0` or `floppy1` variables available with your local diskettes. You must use the exact diskette name. To find it, use the `ls` command on the remote system's `/floppy` directory. If the automounter is running, you can simply `cd` to the system whose diskette you want to mount and then use the `ls` command. If the automounter is not running, you'll have to use another method, such as logging in remotely.

## 3. As superuser, mount the diskette.

```
# mount -F nfs -o rw system-name:/floppy/diskette-name local-mount-point
```

<i>system-name</i>	The name of the system whose diskette you will mount.
<i>diskette-name</i>	The name of the diskette you want to mount
<i>local-mount-point</i>	The local directory onto which you will mount the remote diskette.

## 4. Log out as superuser.

## 5. Verify that the diskette is mounted by using the `ls` command to list the contents of the mount point.

```
$ ls /floppy
```

## Example—Accessing Diskettes on Other Systems

This example mounts the diskette named `myfiles` from the remote system `mars` onto the `/floppy` directory of the local system.

```
$ cd /net/mars
$ ls /floppy
floppy0      myfiles
$ su
Password: password
# mount -F nfs rw mars:/floppy/myfiles /floppy
# exit
$ ls /floppy
myfiles
```

(continued)

(Continuation)

## ▼ How to Make Local Diskettes Available to Other Systems

You can configure your system to share its diskettes; in other words, make any diskettes in those drives available to other systems. Once your diskette drives are shared, other systems can access the diskettes they contain simply by mounting them, as described in “How to Access Diskettes on Other Systems” on page 206.

1. **Become superuser.**
2. **Find out whether the NFS daemon (`nfsd`) is running.**

```
# ps -ef | grep nfsd
root 14533      1 17 10:46:55 ?        0:00 /usr/lib/nfs/nfsd -a 16
root 14656    289  7 14:06:02 pts/3  0:00 grep nfsd
```

If the daemon is running, a line for `/usr/lib/nfs/nfsd` will appear, as shown above. If the daemon is not running, only the `grep nfsd` line will appear.

3. **Select an option from the following table.**

If ...	Then ...
<code>nfsd</code> is running	Go to Step 8 on page 209
<code>nfsd</code> is <i>not</i> running	Continue with Step 4 on page 208

4. **Create a dummy directory for `nfsd` to share.**

```
# mkdir /dummy-dir
```

*dummy-dir*

Can be any directory name; for example, *dummy*. This directory will not contain any files. Its only purpose is to “wake up” the NFS daemon so that it notices your shared diskettes.

**5. Add the following entry into `/etc/dfs/dfstab`.**

```
share -F nfs -o ro [-d comment] /dummy-dir
```

When you start the NFS daemon, it will see this entry, “wake up,” and notice the shared diskette drive. Note that the comment (preceded by `-d`) is optional.

**6. Start the NFS daemon.**

```
# /etc/init.d/nfs.server start
```

**7. Verify that the NFS daemon is indeed running.**

```
# ps -ef | grep nfsd
root 14533    1 17 10:46:55 ?        0:00 /usr/lib/nfs/nfsd -a 16
root 14656   289  7 14:06:02 pts/3    0:00 /grep nfsd
```

**8. Eject any diskette currently in the drive.**

```
# eject floppy0
```

**9. Assign root write permissions to `/etc/rmmount.conf`.**

```
# chmod 644 /etc/rmmount.conf
```

**10. Add the following lines to `/etc/rmmount.conf`.**

```
# File System Sharing
share floppy*
```

These lines share any diskette loaded into your system's diskette drives.

**11. Remove write permissions from `/etc/rmmount.conf`.**

```
# chmod 444 /etc/rmmount.conf
```

This step returns the file to its default permissions.

**12. Load a diskette.**

```
---Insert the diskette---
# volcheck -v
media was found
```

The diskette you now load, and all subsequent diskettes, will be available to other systems. To access the diskette, the remote user must mount it by name, according to the instructions in “How to Access Diskettes on Other Systems” on page 206.

**13. Verify that the diskette is available to other systems by using the `share(1M)` command.**

If the diskette is available, its share configuration will be displayed. (The shared dummy directory will also be displayed.)

```
# share
- /dummy ro "dummy dir to wake up NFS daemon"
- /myfiles rw ""
```

## Example—Making Local Diskettes Available to Other Systems

The following example makes any diskette loaded into the local system's diskette drive available to other systems on the network.

```

# ps -ef | grep nfsd
    root 10127  9986  0 08:25:01 pts/2    0:00 grep nfsd
    root 10118      1  0 08:24:39 ?        0:00 /usr/lib/nfs/nfsd -a
# mkdir /dummy
# vi /etc/dfs/dfstab
(Add the following line:)
share -F nfs -o ro /dummy
# eject floppy0
# chmod 644 /etc/rmmount.conf
# vi /etc/rmmount
(Add the following line to the File System Sharing section.)
share floppy*
# chmod 444 /etc/rmmount.conf
(Load a diskette.)
# volcheck -v
media was found
# share
-           /dummy    ro    ""
-           /floppy/myfiles  rw    ""

```



## Using PCMCIA Memory Cards From the Command Line (Tasks)

---

This chapter describes all the tasks required to format and use PCMCIA memory cards from the command line in the Solaris environment.

This is a list of the step-by-step instructions in this chapter.

- “How to Format a UFS PCMCIA Memory Card” on page 215
- “How to Place a UFS File System on a PCMCIA Memory Card” on page 218
- “How to Format a DOS PCMCIA Memory Card” on page 220
- “How to Load a PCMCIA Memory Card” on page 223
- “How to Examine the Contents of a PCMCIA Memory Card” on page 225
- “How to Copy or Move Information From a PCMCIA Memory Card” on page 225
- “How to Copy or Move Information to a PCMCIA Memory Card” on page 226
- “How to Find Out If a PCMCIA Memory Card Is Still In Use” on page 228
- “How to Eject a PCMCIA Memory Card” on page 228
- “How to Access PCMCIA Memory Cards on Other Systems” on page 229
- “How to Make Local PCMCIA Memory Cards Available to Other Systems” on page 231

---

## Formatting PCMCIA Memory Cards Task Map

**TABLE 14-1** Task Map: Formatting PCMCIA Memory Cards

Task	Description	For Instructions, Go To
1. Load Unformatted PCMCIA Memory Card	Insert the PCMCIA memory card into the drive and enter the <code>volcheck</code> command.	"How to Load a PCMCIA Memory Card" on page 223
2. Format the PCMCIA Memory Card	Format the PCMCIA memory card for UFS.	"How to Format a UFS PCMCIA Memory Card" on page 215
	Format the PCMCIA memory card for DOS.	"How to Format a DOS PCMCIA Memory Card" on page 220
3. Add a UFS File System	<i>UFS Only. Optional.</i> To use the PCMCIA memory card for files, add a UFS file system. To use for characters, skip this step.	"How to Place a UFS File System on a PCMCIA Memory Card" on page 218
4. Eject the PCMCIA Memory Card	When finished formatting, always eject the PCMCIA memory card, even if you are going to use it again right away.	"How to Eject a PCMCIA Memory Card" on page 228

## Using PCMCIA Memory Cards Names

When working with PCMCIA memory cards, you can identify them by name or with a designator from Table 14-2. For brevity, task descriptions use `pcmem0`, but you can replace it with either the PCMCIA memory card's name or a different designator.

**TABLE 14-2** How to Identify PCMCIA Memory Cards

PCMCIA Card	Alternate Name
First PCMCIA drive	<code>pcmem0</code>
Second PCMCIA drive	<code>pcmem1</code>
Third PCMCIA drive	<code>pcmem2</code>



---

**Note** - PCATA drives that are not named (that is, they have no “label”) are assigned the default name of `noname`.

---

## Hardware Considerations

A Solaris platform can format PCMCIA memory cards for use on both Solaris and DOS platforms. However, the hardware platform imposes some limitations. They are summarized in the table below.

Solaris on This Platform ...	Can Format PCMCIA Memory Cards For ...
Solaris on SPARC	Solaris on SPARC (UFS)
	MS-DOS or NEC-DOS (PCFS)
Solaris on x86	Solaris on x86 (UFS)
	MS-DOS or NEC-DOS (PCFS)

PCMCIA memory cards formatted for UFS are restricted to the hardware platform on which they were formatted. In other words, a UFS PCMCIA memory card formatted on a SPARC platform cannot be used for UFS on an x86 platform. Likewise, PCMCIA memory cards formatted on an x86 platform cannot be used on a SPARC platform. This is because the SPARC and x86 UFS formats are different.

A complete format for UFS file systems consists of the basic “bit” formatting plus the structure to support a UFS file system. A complete format for a DOS file system consists of the basic “bit” formatting plus the structure to support either an MS-DOS or an NEC-DOS file system. The procedures required to prepare a PCMCIA memory card for each type of file system are different. Therefore, before you format a PCMCIA memory card, consider which file system you are using. See “Formatting PCMCIA Memory Cards Task Map” on page 213.

To view all the options to the `fdformat` command, either see `fdformat(1)` or enter `fdformat -z`. The `-z` option displays all the options to the command.

### ▼ How to Format a UFS PCMCIA Memory Card

As mentioned in the introduction, a UFS PCMCIA memory card formatted on a SPARC platform can be used only on another SPARC platform, and a UFS PCMCIA memory card formatted on an x86 platform can be used only on an x86 platform running the Solaris release.



---

**Caution** - Formatting a PCMCIA memory card erases any pre-existing content.

---

**1. Quit File Manager.**

File Manager automatically displays a formatting window when you insert an unformatted PCMCIA memory card. Unfortunately, File Manager formatting is unreliable. To avoid the window, quit File Manager. If you prefer to keep File Manager open, quit the formatting window when it appears.

**2. Make sure the PCMCIA memory card is write-enabled.**

Write-protection is controlled by a small slide switch in the end of the PCMCIA memory card.

**3. Insert the PCMCIA memory card.**

Make sure the PCMCIA memory card is completely inserted.

**4. Invoke formatting.**

```
$ fdformat -v -U [convenience-options]
```

-v	Verifies whether the PCMCIA memory card was formatted correctly.
-U	Unmounts the PCMCIA memory card if it is mounted.
<i>convenience-options</i>	
-e	Ejects the PCMCIA memory card when done formatting.
-f	Forces formatting without asking for confirmation.
-b <i>label</i>	Names the PCMCIA memory card. <i>label</i> must be eight characters or less, upper or lower case.
-z	Lists all the options to the fdformat command, but does not format the PCMCIA memory card.

The fdformat command displays a confirmation message (unless you used the -f option), indicating the type of formatting to be performed:

```
Formatting in /vol/dev/aliases/pcmem0
```

(Continuation)

Press return to start formatting pcmem0.

**5. Select one of the options in the table below.**

To ...	Press ...
Confirm the type of formatting	Return (unless you used the -f option in the previous step, in which case no confirmation is necessary).
Cancel formatting	Control-c.

As the formatting progresses, a series of dots is displayed. As the verification progresses, a series of V's appears beneath the dots. When the series stops, the formatting is complete.

The PCMCIA memory card is now ready for raw character operations such as `tar` and `cpio`.

## Examples—Formatting a UFS PCMCIA Memory Card

Following are examples of UFS formatting.

[illegible]

The following example performs the same job, but assigns the PCMCIA memory card the name `myfiles`:

[illegible]

## ▼ How to Place a UFS File System on a PCMCIA Memory Card

Even though the procedure for adding a UFS file system is the same for UFS PCMCIA memory cards formatted on x86 platforms and SPARC platforms, a UFS PCMCIA memory card formatted on a SPARC platform can only be used on another SPARC platform, and a UFS PCMCIA memory card formatted on an x86 platform can only be used on an x86 platform running Solaris.

### 1. Format the PCMCIA memory card for a UFS file system.

Use the procedure “How to Format a UFS PCMCIA Memory Card” on page 215.

### 2. Use the `newfs(1M)` command and the full pathname to the Volume Management directory to create a UFS file system on the PCMCIA memory card.

```
$ /usr/sbin/newfs -v /vol/dev/aliases/pcm0
```

`-v`

Prints status messages.

`/vol/dev/aliases/pcm0`

Indicates the location of the memory card.

The `newfs(1M)` command displays a message asking you to confirm the creation of the file system.

### 3. Confirm the creation of the file system.

```
newfs: construct a new file system \
      /vol/dev/aliases/pcm0: (y/n)? y
```

A status message is displayed, indicating the particulars of the file system and the PCMCIA memory card's formatting:

```
mkfs -F ufs /vol/dev/aliases/pcm0 2848 8 2 8192 1024 16 \
      10 60 2048 t 0 -1 8 -1
/vol/dev/aliases/pcm0: 2848 sectors in 128 cylinders of \
      2 tracks, 8 sectors
```

(continued)

(Continuation)

```
1.0MB in 8 cyl groups (16 c/g, 0.12MB/g, 64 i/g)
super-block backups (for fsck -F ufs -o b=#) at:
    32, 304, 544, 816, 1056, 1328, 1568, 1840
```

The PCMCIA memory card is now ready to be used on a SPARC platform. However, before Volume Management recognizes the memory card, you must use the `volrmmount(1)` command as described in the following step.

4. Use the `volrmmount` command with the `-i` option to notify Volume Management that the memory card is inserted.

```
$ volrmmount -i pcmem0
```

The PCMCIA memory card should now be mounted under `/pcmem/pcmem0`.

5. Verify the UFS file system is on the PCMCIA card by using the `ls` command on the `/pcmem` directory.

If the `pcmem0` subdirectory appears, the PCMCIA memory card has a UFS file system and has been mounted properly.

```
$ ls /pcmem
pcmem0
```

## Example—Placing a UFS File System on a PCMCIA Memory Card

```
$ volcheck -v
media was found
$ /usr/sbin/newfs -v /vol/dev/aliases/pcmem0
newfs: construct a new file system \
    /vol/dev/aliases/pcmem0:(y/n)? y
mkfs -F ufs /vol/dev/aliases/pcmem0 ...
$ volrmmount -i pcmem0
```

```
media was found
```

## ▼ How to Format a DOS PCMCIA Memory Card

You can format a DOS PCMCIA memory card on a SPARC or x86 Solaris platform. The steps are similar, except that instead of a SunOS file system being placed on the PCMCIA memory card, a DOS file system, either MS-DOS or NEC-DOS, is put on the file system.




---

**Caution** - Formatting a PCMCIA memory card erases any pre-existing content.

---

### 1. Quit File Manager.

File Manager automatically displays a formatting window when you insert an unformatted PCMCIA memory card. Unfortunately, File Manager formatting is unreliable. To avoid the window, quit File Manager. If you prefer to keep File Manager open, quit the formatting window when it appears.

### 2. Make sure the PCMCIA memory card is not write-protected.

Write-protection is controlled by a small slide switch in the end of the PCMCIA memory card.

### 3. Insert the PCMCIA memory card.

Make sure the PCMCIA memory card is completely inserted. It must drop down into the drive.

### 4. Invoke formatting.

```
$ fdformat -v -U [density-options convenience-options]
```

<code>-v</code>	Verifies whether the PCMCIA memory card was formatted correctly.
<code>-U</code>	Unmounts the PCMCIA memory card if it is mounted.
<i>density-options</i>	If the drive density is 1.44 Mbytes, <i>density-options</i> are:
<code>-d</code>	Formats for MS-DOS.

`-t nec -M`

Formats at 1.2 Mbytes for NEC-DOS.

A complete list of *density-options* appears in `fdformat(1)`.

#### *convenience-options*

`-e`

Ejects the PCMCIA memory card when done formatting.

`-f`

Does not ask for confirmation before formatting.

`-b label`

Name for the PCMCIA memory card. *Label* must be eight characters or less, upper or lower case.

`-z`

Lists all the options to the `fdformat` command, but does not format the PCMCIA memory card.

---

**Note** - If you try to format a 720 Kbyte (DD) diskette for 1.44 Mbytes, `fdformat` will not stop you unless you include the `-v` option. With the `-v` option, `fdformat` will format the diskette, but the verification will catch the error and notify you with the following message:  
`fdformat: check diskette density, I/O error`

---

The `fdformat` command displays a confirmation message, indicating the type of formatting to be performed:

```
Formatting 1.44 M in /vol/dev/rdiskette0/unformatted
Press return to start formatting floppy.
```

#### 5. Select one of the options in the table below.

To ...	Press ...
Confirm the type of formatting	Return (unless you used the <code>-f</code> option in the previous step, in which case no confirmation is necessary)
Cancel formatting	Control-c

As the formatting progresses, a series of dots is displayed. As the verification progresses, a series of V's appears beneath the dots. When the series stops, the formatting is complete and the PCMCIA memory card is ready for use on a DOS system.

6. Use the `volrmmount` command with the `-i` option to notify Volume Management that the memory card is inserted.

```
$ volrmmount -i pcmem0
```

Volume Management mounts the PCMCIA memory card under `/pcmem/pcmem0`.

## Using PCMCIA Memory Cards Task Map

TABLE 14-3 Task Map: Using PCMCIA Memory Cards

Task	Description	For Instructions, Go To
1. Load the PCMCIA Memory Card	Insert the PCMCIA memory card into its drive and enter the <code>volcheck</code> command.	"How to Load a PCMCIA Memory Card" on page 223
2. Examine the Contents of a PCMCIA Memory Card	<i>Optional.</i> To examine the contents of the PCMCIA memory card, look in the appropriate directory under <code>/PCMCIAmemorycard</code> .	"How to Examine the Contents of a PCMCIA Memory Card" on page 225
3. Exchange Files	<i>Optional.</i> Copy files or directories between the PCMCIA memory card and your file system.	<p>"How to Copy or Move Information From a PCMCIA Memory Card" on page 225</p> <p>"How to Copy or Move Information to a PCMCIA Memory Card" on page 226</p>



**TABLE 14-3** Task Map: Using PCMCIA Memory Cards *(continued)*

Task	Description	For Instructions, Go To
4. Is PCMCIA Memory Card Still in Use?	<i>Optional.</i> Before ejecting the PCMCIA memory card, find out if the PCMCIA memory card is still in use.	"How to Find Out If a PCMCIA Memory Card Is Still In Use" on page 228
5. Eject the PCMCIA memory card	When you finish, eject the PCMCIA Memory Card.	"How to Eject a PCMCIA Memory Card" on page 228

## ▼ How to Load a PCMCIA Memory Card

### 1. Make sure the PCMCIA memory card is formatted.

If you aren't sure, insert it and check the status messages in the Console, as described in "Using PCMCIA Memory Cards Task Map" on page 222. If you need to format the PCMCIA memory card, go to "How to Format a UFS PCMCIA Memory Card" on page 215 or "How to Format a DOS PCMCIA Memory Card" on page 220.

### 2. Insert the PCMCIA memory card.

Make sure the PCMCIA memory card is completely inserted. It must drop down into the drive. If the drive has a door, close it.

### 3. Notify Volume Management.

```
$ volcheck -v
media was found
```

Two status messages are possible:

media was  
found

Volume Management detected the PCMCIA memory card and will attempt to mount it in the `/pcmem` directory.

If the PCMCIA memory card is formatted properly, no error messages appear in the Console.

If the PCMCIA memory card is not formatted, the “media was found” message is still displayed, but the following error messages appear in the Console:

```
fd0: unformatted diskette or no diskette in the drive
```

```
fd0: read failed (40 1 0)
```

```
fd0: bad format
```

You must format the PCMCIA memory card before Volume Management can mount it. Instructions are provided on “How to Format a UFS PCMCIA Memory Card” on page 215 (for UFS) and “How to Format a DOS PCMCIA Memory Card” on page 220 (for DOS).

no media was  
found

Volume Management did not detect a PCMCIA memory card. Make sure the PCMCIA memory card is inserted properly and run `volcheck` again. If unsuccessful, check the PCMCIA memory card; it could be damaged. You can also try to mount the PCMCIA memory card manually.

#### 4. Verify that the PCMCIA memory card was mounted by listing its contents.

```
$ ls /pcmem/pcmem0
pcmem0 myfiles
```

As described earlier, `pcmem0` is a symbolic link to the actual name of the PCMCIA memory card; in this case, `myfiles`. If the PCMCIA memory card has no name but is formatted correctly, the system will refer to it as `unnamed_floppy`.

If nothing appears under the `/pcmem` directory, the PCMCIA memory card was either not mounted or is not formatted properly. To find out, run the `mount` command and look for the line that begins with `/pcmem` (usually at the end of the listing):

```
/pcmem/name on /vol/dev/diskette0/name ...
```

If the line does not appear, the PCMCIA memory card was not mounted. Check the Console for error messages.

## ▼ How to Examine the Contents of a PCMCIA Memory Card

Use the `ls -L` command because some directories under `/pcmem` are symbolic links:

```
$ ls -L [-l] pcmem0
```

`-L` Includes symbolic links in the output.

`-l` Long format. Includes permissions and owners in the output.

### Example—Displaying the Contents of a PCMCIA Memory Card

The following example lists the contents of the PCMCIA memory card in the first floppy drive, identified by `pcmem0`.

```
$ ls -L -l /pcmem/pcmem0
-rwxrwxrwx 1 smith staff 362284 Nov 16 20:54 text.doc
-rwxrwxrwx 1 smith staff 24562 Nov 16 12:20 art.gif
```

## ▼ How to Copy or Move Information From a PCMCIA Memory Card

Once you have inserted a PCMCIA memory card, you can access its files and directories just as you would those of any other file system. The only significant restrictions are ownership and permissions. For instance, if you are not the owner of a file on a PCMCIA memory card, you won't be able to overwrite that file on the PCMCIA memory card. Or, if you copy a file into your file system, you'll be the owner, but that file won't have write permissions (because it never had them on the PCMCIA memory card); you'll have to change the permissions yourself.

**1. Make sure the PCMCIA memory card is formatted and mounted.**

```
$ ls /pcmem
pcmem0 PCMCIA memorycard-name
```

If the PCMCIA memory card is properly formatted and mounted, its name and the symbolic link will appear under `/pcmem`.

If nothing appears under the `/pcmem` directory, the PCMCIA memory card is not mounted. See . The PCMCIA memory card might also need to be formatted. See “How to Format a UFS PCMCIA Memory Card” on page 215 or “How to Format a DOS PCMCIA Memory Card” on page 220.

**2. Copy the files or directories.**

To Copy ...	Use ...
A file	<code>cp</code>
A directory	<code>cp -r</code>

**3. Verify the copy or move operation by using the `ls` command.**

## Examples—Copying or Moving Information from a PCMCIA Memory Card

The first example, below, moves a file (`readme.doc`) from the PCMCIA memory card to the current directory (indicated by the “.” symbol). The second example copies a file (`readme2.doc`) from the PCMCIA memory card to the current directory. The third example copies a directory (`morefiles`) and everything below it from the PCMCIA memory card to the current directory.

```
$ mv /pcmem/pcmem0/readme.doc .  
$ cp /pcmem/pcmem0/readme2.doc .  
$ cp -r /pcmem/pcmem0/morefiles .
```

## ▼ How to Copy or Move Information to a PCMCIA Memory Card

**1. Make sure the PCMCIA memory card is not write-protected.**

Write-protection is controlled by a small slide switch in the end of the PCMCIA memory card.

**2. Make sure the PCMCIA memory card is formatted and mounted.**

```
$ ls /pcmem
pcmem0 PCMCIA memorycard-name
```

If the PCMCIA memory card is properly formatted and mounted, its name and the symbolic link, `pcmem0`, will appear under `/pcmem`.  
If nothing appears under the `/pcmem` directory, the PCMCIA memory card is not mounted. See . The PCMCIA memory card might also need to be formatted. See “How to Format a UFS PCMCIA Memory Card” on page 215 or “How to Format a DOS PCMCIA Memory Card” on page 220.

### 3. Move or copy the files or directories.

To ...	Use ...
Copy a file	<code>cp</code>
Copy a directory	<code>cp -r</code>
Move a file or directory	<code>mv</code>

### 4. Verify the move or copy operation by using the `ls` command.

## Examples—Copying or Moving Information to a PCMCIA Memory Card

The first example, below, moves a file (`readme.doc`) from the current directory to the PCMCIA memory card loaded into the first floppy drive (indicated by `/pcmem/pcmem0`). The second example copies a file (`readme2.doc`) from the current directory to the PCMCIA memory card loaded into the second floppy drive (indicated by `/pcmem/pcmem1`). The third example copies a directory (`morefiles`) and its contents from the `/home/smith/directory` to the PCMCIA memory card loaded into the first floppy drive.

```
$ mv readme.doc /pcmem/pcmem0
$ cp readme2.doc /pcmem/pcmem1
$ cp -r /home/smith/morefiles /pcmem/pcmem0
```

## ▼ How to Find Out If a PCMCIA Memory Card Is Still In Use

### 1. Become superuser.

### 2. Invoke the `fuser(1M)` command.

The `fuser` command lists the processes that are currently accessing the CD that you specify.

```
# fuser -u [-k] pcmem0
```

`-u`

Displays the user of the PCMCIA memory card.

`-k`

Kills the process accessing the PCMCIA memory card.

## Example—Finding Out If a PCMCIA Memory Card Is Still In Use

In the following example, the processes `6400c` and `6399c` are accessing the `/pcmem/pcmem0` directory, and the process owners are `root` and `smith`, respectively.

```
# fuser -u /pcmem/pcmem0
/pcmem/pcmem0: 6400c(root) 6399c(smith)
```

You can kill the processes individually (as superuser), or you can use the `fuser` command with the `-k` option, which kills all the processes accessing that file system:

```
# fuser -u -k /pcmem/pcmem0
/pcmem/pcmem0: 6400c(root)Killed 6399c(smith)Killed
```

The `fuser` command may not always identify all the killed processes. To be sure, run it again with the `-u` option.

## ▼ How to Eject a PCMCIA Memory Card

### 1. Make sure the PCMCIA memory card is not being used.

Remember, a PCMCIA memory card is “being used” if a shell or an application is accessing any of its files or directories.

If you are not sure whether you have found all users of a PCMCIA memory card (a renegade shell hidden behind a desktop tool may be accessing it), use the `fuser` command, as described in “How to Find Out If a PCMCIA Memory Card Is Still In Use” on page 228.

## 2. Eject the PCMCIA memory card.

```
# eject pcmem0
```

You'll have to eject the PCMCIA memory card by hand. If you are running Windows, look for an onscreen message that says you can now eject the PCMCIA memory card.

If the PCMCIA memory card is still in use, the following message appears:

```
/vol/dev/pcmem/noname: Device busy
```

In this case, return to Step 1 and make sure no one is using the PCMCIA memory card, then eject it again.

## ▼ How to Access PCMCIA Memory Cards on Other Systems

You can access a PCMCIA memory card on another system by mounting it manually into your file system—provided the other system has shared its PCMCIA memory card drive according to the instructions in “How to Make Local PCMCIA Memory Cards Available to Other Systems” on page 231.

### 1. Select an existing directory to serve as the mount point or create one.

```
$ mkdir directory
```

*directory*

The name of the directory that you create to serve as a mount point for the other system's PCMCIA memory card.

### 2. Find the name of the PCMCIA memory card you want to mount.

When you manually mount a remote PCMCIA memory card, you cannot use the `pcmem0` or `floppy1` variables available with your local PCMCIA memory cards. You must use the exact PCMCIA memory card name. To find it, use the `ls` command on the remote system's `/pcmem` directory. If the automounter is running, you can simply `cd` to the system whose PCMCIA memory card you

want to mount and then use the `ls` command. If the automounter is not running, you'll have to use another method, such as logging in remotely.

### 3. As superuser, mount the PCMCIA memory card.

```
# mount -F nfs -o rw system-name:/pcmem/PCMCIA memory-card-name
local-mount-point
```

<i>system-name</i>	The name of the system whose PCMCIA memory card you will mount.
<i>PCMCIA memory-card-name</i>	The name of the PCMCIA memory card you want to mount.
<i>local-mount-point</i>	The local directory onto which you will mount the remote PCMCIA memory card.

### 4. Log out as superuser.

### 5. Verify that the PCMCIA memory card is indeed mounted by using the `ls` command to list the contents of the mount point.

```
$ ls /pcmem
```

## Example—Accessing PCMCIA Memory Cards on Other Systems

This example mounts the PCMCIA memory card named `myfiles` from the remote system `mars` onto the `/pcmem` directory of the local system.

```
$ cd /net/mars
$ ls /pcmem
pcmem0      myfiles
$ su
Password: password
# mount -F nfs rw mars:/pcmem/myfiles /pcmem
# exit
$ ls /pcmem
myfiles
```



## ▼ How to Make Local PCMCIA Memory Cards Available to Other Systems

You can configure your system to share its PCMCIA memory cards; in other words, you can make any PCMCIA memory cards in those drives available to other systems. Once your PCMCIA memory card drives are shared, other systems can access the PCMCIA memory cards they contain simply by mounting them, as described in “How to Access PCMCIA Memory Cards on Other Systems” on page 229.

1. **Become superuser.**
2. **Find out whether the NFS daemon (`nfsd`) is running.**

```
# ps -ef | grep nfsd
root 14533      1 17 10:46:55 ?        0:00 /usr/lib/nfs/nfsd -a 16
root 14656    289  7 14:06:02 pts/3 0:00 grep nfsd
```

If the daemon is running, a line for `/usr/lib/nfs/nfsd` will appear, as shown above. If the daemon is not running, only the `grep nfsd` line will appear.

3. **Select an option from the following table.**

If ...	Then ...
<code>nfsd</code> is running	Go to Step 8 on page 232
<code>nfsd</code> is <i>not</i> running	Continue with Step 4 on page 231

4. **Create a dummy directory for `nfsd` to share.**

```
# mkdir /dummy-dir
```

*dummy-dir*

Can be any directory name; for example, `dummy`. This directory will not contain any files. Its only purpose is to “wake up” the NFS daemon so that it notices your shared PCMCIA memory cards.

5. **Add the following entry into the `/etc/dfs/dfstab` file.**

```
share -F nfs -o ro [-d comment] /dummy-dir
```

When you start the NFS daemon, it will see this entry, “wake up,” and notice the shared PCMCIA memory card drive. Note that the comment (preceded by `-d`) is optional.

**6. Start the NFS daemon.**

```
# /etc/init.d/nfs.server start
```

**7. Verify that the NFS daemon is indeed running.**

```
# ps -ef | grep nfsd
root 14533    1 17 10:46:55 ?        0:00 /usr/lib/nfs/nfsd -a 16
root 14656   289  7 14:06:02 pts/3  0:00 grep nfsd
```

**8. Eject any PCMCIA memory card currently in the drive.**

```
# eject pcmem0
```

**9. Assign write permissions to `/etc/rmmount.conf`.**

```
# chmod 644 /etc/rmmount.conf
```

**10. Add the following lines to `/etc/rmmount.conf`.**

```
# File System Sharing
share floppy*
```

These lines share any PCMCIA memory card loaded into your system’s PCMCIA memory card drives.

**11. Remove write permissions from `/etc/rmmount.conf`.**

```
# chmod 444 /etc/rmmount.conf
```

This step returns the file to its default permissions.

**12. Load a PCMCIA memory card.**

```
---Insert the PCMCIA memory card---  
# volcheck -v  
media was found
```

The PCMCIA memory card you now load, and all subsequent PCMCIA memory cards, will be available to other systems. To access the PCMCIA memory card, the remote user must mount it by name, according to the instructions in “How to Access PCMCIA Memory Cards on Other Systems” on page 229.

**13. Verify that the PCMCIA memory card is indeed available to other systems by using the `share` command.**

If the PCMCIA memory card is available, its share configuration will be displayed. (The shared dummy directory will also be displayed.)

```
# share  
- /dummy ro "dummy dir to wake up NFS daemon"  
- /myfiles rw ""
```

## Example—Making Local PCMCIA Memory Cards Available to Other Systems

The following example makes any PCMCIA memory card loaded into the local system’s PCMCIA memory card drive available to other systems on the network.

```
# ps -ef | grep nfsd  
root 10127 9986 0 08:25:01 pts/2 0:00 grep nfsd  
root 10118 1 0 08:24:39 ? 0:00 /usr/lib/nfs/nfsd -a  
# mkdir /dummy  
# vi /etc/dfs/dfstab  
(Add the following line:)  
share -F nfs -o ro /dummy  
# eject pcmem0  
# chmod 644 /etc/rmmount.conf  
# vi /etc/rmmount  
(Add the following line to the File System Sharing section.)  
share floppy*  
# chmod 444 /etc/rmmount.conf  
(Load a PCMCIA memory card.)  
# volcheck -v  
media was found  
# share  
- /dummy ro ""
```

(continued)

(Continuation)

-	/pcmem/myfiles	rw	" "
---	----------------	----	-----

## How Volume Management Works (Reference)

---

This chapter describes the mount points and symbolic links that Volume Management creates to accommodate removable media.


This is a list of reference information in this chapter.

- “Volume Management Mounts All Removable Media” on page 235
- “Volume Management Provides Access to Diskettes” on page 236
- “Volume Management Provides Access to CDs” on page 237
- “Volume Management Supplies Convenient Mount Points for Easier Access ” on page 238
- “Volume Management Creates Two Sets of Symbolic Links” on page 240
- “Volume Management Can Be Limited by UFS Formats” on page 241

---


## Volume Management Mounts All Removable Media

Volume Management provides access to all CD-ROM and diskette drives under /vol/dev:



## Volume Management Provides Access to Diskettes


Volume Management provides access to a system's diskette drive through subdirectories of `/vol/dev`; namely, `diskette0` and `rdiskette0`.



If a system has a second diskette drive, Volume Management creates a second pair of directories named `diskette1` and `rdiskette1`. For a third diskette drive, it would create `diskette2` and `rdiskette2`. And so on for additional drives.


The `diskette` directories provide access to file systems, and the `rdiskette` directories provide access to raw characters. The diskettes themselves appear in subdirectories beneath the drive directories<sup>1</sup>:

1. In this and subsequent illustrations, some nodes are "grayed out" to draw attention to the other nodes. There is no structural significance to this convention; it is simply a means of highlighting.




## Volume Management Provides Access to CDs

The arrangement for CDs is similar, except that the block and raw directories are labelled `/dsk` and `/rdsk`, respectively, and the CD-ROM device is actually located one directory beneath them.




In the illustration above, the additional directory is named `c0t6`. That simply reflects a particular system's device naming conventions. The directory name on your system could be different, though it would have the same format.

The CDs themselves, however, follow a convention similar to diskettes, in that they are mounted beneath the directory belonging to their device:




As a result of this arrangement, a system with one diskette drive and one CD-ROM drive would have the following `/vol/dev` file system:



(Actually, `/vol/dev` includes an additional subdirectory named `aliases`, but that is described later in this section.)


## Volume Management Supplies Convenient Mount Points for Easier Access

To make access more convenient, Volume Management uses two special mount points, `/floppy` and `/cdrom`.




Volume Management mounts the `/vol/dev/diskette0` and `/vol/dev/dsk/c0t6` directories onto `/floppy` and `/cdrom`:





Because of these mount points, when you insert a diskette, you can access it under `/floppy/diskette-name`. Likewise, when you insert a CD, you can access it under `/cdrom/cd-name`.



However, these mount points depend on proper formatting. If a diskette is formatted, the mount succeeds, but if it is unformatted, the mount fails and the diskette is only available under `/vol/dev/diskette0`. You can format diskettes according to the instructions in “How to Format a UFS Diskette” on page 193 or “How to Format a DOS Diskette” on page 197.

If a system has multiple drives, they are mounted onto parallel directories such as /floppy/floppy0, /floppy/floppy1, /cdrom/cdrom0, etc.

---

## Volume Management Creates Two Sets of Symbolic Links

As an additional convenience, Volume Management creates two separate sets of symbolic links:

- One for file system access
- One for raw device access

### Symbolic Links for File System Access

The symbolic links for file system access simply link the directories /floppy/floppy0 and /cdrom/cdrom0 to the diskette inserted into the first diskette drive and the CD inserted into the first CD-ROM drive:


```
/floppy/floppy0 --> /floppy/name --> /vol/dev/diskette0/name  
/cdrom/cdrom0 --> /cdrom/cd-name --> /vol/dev/dsk/c0t6d0/cd-name
```

These links enable you to access floppies and CDs without knowing their names. You can use the link names, floppy0 or cdrom0, instead.

Diskettes and CDs inserted into subsequent drives would follow the naming conventions summarized in Table 11-3.

### Symbolic Links for Raw Device Access

To make raw device access more convenient, Volume Management creates the `aliases` directory, under /vol/dev:




Beneath the `aliases` directory, Volume Management creates a set of symbolic links similar to those used for block access. In other words, for character access, these directories are equivalent:

```
/vol/dev/aliases/floppy0 --> /vol/dev/rdiskette0/diskette-name
```

```
/vol/dev/aliases/cdrom0 --> /vol/dev/rdsk/c0t6d0/cd-name
```

Like the symbolic links for file system access, the purpose of these links is to enable you to access a raw-character diskette or CD without knowing its name; in other words, by using the `/vol/dev/aliases/floppy0` and `/vol/dev/aliases/cdrom0` link names.

The example above shows only one symbolic link for diskettes and one for CDs. If your system had two diskettes or two CDs, there would be one symbolic link for each:



---

## Volume Management Can Be Limited by UFS Formats

UFS formats are not portable between architectures, so they must be used on the architecture for which they were formatted. For instance, a UFS CD formatted for a SPARC platform cannot be recognized by an x86 platform. Likewise, an x86 UFS CD cannot be mounted by Volume Management on a SPARC platform. The same limitation applies to diskettes. (Actually, some architectures share the same bit structure, so occasionally a UFS format specific to one architecture will be recognized by another architecture, but the UFS file system structure was not designed to guarantee this compatibility).


Therefore, Volume Management cannot recognize and mount x86 UFS media on a SPARC platform—or SPARC UFS media on an x86 platform.

Most CDs are formatted according to the ISO 9660 standard (High Sierra File System—HSFS), which imposes no limitations on Volume Management, so incompatibility is seldom a problem with CDs.


With diskettes, UFS incompatibility can occur more often because formats can be established by the user. Be aware that if you format a UFS diskette on one architecture, you won't be able to use it on a different architecture. (For instructions, see "How to Format a UFS Diskette" on page 193).

## What About Mixed Formats?

Some CDs, particularly installation CDs, contain mixed formats; that is, part UFS, part ISO 9660. To accommodate the different formats, the CD is split into slices, which are similar in effect to partitions on hard disks. The 9660 portion is portable, but the UFS portion is architecture-specific. Furthermore, to make the CD usable by several different architectures (as in the case of installation, when different PROM architectures might be used to boot the system), more than one UFS format is loaded onto the CD:



When Volume Management encounters this arrangement, it simply ignores the UFS formats not specific to the local system's architecture and mounts the appropriate UFS slice and the ISO 9660 slice:



These slices appear as subdirectories both under `/vol/dev/dsk/c0t6` and `/cdrom/cdrom0`:

```
$ ls /cdrom/cdrom0
S0  S2
```

(continued)

(Continuation)

```
$ ls /vol/dev/dsk/c0t6  
S0 S2
```



## PART **V** Managing Software

---

This part provides instructions for managing Solaris software packages and patches. This part contains these chapters.

Chapter 16	Provides overview information about adding and removing software products in the Solaris operating environment.
Chapter 17	Provides step-by-step instructions for installing and removing software packages on different client types.
Chapter 18	Provides overview information and step-by-step instructions about adding and removing patches in the Solaris operating environment.





## Software Administration (Overview)

---

Software administration involves installing and removing software from standalone systems, servers, and their clients. This chapter describes background and other useful information about installing and managing software. This chapter does not describe installing the Solaris software, which has its own installation and setup procedures.

This is a list of the overview information in this chapter.

- “Where to Find Software Administration Tasks” on page 247
- “Software Packages” on page 248
- “Tools for Managing Software” on page 248
- “What Happens When You Add or Remove a Package” on page 249
- “What You Should Know Before Adding or Removing Packages” on page 250
- “Guidelines for Client Software Administration” on page 250
- “Guidelines for Removing Packages” on page 252
- “Avoiding User Interaction When Adding Packages” on page 253

---

## Where to Find Software Administration Tasks

Use this reference to find step-by-step instructions for administering software.

- Chapter 17
- Chapter 18

- “Troubleshooting Software Administration Problems” in *System Administration Guide, Volume II* for information on troubleshooting software administration problems.

---

## Software Packages

For the purpose of this discussion, software administration involves installing or removing software products. Sun and its third-party vendors deliver products in a form called a software *package*. (The term *packaging* generically refers to the method for distributing and installing software products to systems where the products will be used.) In its simplest form, you can think of a package as a collection of files and directories in a defined format. This format conforms to the Application Binary Interface (ABI), which is a supplement to the System V Interface Definition. The Solaris operating environment provides a set of utilities that interpret this format and provide the means to install or remove a package or to verify its installation.

---

## Tools for Managing Software

There are two tools for adding and removing software from a system:

- The `pkgadd` and `pkgrm` commands
- Admintool™

Although either of these are appropriate to use, each has its merits.

Using the `pkgadd` and `pkgrm` commands offers flexibility. For example, you can incorporate these commands into scripts, set up optional files to avoid user interaction or perform special checks, and copy software packages to spool directories. If you're already familiar with adding and removing packages with the `pkgadd` and `pkgrm` commands, it's probably easiest for you to continue using them.

Using Admintool to add and remove software offers ease of use, because it is a graphical interface to the `pkgadd` and `pkgrm` commands and it includes online help that provides general information on using the tool. Using the Admintool graphical interface is an especially nice way to view software already installed on a system or the software that resides on the installation media. If you're unfamiliar with software package naming conventions, you're uncomfortable using command line options, and you're managing software only on one system at a time, it's probably easiest for you to use Admintool to add and remove software.

Table 16-1 suggests some of the relative merits of using Admintool as opposed to using the `pkgadd` and `pkgrm` commands to manage software.

**TABLE 16-1** Admintool Software Management Capabilities

Software Management Tasks	Performed With Admintool?
Add and remove packages on standalone, server, or diskless systems	Yes
Easily view all installed software	Yes
Easily view and select packages from an installation media	Yes
Add packages to a spool directory	No
Eliminate user interaction by using an administration file	No

Note that prior to the Solaris 2.5 release, Software Manager (accessed with the `swmtool` command) was the graphical tool for adding and removing software. With the Solaris 2.5 release and compatible versions, Admintool (accessed with the `admintool` command) provides that capability. If you use the `swmtool` command on a Solaris 2.5 or compatible system, it will start Admintool.

## What Happens When You Add or Remove a Package

The `pkgadd` and `pkgrm` commands or Admintool are used to add and remove software. Admintool is a graphical front-end to the `pkgadd` and `pkgrm` commands.

When you add a package, the `pkgadd` command uncompresses and copies files from the installation media to a local system's disk. When you remove a package, the `pkgrm` command deletes all files associated with that package, unless those files are also shared with other packages.

Package files are delivered in package format and are unusable as they are delivered. The `pkgadd` command interprets the software package's control files, and then uncompresses and installs the product files onto the system's local disk.

Although the `pkgadd` and `pkgrm` commands do not log their output to a standard location, they do keep track of the product installed or removed. The `pkgadd` and `pkgrm` commands store information about a package that has been installed or removed in a software product database.

By updating this database, the `pkgadd` and `pkgrm` commands keep a record of all software products installed on the system.

---

## What You Should Know Before Adding or Removing Packages

Before installing or removing packages on your system, you should know:

- Package naming conventions – Sun packages always begin with the prefix `SUNW`, as in `SUNWvol1r`, `SUNWadmap`, and `SUNWab2m`. Third-party packages usually begin with a prefix that corresponds to the company's stock symbol.
- What software is already installed – You can use the `pkginfo` command to determine the software already installed on a system or you can use `Admintool` to view already installed software.
- How servers and clients share software – Clients may have software that resides partially on a server and partially on the client. If this is the case, adding software for the client requires adding packages to both the server and the client. (“Guidelines for Client Software Administration” on page 250 describes in more detail how to manage client software.)

---

## Guidelines for Client Software Administration

Managing software on a standalone system is fairly straightforward, after you're familiar with the package installation tools and conventions. You install the software package on a system's local disk and that software is then available for use. However, managing software on client systems can be more difficult—especially when the software resides partially on the server and partially on the client. (For example, a piece of software may have a package with files that are installed on the client's root file system and a package with files that are installed on the `/usr` file system, which the client typically mounts from a server.)

Solaris supports diskless clients and Solstice AutoClient systems. On diskless and AutoClient systems, all software resides on the server. For example, when you add a software package to a diskless client, you don't actually install the package on the client, because it doesn't have any local disk storage device. Instead, you add the package either to the server or to the client's root file system (which resides on the

server), or both. A diskless or AutoClient system's root file system is typically in `/export/root/hostname` on the server.

AutoClient systems have their own disk storage, but it is only used for caching. The software resides on a server. (See the *Solstice AutoClient 2.1 Administration Guide* for more information.)

Because diskless and AutoClient systems may have software partially installed on their root file system and partially installed on a server's `/usr` (or some other shared file system), adding software packages to these clients requires that you know where (in what file systems) a software package is supposed to be installed.

## Installing Sun Packages on Servers and Clients

When adding packages for diskless and AutoClient systems, it is important to know where those packages' files are installed—in the client's root file system or in a server's `/usr` file system (or any other file system shared with the client).

Many Sun software packages are named to indicate where they are installed. For example, the `SUNWvolr` package is installed in the root file system and the `SUNWvolu` package is installed in the `/usr` file system. The "r" suffix stands for root, and the "u" suffix stands for `/usr`. However, the surest way to determine where a Sun package's files are installed is to examine the `SUNW_PKGTYPE` parameter, which is set in the package's `pkginfo` file. An interface for examining the `pkginfo` file is described in the procedure "How to Determine Where a Package's Files Will Be Installed" on page 264.

Some Sun packages do not have a `SUNW_PKGTYPE` parameter associated with them. These packages are usually set up to be installed in `/opt`. If a Sun package does not have a `SUNW_PKGTYPE` parameter value, treat it as a third-party package when installing it. (See "Installing Third-Party Packages on Servers and Clients" on page 252 for more information.)

When installing Sun packages on diskless or AutoClient systems, follow the general guidelines in Table 16-2.

**TABLE 16-2** Installing Sun Packages on Clients

If Package's Files Are Installed in The ...	Then Install the Package on The ...
root (/) file system	Client or the client's root file system
<code>/usr</code> (or any other shared file system)	Server

## Installing Third-Party Packages on Servers and Clients

Third-party packages do not use the `SUNW_PKGTYPE` parameter. As a result, there is no convenient way to determine where the package's files are installed. The surest way is to examine the package's `pkgmap` file. Based on that information, you can install according to the guidelines in Table 16–2. However, if you want to avoid having to examine a package's `pkgmap` file, you can use the following two-step process, which is the safest way to install third-party packages on diskless and AutoClient systems:

1. Install software on the server. Everything the server shares with clients is updated. (This assumes the server and clients are running the same version of Solaris software and are running on the same hardware platform: for example, either both x86 platforms or both SPARC platforms.)
2. Install the software on the client. The `pkgadd` command or `Admintool`, whichever you're using, will install only those files appropriate for the client. The `pkgadd` command or `Admintool` will not install software already available from file systems that are mounted from a server, because that software is already available to the client.

## Installing Packages in Heterogeneous Environments

There are two cases in which software management on clients/servers is further complicated:

- When the server is running a different Solaris release than the client – For example, the server is running the Solaris 7 release and it is serving Solaris 2.5 diskless clients.
- When the server and the clients are different hardware platforms – For example, the server is a SPARC system serving diskless clients that are x86 systems.

These are generically referred to as heterogeneous environments. When managing software in heterogeneous environments, you must first add the proper Solaris and architecture services appropriate for the server's clients. To do this, you use Host Manager to “add services” to the server (for detailed information, see Chapter 4.

For detailed information about how to add packages in a heterogeneous environment, see “Adding Packages in a Heterogeneous Client/Server Environment” on page 263.

---

## Guidelines for Removing Packages

Because the `pkgadd` and `pkgrm` commands update information in a software products database, it is important when you remove a package to use the `pkgrm`

command—even though you might be tempted to use the `rm` command instead. For example, you could use the `rm` command to remove a binary executable file, but that is not the same as using `pkgrm` to remove the software package that includes that binary executable. Using the `rm` command to remove a package's files will corrupt the software products database. (If you really only want to remove one file, you can use the `removef` command, which will update the software product database correctly. See `removef(1M)` for more information.)

If you intend to keep multiple versions of a package (for example, multiple versions of a document processing application), install new versions into a different directory than the already installed package. The directory where a package is installed is referred to as the base directory, and you can manipulate the base directory by setting the `basedir` keyword in a special file called an administration file. See “Avoiding User Interaction When Adding Packages” on page 253 and `admin(4)` for more information on use of an administration file and setting the base directory.

---

**Note** - If you use the upgrade option when installing the Solaris software, the Solaris installation software consults the software product database to determine the products already installed on the system.

---

---

## Avoiding User Interaction When Adding Packages

### Using an Administration File

When you use the `pkgadd -a` command, the `pkgadd` command consults a special *administration* file for information about how the installation should proceed. Normally, `pkgadd` performs several checks and prompts the user for confirmation before actually adding the specified package. You can, however, create an administration file that indicates to `pkgadd` it should bypass these checks and install the package without user confirmation.

The `pkgadd` command, by default, looks in the current working directory for an administration file. If `pkgadd` doesn't find an administration file in the current working directory, `pkgadd` looks in the `/var/sadm/install/admin` directory for the specified administration file. The `pkgadd` command also accepts an absolute path to the administration file.



---

**Caution** - Use administration files judiciously. You should know where a package's files are installed and how a package's installation scripts run before using an administration file to avoid the checks and prompts `pkgadd` normally provides.

---

This is an example of an administration file that will prevent `pkgadd` from prompting the user for confirmation before installing the package.

```
mail=
instance=overwrite
partial=nocheck
runlevel=nocheck
idepend=nocheck
rdepend=nocheck
space=nocheck
setuid=nocheck
conflict=nocheck
action=nocheck
basedir=default
```

Besides using administration files to avoid user interaction when adding packages, you can use them in several other ways. For example, you can use an administration file to quit a package installation (without user interaction) if there's an error or to avoid interaction when removing packages with the `pkgrm` command.

You can also assign a special installation directory for a package. (It would make sense to do this if you wanted to maintain multiple versions of a package on a system.) To do this, set an alternate base directory in the administration file (using the `basedir` keyword), which specifies where the package will be installed. See `admin(4)` for more information.

## Using a Response File

A response file contains your answers to specific questions asked by an *interactive package*. An interactive package includes a `request` script that asks you questions prior to package installation, such as whether or not optional pieces of the package should be installed.

If you know that the package you want to install is an interactive package, prior to installation, and you want to store your answers to prevent user interaction during future installations of this package, you can use the `pkgask` command to save your response. See `pkgask(1M)` for more information on this command.

Once you have stored your responses to the questions asked by the `request` script, you can use the `pkgadd -r` command to install the package without user interaction.



## Software Administration (Tasks)

---

This chapter describes how to install, remove, and administer software packages with Solaris commands and the Admintool graphical interface.

This is a list of step-by-step instructions in this chapter.

- “How to Add Packages to a Standalone System” on page 257
- “How to Add a Package to a Spool Directory” on page 259
- “How to Determine Where a Package’s Files Will Be Installed” on page 264
- “How to Add a Package to a Diskless or AutoClient System’s root (/) File System” on page 265
- “How to Add Packages to a Server” on page 267
- “How to Check the Integrity of an Installed Package” on page 271
- “How to List Information About All Installed Packages” on page 270
- “How to Display Detailed Information About a Package” on page 273
- “How to Remove a Package” on page 274
- “How to Remove a Spooled Package” on page 274
- “How to Remove a Diskless or AutoClient System’s Package” on page 275
- “How to Add Packages With Admintool” on page 276
- “How to Remove Packages With Admintool” on page 278

---

## Commands for Handling Software Packages

Table 17-1 shows commands to use for adding, removing, and checking the installation of software packages.

**TABLE 17-1** Commands for Adding and Removing Packages

Command	Description
<code>pkgadd(1M)</code>	Installs a software package
<code>pkgrm(1M)</code>	Removes a software package
<code>pkgchk(1M)</code>	Checks the installation of a software package
<code>pkginfo(1)</code>	Lists software package information
<code>pkgparam(1)</code>	Displays software package parameter values

---

## Known Problem With Adding and Removing Packages

There is a known problem with adding or removing some packages developed before the Solaris 2.5 release. If adding or removing a package fails during user interaction, or if you are prompted for user interaction and your responses are ignored, set the following environment variable:

```
NONABI_SCRIPTS=TRUE
```

# Adding Packages

## ▼ How to Add Packages to a Standalone System

1. Log in as superuser.
2. Remove any already installed packages with the same names as the ones you are adding.

This ensures that the system keeps a proper record of software that has been added and removed. There may be times when you want to maintain multiple versions of the same application on the system. For strategies on how to do this, see “Guidelines for Removing Packages” on page 252, and for task information, see “How to Remove a Package” on page 274.

3. Add a software package to the system.

```
# pkgadd -a admin-file -d device-name pkgid ...
```

<i>-a admin-file</i>	(Optional) Specifies an administration file <code>pkgadd</code> should consult during the installation. (For details about using an administration file, see “Using an Administration File” on page 253 in the previous chapter.)
<i>-d device-name</i>	Specifies the absolute path to the software packages. <i>device-name</i> can be a the path to a device, a directory, or a spool directory. If you do not specify the path where the package resides, the <code>pkgadd</code> command checks the default spool directory ( <code>/var/spool/pkg</code> ). If the package is not there, the package installation fails.
<i>pkgid</i>	(Optional) Is the name of one or more packages (separated by spaces) to be installed. If omitted, the <code>pkgadd</code> command installs all available packages.

If `pkgadd` encounters a problem during installation of the package, it displays a message related to the problem, followed by this prompt:

```
Do you want to continue with this installation?
```

Respond with `yes`, `no`, or `quit`. If more than one package has been specified, type `no` to stop the installation of the package being installed. `pkgadd` continues to install the other packages. Type `quit` to stop the installation.

4. Verify that the package has been installed successfully, using the `pkgchk` command.

```
# pkgchk -v pkgid
```

If `pkgchk` determines there are no errors, it returns a list of installed files. Otherwise, it reports the error.

## Example—Installing Software From a Mounted CD

**Note** - The name of this release is Solaris 7 but code and path or package path names may use Solaris 2.7 or SunOS 5.7. Always follow the code or path as it is written.

The following example shows a command to install the `SUNWaudio` package from a mounted Solaris 7 CD. The example also shows use of the `pkgchk` command to verify that the packages files were installed properly.

```
# pkgadd -d /cdrom/cdrom0/s0/Solaris_2.7/Product SUNWaudio
.
.
.
Installation of <SUNWaudio> complete.
# pkgchk -v SUNWaudio
/usr
/usr/bin
/usr/bin/audioconvert
/usr/bin/audioplay
/usr/bin/audiorecord
```

## Example—Installing Software From a Remote Package Server

If the packages you want to install are available from a remote system, you can manually mount the directory containing the packages (in package format) and install packages on the local system. The following example shows the commands to do this. In this example, assume the remote system named `package-server` has software packages in the `/latest-packages` directory. The `mount` command mounts the packages locally on `/mnt`, and the `pkgadd` command installs the `SUNWaudio` package.

```
# mount -F nfs -o ro package-server:/latest-packages /mnt
# pkgadd -d /mnt SUNWaudio
.
.
.
Installation of <SUNWaudio> was successful.
```

(continued)

(Continuation)

If the automounter is running at your site, you do not need to mount the remote package server manually. Instead, use the automounter path (in this case, `/net/package-server/latest-packages`) as the argument to the `-d` option.

```
# pkgadd -d /net/package-server/latest-packages SUNWaudio
.
.
.
Installation of <SUNWaudio> was successful.
```

The following example is similar to the previous one, except it uses the `-a` option and specifies an administration file named `noask-pkgadd`, which is illustrated in “Avoiding User Interaction When Adding Packages” on page 253. In this example, assume the `noask-pkgadd` administration file is in the default location, `/var/sadm/install/admin`.

```
# pkgadd -a noask-pkgadd -d /net/package-server/latest-packages SUNWaudio
.
.
.
Installation of <SUNWaudio> was successful.
```

---

## Using a Spool Directory

For convenience, you can copy frequently installed packages to a spool directory. If you copy packages to the default spool directory, `/var/spool/pkg`, you do not need to specify the source location of the package (`-d device-name` argument) when using the `pkgadd` command. The `pkgadd` command, by default, looks in the `/var/spool/pkg` directory for any packages specified on the command line. Note that copying packages to a spool directory is not the same as installing the packages on a system.

### ▼ How to Add a Package to a Spool Directory

1. Log in as superuser to the server or standalone system.

2. Remove any already spooled packages with the same names as the ones you are adding.

For information on removing spooled packages, see “How to Remove a Spooled Package” on page 274.

3. Add a software package to a spool directory.

```
# pkgadd -d device-name -s spooldir pkgid ...
```

<code>-d device-name</code>	Specifies the absolute path to the software packages. <i>device-name</i> can be the path to a device, a directory, or a spool directory.
<code>-s spooldir</code>	Specifies the name of the spool directory where the package will be spooled. You must specify a <i>spooldir</i> .
<i>pkgid</i>	(Optional) Is the name of one or more packages (separated by spaces) to be added to the spool directory. If omitted, <code>pkgadd</code> copies all available packages.

4. Verify that the package has been copied successfully to the spool directory, using the `pkginfo` command.

```
$ pkginfo -d spooldir | grep pkgid
```

If *pkgid* is copied correctly, the `pkginfo` command returns a line of information about it. Otherwise, `pkginfo` returns the system prompt.

## Example—Setting Up a Spool Directory From a Mounted CD

The following example shows a command to copy the `SUNWaudio` and `SUNWab2m` packages from a mounted SPARC Solaris 7 CD to the default spool directory (`/var/spool/pkg`).

```
# pkgadd -d /cdrom/cdrom0/s0/Solaris_2.7/Product -s /var/spool/pkg SUNWaudio SUNWab2m
Transferring <SUNWaudio> package instance
Transferring <SUNWab2m> package instance
```

## Example—Setting Up a Spool Directory From a Remote Package Server

If packages you want to copy are available from a remote system, you can manually mount the directory containing the packages (in package format) and copy them to a

local spool directory. The following example shows the commands to do this. In the following example, assume the remote system named `package-server` has software packages in the `/latest-packages` directory. The `mount` command mounts the package directory locally on `/mnt`, and the `pkgadd` command copies the `SUNWman` package from `/mnt` to the default spool directory (`/var/spool/pkg`).

```
# mount -F nfs -o ro package-server:/latest-packages /mnt
# pkgadd -d /mnt -s /var/spool/pkg SUNWman
Transferring <SUNWman> package instance
```

If the automounter is running at your site, you do not have to mount the remote package server manually. Instead, use the automounter path (in this case, `/net/package-server/latest-packages`) as the argument to the `-d` option.

```
# pkgadd -d /net/package-server/latest-packages -s /var/spool/pkg SUNWman
Transferring <SUNWman> package instance
```

## Example—Installing a Package From the Default Spool Directory

The following example shows a command to install the `SUNWman` package from the default spool directory. (When no options are used with `pkgadd`, it searches `/var/spool/pkg` for the named packages.)

```
# pkgadd SUNWman
.
.
.
Installation of <SUNWman> was successful.
```

---

## Adding Packages in a Homogeneous Client/Server Environment

For the purposes of this discussion, a *homogeneous client/server* means the clients and servers are running the same version of the Solaris operating environment and are the same hardware platform (either all SPARC or all x86 platforms).

This section describes how to install packages that place files in a client's root file system. If you are installing a package for clients, and that package does not place files on the client's root file system, the package can be installed directly on the

server and shared. (This assumes that the package is installed to a file system such as `/usr` on the server.)

Use the `pkgadd` command with the `-R` option to specify the location of the client's root file system for the client installation. (There's a common misconception that you can use the `-R` option to specify an alternate base directory for a package installation. That is not the case. The `-R` option is specifically for defining the client's root file system. To specify an alternate base directory, use `pkgadd` with the `-a` option and provide an administration file that has the `basedir` keyword set to the new installation directory.)

---

**Note** - Packages installed on the server for diskless and AutoClient systems are read-only to the client and are shared with other clients.

---

Although there are several ways to install and maintain packages in a client/server environment, this section provides instructions on how to do this from a server. This is a centralized software administration model. Note, however, that you can log in to clients and install software directly on them.

## Adding Sun Packages on Clients

In general, when installing Sun packages on clients in a homogeneous environment, follow the guidelines in Table 17-2.

**TABLE 17-2** Installing Sun Packages on Clients in a Homogeneous Environment

If the Package's Files Are Installed in The ... Then ...	
root (/) file system	Add the package using the procedure in "How to Add a Package to a Diskless or AutoClient System's root (/) File System" on page 265.
<code>/usr</code>	Add the package using the procedure in "How to Add Packages to a Standalone System" on page 257.

You can determine where a Sun package's files are installed by using the procedure "How to Determine Where a Package's Files Will Be Installed" on page 264.



## Adding Third-Party Packages on Clients

When installing third-party packages on clients, follow these guidelines:

1. Install the package on the server using the procedure “How to Add Packages to a Standalone System” on page 257.
2. Install the package on the client using the procedure “How to Add a Package to a Diskless or AutoClient System’s root (/) File System” on page 265.

---

## Adding Packages in a Heterogeneous Client/Server Environment

For the purposes of this discussion, a *heterogeneous client/server environment* means the clients and servers are either running different versions of the Solaris operating environment or are different hardware platforms (for example, a Solaris 2.3 server of Solaris 7 clients, or an x86 server with SPARC clients). Adding packages in a heterogeneous client/server environment presents its own difficulties. The server will have multiple `/usr` file systems for the heterogeneous clients it supports. For example, it might have an x86 `/usr` file system for its x86 clients, a Solaris 2.4 `/usr` file system for its Solaris 2.4 clients, and so on. In general, when installing packages in a heterogeneous client/server environment, follow the guidelines in Table 17–3.

**TABLE 17–3** Installing Packages in a Heterogeneous Environment

If the Package’s Files Are Installed in The ...	Then ...
root (/) file system	Add the package using the procedure in “How to Add a Package to a Diskless or AutoClient System’s root (/) File System” on page 265.
<code>/usr</code>	Add the package using the procedure in “How to Add Packages to a Server” on page 267.

## ▼ How to Determine Where a Package's Files Will Be Installed

This procedure is valid only for Sun software packages. For third-party software products, the surest way to determine where the package's files will be installed is to look in the package's directory in the `pkgmap` file.

### 1. Log in to any system.

You must be able to access the directory where the packages reside.

### 2. Determine where a Sun package's files will be installed.

```
$ pkgparam -d device-name pkgid SUNW_PKGTYPE
```

`-d device-name`

Specifies the absolute path to the software packages. *device-name* can be the path to a device, a directory, or a spool directory. If you do not use the `-d` option, the `pkgparam` command will return the default installation directory of the specified *pkgid* installed on the local system.

*pkgid*

Is the name of a software package.

`SUNW_PKGTYPE`

Is a special parameter that reports where a Solaris software package will be installed. If the package does not have the `SUNW_PKGTYPE` parameter set, the `pkgparam` command returns an empty string. For Sun packages, this usually means the package will be installed in `/opt`.

## Example—Determining Where a Package's Files Will Be Installed

```
$ pkgparam -d /cdrom/cdrom0/s0/Solaris_2.7
/Product SUNWvolr SUNW_PKGTYPE
root
$ pkgparam -d /cdrom/cdrom0/s0/Solaris_2.7/Product SUNWvolu SUNW_PKGTYPE
usr
```

## ▼ How to Add a Package to a Diskless or AutoClient System's root (/) File System

When you add a package to a diskless or AutoClient system, you don't actually install the package on the client. Instead, you add the package to the client's root file system, which resides on a server. A diskless or AutoClient system's root file system is typically in `/export/root/hostname` on the server.

---

**Note** - If the package's files are installed into the `/usr` file system, you need to install the package on the server. If you are working in a homogeneous client/server environment, use Table 17-2 to determine how to install the package. If you are working in a heterogeneous client/server environment, use Table 17-3 to determine how to install the package.

---

1. **Log in to the server as superuser.**
2. **Remove any already installed packages with the same names as the ones you are adding.**

This ensures that the system keeps a proper record of software that has been added and removed. There may be times when you want to maintain multiple versions of the same application on the system. For strategies on how to do this, see "Guidelines for Removing Packages" on page 252, and for task information, see "How to Remove a Diskless or AutoClient System's Package" on page 275.

3. **Add a software package to the client system's root (/) file system.**

```
server# pkgadd -R rootpath -d device-name pkgid . . .
```

<code>-R rootpath</code>	Specifies the path name of the client's root file system.
<code>-d device-name</code>	Specifies the absolute path to the software packages. <i>device-name</i> can be the path to a device, a directory, or a spool directory. If you do not specify the path where the package resides, the <code>pkgadd</code> command checks the default spool directory ( <code>/var/spool/pkg</code> ). If the package is not there, the package installation fails.
<code>pkgid</code>	(Optional) Is the name of one or more packages (separated by spaces) to be installed. If omitted, <code>pkgadd</code> installs all available packages.



---

**Caution** - During the installation, you may see the following message:

WARNING: filename <not present on Read Only file system>

This indicates that not all of the package's files have been installed. The client may not have access to all files necessary for the software to work correctly. If you see this warning message, you must also install the package on the server as well as the client's root file system.

---

4. **Verify the package has been installed by logging in to the server as superuser and using the `pkginfo` command.**

```
server# pkginfo -R rootpath | egrep pkgid
```

The `pkginfo` command returns a line of information about the installed *pkgid*. If *pkgid* is not installed, `pkginfo` returns the system prompt.

5. **Verify that the package has been installed successfully using the `pkgchk` command.**

```
server# pkgchk -R rootpath -v pkgid
```

If `pkgchk` determines there are no errors, it returns a list of installed files. Otherwise, it reports the error.

## Example—Installing a Package From a Mounted CD to a Diskless Client's Root File System

---

**Note** - The name of this release is Solaris 7 but code and path or package path names may use Solaris 2.7 or SunOS 5.7. Always follow the code or path as it is written.

---

The following example shows a command to install the `SUNWadmr` (software to support system and network administration) package from a server onto a diskless client's root file system. In this case, the diskless client's root file system is `/export/root/client-1`. This example assumes the `SUNWadmr` package is available from a mounted SPARC 2.7 Solaris CD (`/cdrom/cdrom0/s0/Solaris_2.7/Product`). The example also shows use of `pkginfo` and `pkgchk` to verify that the package's files were installed properly.

```
server# pkgadd -R /export/root/client-1
-d /cdrom/cdrom0/s0/Solaris_2.7/Product SUNWadmr
```

(continued)

(Continuation)

```
.  
. .  
Installation of <SUNWadmr> complete.  
server# pkginfo -R /export/root/client-1 | egrep SUNWadmr  
system    SUNWadmr    System & Network Administration Root  
server# pkgchk -v -R /export/root/client-1 SUNWadmr  
/etc  
/etc/init.d  
/etc/init.d/autoinstall  
/etc/init.d/sysid.net  
/etc/init.d/sysid.sys  
/etc/rc2.d  
/etc/rc2.d/S30sysid.net  
/etc/rc2.d/S71sysid.sys  
/etc/rc2.d/S72autoinstall  
/sbin  
/sbin/bpgetfile
```

## Example—Installing a Package From a Package Server to a Diskless Client's Root File System

The following example shows a command to install the SUNWcg6 package from a server onto a diskless client's root file system. In this case, the diskless client's root file system is /export/root/client-2. This example assumes the SUNWcg6 package is available from a package server on the network (/net/package-server/latest-packages).

```
server# pkgadd -R /export/root/client-2  
-d /net/package-server/latest-packages SUNWcg6  
.  
.  
.  
Installation of <SUNWcg6> complete.
```

## ▼ How to Add Packages to a Server

1. **Log in to the server as superuser.**

2. **Make sure the server has the OS services necessary for its diskless and AutoClient systems.**

Use Host Manager to verify the OS services available on the server. If you need to add OS services, you can do that using the “Add Services” capability of Host Manager. For detailed information, see Chapter 4.

**3. Determine your next step based on whether the server and the diskless or AutoClient systems are the same Solaris release and the same hardware platform.**

If the Diskless or AutoClient Systems and Server Are ...	Then ...
The same Solaris release and the same hardware architecture	Do not use this procedure. Instead, use the procedure “How to Add Packages to a Standalone System” on page 257.
Either different Solaris releases or different hardware platforms (for example, a Solaris 2.5 server of Solaris 7 diskless clients, or an x86 server of SPARC diskless clients)	Go to Step 4 on page 268.

**4. Make a copy of the default administration file.**

```
# cp /var/sadm/install/admin/default
/var/sadm/install/admin/admin-file
```

**5. Edit the new administration file and set the `basedir` keyword.**

Use a text editor to edit the new administration file and set the `basedir` keyword to the correct path for the OS services supporting the client.

```
basedir=/export/exec/Solaris_2.7_platform.all/usr
```

`Solaris_2.7`

Is the Solaris version number: for example,  
`Solaris_2.7`

`platform`

Is the hardware architecture of the client: for example,  
`i386` or `sparc`, as in `Solaris_2.7_i386.all` or  
`Solaris_2.7_sparc.all`.

**6. Add a software package to the server.**

The administration file will specify to install the package into the `/usr` file system appropriate for the client.

```
# pkgadd -a admin-file -d device-name pkgid ...
```

<code>-a admin-file</code>	(Optional) Specifies an administration file <code>pkgadd</code> should consult during the installation. By default, <code>pkgadd</code> looks in the <code>/var/sadm/install/admin</code> directory for the specified administration file. You can also specify an absolute path to an administration file.
<code>-d device-name</code>	Specifies the absolute path to the software packages. <i>device-name</i> can be the path to a device, a directory, or a spool directory. If you do not specify the path where the package resides, <code>pkgadd</code> checks the default spool directory ( <code>/var/spool/pkg</code> ). If the package is not there, the package installation fails.
<code>pkgid</code>	(Optional) Is the name of one or more packages (separated by spaces) to be installed. If omitted, <code>pkgadd</code> installs all available packages.

If the `pkgadd` command encounters a problem during installation of the package, it displays a message related to the problem, followed by this prompt:

```
Do you want to continue with this installation?
```

Respond with `yes`, `no`, or `quit`. If more than one package has been specified, type `no` to stop the installation of the package being installed. `pkgadd` continues to install the other packages. Type `quit` to stop the installation.

#### 7. Verify that the package has been installed, using the `pkginfo` command.

```
# pkginfo pkgid*
```

The `pkginfo` command will return all instances of the installed package. Typically, `pkgadd` installs duplicate versions of an already installed package as `pkgid.1`, `pkgid.2`, and so on.

#### 8. Verify that the package has been installed successfully, using the `pkgchk` command.

```
# pkgchk -v pkgid
```

If the `pkgchk` command determines there are no errors for the specified package instance, it returns a list of installed files. Otherwise, it reports the error.

## Example—Installing Software From a Mounted CD

The following example shows a command to install a fictitious package `SUNWtoolu`, which will install files into a `/usr` file system. Assume that the package resides on a

mounted product CD, which is mounted on `/cdrom/cdrom0` by default. The `pkgadd` command uses an administration file named `new-basedir`, which specifies a new installation directory for the package. The example also shows use of `pkgchk` to verify that the package's files were installed properly.

```
# pkgadd -a new-basedir /cdrom/cdrom0 SUNWtoolu
.
.
.
Installation of <SUNWtoolu> complete.
# pkgchk -v SUNWtoolu
/usr
/usr/bin
/usr/bin/toolconvert
/usr/bin/toolplay
/usr/bin/toolrecord
```

---

## Checking the Installation of Packages

You use the `pkgchk` command to check installation completeness, path name, file contents, and file attributes of a package. See `pkgchk(1M)` for more information on all the options.

Use the `pkginfo` command to display information about the packages that are installed on the system.

### ▼ How to List Information About All Installed Packages

List information about installed packages with the `pkginfo` command.

```
$ pkginfo
```

#### Example—Listing All Packages Installed

The following example shows the `pkginfo` command to list all packages installed on a local system, whether that system is a standalone, server, diskless client, or AutoClient system. The output shows the primary category, package name, and a description of the package.



```
$ pkginfo
system      SUNWab2m      Solaris Documentation Server Lookup
system      SUNWaccr      System Accounting, (Root)
system      SUNWaccu      System Accounting, (Usr)
system      SUNWadmap     System administration applications
system      SUNWadmc      System administration core libraries
```

## Example—Listing All Packages Installed on a Diskless or AutoClient System

In a diskless or AutoClient system client/server setup, you may want to manage software from a central location. Since the server is the place to do this, you would need to use a variation of the `pkginfo` command. The following example shows the `pkginfo -R` command to list all packages installed on a diskless client named `io`. This command is executed from the diskless client's server.

```
server$ pkginfo -R /export/root/io
system      SUNWaccr      System Accounting, (Root)
system      SUNWaccu      System Accounting, (Usr)
system      SUNWadmap     System & Network Administration Applications
system      SUNWadmfw     System & Network Administration Framework
.
.
.
```

## ▼ How to Check the Integrity of an Installed Package

1. Log in to a system as superuser.
2. Check the status of an installed package with the `pkgchk` command.

```
# pkgchk -a | -c -v pkgid ...
# pkgchk -d spooldir pkgid ...
```

<code>-a</code>	Specifies to audit only the file attributes (that is, the permissions), rather than the file attributes and contents, which is the default for <code>pkgchk</code> .
<code>-c</code>	Specifies to audit only the file contents, rather than the file contents and attributes, which is the default for <code>pkgchk</code> .
<code>-v</code>	Specifies verbose mode, which displays file names as <code>pkgchk</code> processes them.
<code>-d <i>spooldir</i></code>	Specifies the absolute path of the spool directory.
<code><i>pkgid</i></code>	(Optional) Is the name of one or more packages (separated by spaces). If you do not specify a <i>pkgid</i> , <code>pkgchk</code> checks all the software packages installed on the system. If omitted, <code>pkgchk</code> displays all available packages.

## Example—Checking the Contents of an Installed Package

The following example shows how to check the contents of a package.

```
# pkgchk -c SUNWadmfw
```

If `pkgchk` determines there are no errors, it returns the system prompt. Otherwise, it reports the error.

## Example—Checking the File Attributes of an Installed Package

The following example shows how to check the file attributes of a package.

```
# pkgchk -a SUNWadmfw
```

If `pkgchk` determines there are no errors, it returns the system prompt. Otherwise, it reports the error.

## Example—Checking Packages Installed in a Spool Directory

The following example shows how to check a software package copied to a spool directory (`/export/install/packages`).

```
# pkgchk -d /export/install/packages
## checking spooled package <SUNWadmap>
```

(continued)

(Continuation)

```
## checking spooled package <SUNWadmfw>
## checking spooled package <SUNWadmhc>
## checking spooled package <SUNWsdml>
```

---

**Note** - The checks made on a spooled package are limited because not all information can be audited until a package is installed.

---

## ▼ How to Display Detailed Information About a Package

List information about installed packages with the `pkginfo -l` command.

```
$ pkginfo -l pkgid ...
```

`-l` Specifies to display output in long format, which includes all available information about the package.

`pkgid` (Optional) Is the name of one or more packages (separated by spaces). If omitted, `pkginfo` displays information about all available packages.

### Example—Displaying Detailed Information About a Package

```
$ pkginfo -l SUNWcar
  PKGINST: SUNWcar
    NAME: Core Architecture, (Root)
  CATEGORY: system
    ARCH: sparc.sun4m
  VERSION: 11.6.0,REV=1998.05.06.20.36
  BASEDIR: /
  VENDOR: Sun Microsystems, Inc.
    DESC: core software for a specific hardware platform group
  PSTAMP: on99819980507193137
  INSTDATE: Jun 02 1998 11:43
  HOTLINE: Please contact your local service provider
  STATUS: completely installed
  FILES:
    48 installed pathnames
    5 shared pathnames
    7 directories
    20 executables
    3299 blocks used (approx)
```

---

# Removing Packages From Servers and Standalone Systems

---



**Caution** - Always use the `pkgrm` command to remove installed packages. Do not use the `rm` command, which will corrupt the system's record-keeping of installed packages.

---

## ▼ How to Remove a Package

1. Log in to the system as superuser.
2. Remove an installed package.

```
# pkgrm pkgid ...
```

*pkgid*

(Optional) Is the name of one or more packages (separated by spaces). If omitted, `pkgrm` removes all available packages.

## ▼ How to Remove a Spooled Package

1. Log in as superuser.
2. Remove a package from a spool directory with the `pkgrm -s` command.

```
# pkgrm -s spooldir pkgid ...
```

`-s spooldir`

Specifies the name of the spool directory where the package was spooled.

*pkgid*

(Optional) Is the name of one or more packages (separated by spaces). If no *pkgid* is supplied, `pkgrm` prompts the user to remove each package listed in the spool directory. If omitted, `pkgrm` removes all available packages.

## ▼ How to Remove a Diskless or AutoClient System's Package

1. Log in to the server and become superuser.
2. Remove a software package from a diskless client's OS server with the `pkgrm -R` command.

```
server# pkgrm -R rootpath pkgid ...
```

`-R rootpath` Specifies the mount point of the client's root file system.

`pkgid` (Optional) Is the name of one or more packages (separated by spaces) to be removed. If omitted, `pkgrm` removes all available packages.

Files in the client's package database that are marked shared are not removed from the server, but are removed from the client's database. If all clients have removed the package, you can remove the shared files from the server by using a separate invocation of `pkgrm` on the server.

3. Verify that the package has been removed successfully by using the `pkginfo` command.

```
server# pkginfo -R rootpath | egrep pkgid
```

If `pkgid` is installed, the `pkginfo` command returns a line of information about it. Otherwise, `pkginfo` returns the system prompt.

### Example—Removing a Diskless Client's Package

In the following example, assume the client's root file system is shared. Also, assume these commands are executed on the client's server.

```
server# pkgrm -R /export/root/client-1 SUNWaudio
The following package is currently installed.
SUNWaudio
Do you want to remove this package? y/n/q?

y
.
.
```

(continued)

(Continuation)

```
.
```

---

## Adding and Removing Packages Using Admintool

The Solaris 7 operating environment includes Admintool, which is a graphical user interface for performing several administration tasks, including adding and removing software packages. Specifically, you can use Admintool to:

- Add software packages to a local system
- Remove software packages from a local system
- View software already installed on the local system
- Customize software packages to be installed
- Specify an alternate installation directory for a software package

### ▼ How to Add Packages With Admintool

**1. Log in to the installed system and become superuser.**

At the shell prompt, type:

```
$ su
```

Unless you are a member of the UNIX sysadmin group (group 14), you must become superuser on your system to add or remove software packages with Admintool.

**2. Load a CD into the CD-ROM drive.**

Volume Manager will automatically mount the CD.

**3. Start Admintool.**

```
# admintool &
```

The Users window is displayed.


**4. Choose Software from the Browse menu.**

The Software window is displayed.

**5. Choose Add from the Edit menu.**

The Set Source Media window may appear. If so, specify the path to the installation media and click on OK. The default path is a mounted SPARC Solaris CD.

The Add Software window is displayed.



**6. Select the software you want to install on the local system.**

In the Software portion of the window, click on the check boxes corresponding to the software you want to install.

**7. Click on Add.**

A Command Tool window appears for each package being installed, displaying the installation output.

The Software window refreshes to display the packages just added.

## ▼ How to Remove Packages With Admintool

### 1. Log in to the installed system and become superuser.

At the shell prompt, type:

```
$ su
```


Unless you are a member of the UNIX sysadmin group (group 14), you must become superuser on your system to add or remove software packages with Admintool.

### 2. Start Admintool.

```
# admintool &
```

### 3. Choose Software from the Browse menu.

The Software window is displayed.



### 4. Select the software you want to remove from the local system.

### 5. Choose Delete from the Edit menu.

A warning pop-up window is displayed to confirm whether you really want to delete the software.



**6. Click on Delete to confirm that you want to remove the software.**

For each package that is being deleted, a Command Tool window is displayed that asks for confirmation, again, before deleting the software. Type `y`, `n`, or `q`. If you choose to delete the software, the output from the removal process is displayed.



## Patch Administration (Overview)

---

For the purpose of this discussion, patch administration involves installing or removing Solaris patches from a running Solaris system. It may also involve removing (called *backing out*) unwanted or faulty patches.

This is a list of the overview information in this chapter.

- “What Is a Patch” on page 281
- “Tools For Managing Patches” on page 282
- “Patch Distribution” on page 282
- “Patch Numbering” on page 284
- “What Happens When You Install a Patch” on page 284
- “What Happens When You Remove a Patch” on page 285

---

### What Is a Patch

In its simplest form, you can think of a patch as a collection of files and directories that replace or update existing files and directories that are preventing proper execution of the software. The existing software is derived from a specified *package* format, which conforms to the Application Binary Interface. (For details about packages, see Chapter 16.)

## Tools For Managing Patches

There are two utilities for managing patches:

- `patchadd` - use to install directory-format patches to a Solaris 7 system.
- `patchrm` - use to remove patches installed on a Solaris 7 system. This command restores the file system to its state before a patch was applied.

Detailed information about how to install and back out a patch is provided in the `Install.info` file with each patch. Each patch also contains a `README` file that contains specific information about the patch.

Before installing patches, you might want to know more about patches that have previously been installed. Table 18-1 shows commands that provide useful information about patches already installed on a system.

**TABLE 18-1** Helpful Commands for Patch Administration

Command	Function
<code>showrev -p</code>	Shows all patches applied to a system.
<code>pkgparam <i>pkgid</i> PATCHLIST</code>	Shows all patches applied to the package identified by <i>pkgid</i> .
<code>pkgparam <i>pkgid</i> PATCH_INFO_patch-number</code>	Shows the installation date and name of the host from which the patch was applied. <i>pkgid</i> is the name of the package: for example, <code>SUNWadmap</code> .
<code>patchadd -R <i>client_root_path</i> -p</code>	Shows all patches applied to a client, from the server's console.
<code>patchadd -p</code>	Shows all patches applied to a system.

## Patch Distribution

All Sun customers can access security patches and other recommended patches via the World Wide Web or anonymous `ftp`. Sun customers who have purchased a service contract can access an extended set of patches and a complete database of

patch information. This information is available via the World Wide Web, anonymous `ftp`, and it is regularly distributed on a CD-ROM (See Table 18-2).

**TABLE 18-2** Customer Patch Access Information

If You Are ...	Then ...
A Sun Service customer	<p>You have access to the SunSolve database of patches and patch information. These are available via the World Wide Web or anonymous <code>ftp</code>, as described in “Patch Access Via the World Wide Web” on page 283 and “Patch Access Via <code>ftp</code>” on page 284.</p> <p>These patches are updated nightly. You also receive a patch CD-ROM every 6 to 8 weeks.</p>
Not a Sun Service customer	<p>You have access to a general set of security patches and other recommended patches. These are available via the World Wide Web or anonymous <code>ftp</code>, as described in “Patch Access Via the World Wide Web” on page 283 and “Patch Access Via <code>ftp</code>” on page 284.</p>

## What You Need to Access Sun Patches

You can access Sun patches via the World Wide Web or anonymous `ftp`. If you have purchased a Sun service contract, you will also be able to get patches from the patch CD-ROM that is regularly distributed.

To access patches on the World Wide Web, you need a machine that is:

- Connected to the Internet
- Capable of running Web browsing software such as Mosaic or Netscape

To access patches via anonymous `ftp`, you need a machine that is:

- Connected to the Internet
- Capable of running the `ftp` program

## Patch Access Via the World Wide Web

To access patches via the World Wide Web, use this uniform resource locator (URL):

`http://www.sun.com/`

After reaching the Sun home page, click on the Sales and Service button and navigate your way to the SunSolve patch database.

The patch database for publicly available patches are labeled “Public patch access.” The patch database for the comprehensive set of patches and patch information available to contract customers is labeled “Contract customer patch access.” You will be prompted for a password to access this contract customer database.

You can also access publicly available patches using this URL:

`http://sunsite.unc.edu/`

## Patch Access Via `ftp`

To access patches via `ftp`, you can use the `ftp` command to connect to either the `sunsolve1.sun.com` (provided by Sun Service) or `sunsite.unc.edu` (maintained by the University of North Carolina). When `ftp` prompts you for a login, enter `anonymous` as the login name. Use your complete email address when prompted for a password. After the connection is complete, you can find publicly available patches in the `/pubs/patches` directory.

---

**Note** - To transfer patches, you will need to change the `ftp` transfer mode to binary. To do this, enter `bin` at the `ftp` prompt.

---

---

## Patch Numbering

Patches are identified by unique alphanumeric strings, with the patch base code first, a hyphen, and a number that represents the patch revision number. For example, patch 101977-02 is a Solaris 2.4 patch to correct the `lockd` daemon.

---

## What Happens When You Install a Patch

When you install a patch, the `patchadd` command copies files from the patch directory to a local system's disk. More specifically, `patchadd`:

- Determines the Solaris version number of the managing host and the target host
- Updates the patch package's `pkginfo` file with information about patches obsoleted by the patch being installed, other patches required by this patch, and patches incompatible with this patch

During the patch installation, `patchadd` keeps a log of the patch installation in `/var/sadm/patch/patch-number/log` for the Solaris 2.4 release and compatible

versions. The Solaris 2.5 release and compatible versions also store log files in this location, but only if installation errors occurred.

The `patchadd` command will not install a patch under the following conditions:

- The package is not fully installed on the host
- The patch's architecture differs from the system's architecture
- The patch's version does not match the installed package's version
- There is already an installed patch with the same base code and a higher version number
- The patch is incompatible with another, already installed patch. (Each installed patch keeps this information in its `pkginfo` file)
- The patch being installed requires another patch that is not installed

---

## What Happens When You Remove a Patch

When you back out a patch, the `patchrm` command restores all files modified by that patch, unless:

- The patch was installed with `patchadd -d` (which instructs `patchadd` not to save copies of files being updated or replaced)
- The patch has been obsoleted by a later patch
- The patch is required by another patch

The `patchrm` command calls `pkgadd` to restore packages that were saved from the initial patch installation.

During the patch installation, `patchrm` keeps a log of the patch installation in `/tmp/backoutlog.process_id`. This log file is removed if the patch backs out successfully.





## PART VI Managing Devices

---

This part provides instructions for managing devices in the Solaris environment. This part contains these chapters.

Chapter 19	Provides a high-level overview of device configuration and step-by-step instructions for configuring devices.
Chapter 20	Provides an overview of device naming conventions and instructions for accessing devices.



## Device Management (Overview/Tasks)

---

The chapter provides overview information about managing peripheral devices in the Solaris environment.

This is a list of overview information in this chapter.

- “Where to Find Device Management Tasks” on page 290
- “About Device Drivers” on page 291
- “Automatic Configuration of Devices” on page 291
- “Adding a Peripheral Device to a System” on page 293
- “Displaying Device Configuration Information” on page 296

This is a list of step-by-step instructions in this chapter.

- “How to Add a Peripheral Device” on page 293
- “How to Add a Device Driver” on page 295
- “How to Display System Configuration Information” on page 297
- “How to Display Device Information” on page 299

For information about accessing devices, see Chapter 20.

Device management in the Solaris environment usually includes adding and removing peripheral devices from systems, possibly adding a third-party device driver to support a device, and displaying system configuration information.

---

## What’s New in Device Management?

This section provides information about Solaris 7 features related to device management.

# Dynamic Reconfiguration

*Dynamic reconfiguration*, available on certain SPARC servers, allows a service provider to remove replace hotpluggable system I/O boards in a running system, eliminating the time lost in rebooting. Also, if a replacement board is not immediately available, the system administrator can use dynamic reconfiguration to shut down a failing board while allowing the system to continue operation.

See your hardware manufacturer’s documentation for informaiton about whether dynamic reconfiguration is supported on your server.

## x86: SCSI Disk Driver (sd)

In previous Solaris release, SCSI disk suport on the Intel platform was handled by the `cmdk` driver. In the Solaris 7 release, this support is handled by the `sd` driver. This driver is similar to the SCSI disk driver on Solaris SPARC platforms, which is also named `sd`.

There is no change in the administration of these devices. System administrators will see references to `sd` instead of `cmdk` in the output of `prtconf`, `sysdef`, and `dmesg` commands, as well as the `format` utility.

Features and functionality are a superset of the features supplied by `cmdk`, so applications (which use logical disk names in `/dev/dsk` will not be affected by the driver change. x86 systems with IDE devices will still use the `cmdkdriver`.

---

# Where to Find Device Management Tasks

Table 19-1 describes where to find step-by-step procedures for adding serial devices, such as printers and modems, and peripheral devices, such as a disk, CD-ROM, or tape drive to your system.

**TABLE 19-1** Where to Find Instructions for Adding a Device

For Information On ...	See the Following
Adding a disk	Chapter 23 or Chapter 24
Adding a CD-ROM or tape device	“How to Add a Peripheral Device” on page 293

TABLE 19-1 Where to Find Instructions for Adding a Device (continued)

For Information On ...	See the Following
Adding a modem	“Managing Terminals and Modems (Overview)” in <i>System Administration Guide, Volume II</i>
Adding a printer	“Print Management (Overview)” in <i>System Administration Guide, Volume II</i>

## About Device Drivers

A computer typically uses a wide range of peripheral and mass-storage devices. Your system, for example, probably has a SCSI disk drive, a keyboard and a mouse, and some kind of magnetic backup medium. Other commonly used devices include CD-ROM drives, printers and plotters, light pens, touch-sensitive screens, digitizers, and tablet-and-stylus pairs.

The Solaris software does not directly communicate with all these devices. Each type of device requires different data formats, protocols, and transmission rates.

A *device driver* is a low-level program that allows the operating system to communicate with a specific piece of hardware. The driver serves as the operating system’s “interpreter” for that piece of hardware.

## Automatic Configuration of Devices

The kernel, consisting of a small generic core with a platform-specific component and a set of modules, is configured automatically in the Solaris environment.

A kernel module is a hardware or software component that is used to perform a specific task on the system. An example of a *loadable* kernel module is a device driver that is loaded when the device is accessed.

The platform-independent kernel is `/kernel/genunix`. The platform-specific component is `/platform/`uname -m`/kernel/unix`.

The kernel modules are described in Table 19-2.

**TABLE 19-2** Description of Kernel Modules

Location	This Directory Contains ...
<code>/platform/`uname -m`/kernel</code>	Platform-specific kernel components
<code>/kernel</code>	Kernel components common to all platforms that are needed for booting the system
<code>/usr/kernel</code>	Kernel components common to all platforms within a particular instruction set

The system determines what devices are attached to it at boot time. Then the kernel configures itself dynamically, loading needed modules into memory. At this time, device drivers are loaded when devices, such as disk and tape devices, are accessed for the first time. This process is called *autoconfiguration* because all kernel modules are loaded automatically when needed.

You can customize the way in which kernel modules are loaded by modifying the `/etc/system` file. See “Tuning Kernel Parameters (Tasks)” in *System Administration Guide, Volume II* for instructions on modifying this file.

## Features and Benefits

The benefits of autoconfiguration are:

- Main memory is used more efficiently because modules are loaded when needed.
- There is no need to reconfigure the kernel when new devices are added to the system.
- Drivers can be loaded and tested without having to rebuild the kernel and reboot the system.

The autoconfiguration process is used by a system administrator when adding a new device (and driver) to the system. At this time, the administrator performs a reconfiguration boot so the system will recognize the new device.

## What You Need For Unsupported Devices

Device drivers needed to support a wide range of standard devices are included in the Solaris environment. These drivers can be found in the `/kernel/drv` and `/platform/`uname -m`/kernel/drv` directories.

However, if you've purchased an unsupported device, the manufacturer should provide the software needed for the device to be properly installed, maintained, and administered.

At a minimum, this software includes a device driver and its associated configuration (.conf) file. The .conf files reside in the `drv` directories. In addition, the device may be incompatible with Solaris utilities, and may require custom maintenance and administrative utilities.

Contact your device manufacturer for more information.

---

## Adding a Peripheral Device to a System

Adding a new peripheral device usually involves:

- Shutting down the system
- Connecting the device to the system
- Rebooting the system

Use the procedure below to add the following devices to a system:

- CD-ROM
- Secondary disk drive
- Tape drive
- SBUS card

In some cases, you may have to add a third-party device driver to support the new device.

### ▼ How to Add a Peripheral Device

1. **Become superuser.**
2. **Follow steps 2 and 3 of “How to Add a Device Driver” on page 295 if you need to add a device driver to support the device.**
3. **Create the `/reconfigure` file.**

```
# touch /reconfigure
```

The `/reconfigure` file will cause the Solaris software to check for the presence of any newly installed devices the next time you turn on or boot your system.

4. **Shut down the system.**

```
# shutdown -i0 -g30 -y
```

-i0	Brings the system to the 0 init state, which is the appropriate state for turning the system power off for adding and removing devices.
-g30	Shuts the system down in 30 seconds. The default is 60 seconds.
-y	Continues the system shutdown without user intervention; otherwise, you are prompted to continue the shutdown process.

**5. Turn off power to the system after it is shut down.**

On SPARC Platforms ...	On Intel Platforms ...
It is safe to turn off power if the ok or > prompt is displayed.	It is safe to turn off power if the type any key to continue prompt is displayed.

Refer to the hardware installation guide that accompanies your system for the location of the power switch.

**6. Turn off power to all external devices.**

For location of power switches on any peripheral devices, refer to the hardware installation guides that accompany your peripheral devices.

**7. Install the peripheral device making sure the device you are adding has a different target number than the other devices on the system.**

You will often find a small switch located at the back of the disk for this purpose. Refer to the hardware installation guide that accompanies the peripheral device for information on installing and connecting the device.

**8. Turn on the power to the system.**

The system will boot to multiuser mode and the login prompt will be displayed.

**9. Verify that the peripheral device has been added by attempting to access the device. See Chapter 20 for information on accessing the device.**



## ▼ How to Add a Device Driver

This procedure assumes that the device has already been added to the system. If not, see “How to Add a Peripheral Device” on page 293.

1. **Become superuser.**
2. **Place the tape, diskette, or CD-ROM into the drive.**
3. **Use the `pkgadd` command install the driver.**

```
# pkgadd -d device package-name
```

`-d device`

Identifies the device pathname.

`package-name`

Identifies the package name that contains the device driver.

4. **Verify that the package has been added correctly by using the `pkgchk` command. The system prompt returns with no response if the package is installed correctly.**

```
# pkgchk packagename  
#
```

### Example—Adding a Device Driver

The following example installs and verifies a package called XYZdrv.

```
# pkgadd XYZdrv  
(licensing messages displayed)  
.  
.  
.  
Installing XYZ Company driver as <XYZdrv>  
.  
.  
.  
Installation of <XYZdrv> was successful.  
# pkgchk XYZdrv
```

(continued)

(Continuation)

#

---

## Displaying Device Configuration Information

Three commands are used to display system and device configuration information:

<code>prtconf(1M)</code>	Displays system configuration information, including total amount of memory and the device configuration as described by the system's device hierarchy. The output displayed by this command depends upon the type of system.
<code>sysdef(1M)</code>	Displays device configuration information including system hardware, pseudo devices, loadable modules, and selected kernel parameters.
<code>dmesg(1M)</code>	Displays system diagnostic messages as well as a list of devices attached to the system since the last reboot.

See “Device Naming Conventions” on page 302 for information on the device names used to identify devices on the system.

### driver not attached Message

The following driver-related message may be displayed by the `prtconf` and `sysdef` commands:

```
device, instance #number (driver not attached)
```

This message does not always mean that a driver is unavailable for this device. It means that no driver is *currently* attached to the device instance because there is no device at this node or the device is not in use. Drivers are loaded automatically when the device is accessed and unloaded when the device is not in use.

## Identifying a System's Devices

Use the output of `prtconf` and `sysdef` commands to identify which disk, tape, and CD-ROM devices are connected to the system. The output of these commands display the `driver not attached` messages next to the device instances. Since these devices are always being monitored by some system process, the `driver not attached` message is usually a good indication that there is no device at that device instance.

For example, the following `prtconf` output identifies a device at instance #3 and instance #6, which is probably a disk device at target 3 and a CD-ROM device at target 6 of the first SCSI host adapter (`esp`, instance #0).

```
$ /usr/sbin/prtconf
.
.
.
esp, instance #0
    sd (driver not attached)
    st (driver not attached)
    sd, instance #0 (driver not attached)
    sd, instance #1 (driver not attached)
    sd, instance #2 (driver not attached)
    sd, instance #3
    sd, instance #4 (driver not attached)
    sd, instance #5 (driver not attached)
    sd, instance #6
.
.
.
```

The same device information can be gleaned from the `sysdef` output.

## ▼ How to Display System Configuration Information

Use the `prtconf` command to display system configuration information.

```
# /usr/sbin/prtconf
```

Use the `sysdef` command to display system configuration information including pseudo devices, loadable modules, and selected kernel parameters.

```
# /usr/sbin/sysdef
```

## Examples—Displaying System Configuration Information

The following `prtconf` output is displayed on a SPARC system.

```

# prtconf
System Configuration: Sun Microsystems sun4m
Memory size: 32 Megabytes
System Peripherals (Software Nodes):

SUNW,SPARCstation-10
  packages (driver not attached)
    disk-label (driver not attached)
    deblocker (driver not attached)
    obp-tftp (driver not attached)
  options, instance #0
  aliases (driver not attached)
  openprom (driver not attached)
  iommu, instance #0
    sbus, instance #0
      espdma, instance #0
      esp, instance #0
        sd (driver not attached)
        st (driver not attached)
        sd, instance #0 (driver not attached)
        sd, instance #1
        sd, instance #2 (driver not attached)
        sd, instance #3
        sd, instance #4 (driver not attached)
        sd, instance #5 (driver not attached)
        sd, instance #6 (driver not attached)
.
.
.

```

The following sysdef output is displayed from an x86 system.

```

# sysdef
* Hostid
*
  29f10b4d
*
* i86pc Configuration
*
*
* Devices
*
+boot (driver not attached)
  memory (driver not attached)
  aliases (driver not attached)
  chosen (driver not attached)
  i86pc-memory (driver not attached)
  i86pc-mmio (driver not attached)
  openprom (driver not attached)
  options, instance #0
  packages (driver not attached)
  delayed-writes (driver not attached)
  itu-props (driver not attached)
  isa, instance #0

```

(continued)

(Continuation)

```
motherboard (driver not attached)
pnpADP,1542, instance #0
asy, instance #0
asy, instance #1
lp, instance #0 (driver not attached)
fdc, instance #0
fd, instance #0
fd, instance #1 (driver not attached)
kd (driver not attached)
kdmouse (driver not attached)
.
.
.
```

## ▼ How to Display Device Information

Display device information with the `dmesg` command.

```
# /usr/sbin/dmesg
```

The `dmesg` output is displayed as messages on the system console and identifies which devices are connected to the system since the last reboot.

## Examples—Displaying Device Information

The following `dmesg` output is displayed from a SPARC system.

```
# dmesg
SunOS Release 5.7 Version generic [UNIX(R) System V Release 4.0]
Copyright (c) 1983-1998, Sun Microsystems, Inc.
pac: enabled - SuperSPARC
cpu0: TI,TMS390Z50 (mid 8 impl 0x0 ver 0x0 clock 40 MHz)
mem = 32768K (0x2000000)
avail mem = 27803648
Ethernet address = 8:0:20:1f:33:9g
root nexus = SUNW,SPARCstation-10
iommu0 at root: obio 0xe0000000
sbus0 at iommu0: obio 0xe0001000
dma0 at sbus0: SBus slot f 0x400000
dma0 is /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000
/iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000 (esp0):
 esp-options=0x46
esp0 at dma0: SBus slot f 0x800000 sparc ipl 4
esp0 is /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000
sdl at esp0: target 1 lun 0
```

(continued)

(Continuation)

```
sd1 is /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/sd@1,0
sd3 at esp0: target 3 lun 0
sd3 is /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/sd@3,0
root on /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/sd@3,0:a ...
obio0 at root
obio0 at obio0: obio 0x100000 sparc ipl 12
zs0 is /obio/zs@0,100000
obiol at obio0: obio 0x0 sparc ipl 12
zsl is /obio/zs@0,0
cpu 0 initialization complete - online
ledma0 at sbus0: SBus slot f 0x400010
le0 at ledma0: SBus slot f 0xc00000 sparc ipl 6
le0 is /iommu@f,e0000000/sbus@f,e0001000/ledma@f,400010/le@f,c00000
dump on /dev/dsk/c0t3d0s1 size 200 MB
#
```

The following dmesg output is displayed from an x86 system.

```
# dmesg
SunOS Release 5.7 Version generic [UNIX(R) System V Release 4.0]
Copyright (c) 1983-1998, Sun Microsystems, Inc.
mem = 130684K (0x7f9f000)
avail mem = 114970624
root nexus = i86pc
isa0 at root
ISA-device: asy0
asy0 is /isa/asy@1,3f8
ISA-device: asy1
asy1 is /isa/asy@1,2f8
pci0 at root: space 0 offset 0
IDE device at targ 0, lun 0 lastlun 0x0
model WDC AC31000H, stat 50, err 0
cfg 0x427a, cyl 2100, hd 16, sec/trk 63
mult1 0x8010, mult2 0x108, dwcap 0x0, cap 0xf00
piomode 0x180, dmamode 0x200, advpiomode 0x1
minpio 380, minpioflow 180
valid 0x3, dwdma 0x3, majver 0x0
ata_set_feature: (0x66,0x0) failed
ISA-device: ata0
Disk0: cmdk0 at ata0 target 0 lun 0
cmdk0 is /isa/ata@1,1f0/cmdk@0,0
root on /isa/ata@1,1f0/cmdk@0,0:a fstype ufs
Number of console virtual screens = 13
cpu 0 initialization complete - online
Ethernet address = 2:7:1:1c:27:e5
.
.
.
```

## Accessing Devices (Overview)

---

This chapter provides information about how system administrators access the devices on their systems.

This is a list of overview information in this chapter.

- “Accessing Devices” on page 301
- “Logical Disk Device Names” on page 302
- “Logical Tape Device Names” on page 306
- “Logical CD-ROM Device Names” on page 307

For overview information about configuring devices, see Chapter 19.

---

## Accessing Devices

System administrators need to know how to specify device names when using commands to manage disks, file systems, and other devices. In most cases, system administrators use logical device names to represent devices connected to the system. Both logical and physical device names are represented on the system by logical and physical device files.

## How Device Information Is Created

When a system is booted for the first time, a device hierarchy is created to represent all the devices connected to the system. The kernel uses the device hierarchy information to associate drivers with their appropriate devices, and provides a set of

pointers to the drivers that perform specific operations. See *OpenBoot 3.x Command Reference Manual* for more information on device hierarchy information.

## Device Naming Conventions

Devices are referenced in three ways in the Solaris environment.

- **Physical device name** – Represents the full device pathname in the device information hierarchy. Physical device names are displayed using the following commands:

- `dmesg`
- `format`
- `sysdef`
- `prtconf`

Physical device files are found in the `/devices` directory.

- **Instance name** – Represents the kernel's abbreviation name for every possible device on the system. For example, `sd0` and `sd1` represent the instance names of two disk devices. Instance names are mapped in the `/etc/path_to_inst` file and are displayed using the following commands:

- `dmesg`
- `sysdef`
- `prtconf`

- **Logical device name** – Used by system administrators with most file system commands to refer to devices. See Table 20–1 for a list of file commands that use logical device names. Logical device files in the `/dev` directory are symbolically linked to physical device files in the `/devices` directory.

---

## Logical Disk Device Names

Logical device names are used to access disk devices when you:

- Add a new disk to the system
- Move a disk from one system to another
- Access (or mount) a file system residing on a local disk
- Back up a local file system

Many administration commands take arguments that refer to a disk slice or file system.



Refer to a disk device by specifying the subdirectory to which it is symbolically linked (either `/dev/dsk` or `/dev/rdsk`), followed by a string identifying the particular controller, disk, and slice.

`/dev/[r]dsk/cwtxdysz`

Controller, Target, Drive, and Slice Identifier

Disk Subdirectory

## Specifying the Disk Subdirectory

Disk and file administration commands require the use of either a *raw* (or *character*) device interface, or a *block* device interface. The distinction is made by how data is read from the device.

Raw device interfaces transfer only small amounts of data at a time. Block device interfaces include a buffer from which large blocks of data are read at once.

Different commands require different interfaces.

- When a command requires the raw device interface, specify the `/dev/rdsk` subdirectory. (The “r” in `rdsk` stands for “raw.”)
- When a command requires the block device interface, specify the `/dev/dsk` subdirectory.
- When you’re not sure whether a command requires use of `/dev/dsk` or `/dev/rdsk`, check the man page for that command.

Table 20–1 shows which interface is required for a few commonly used disk and file system commands.

**TABLE 20–1** Device Interface Type Required by Some Frequently Used Commands

Command	Interface Type	Example of Use
<code>df(1M)</code>	Block	<code>df /dev/dsk/c0t3d0s6</code>
<code>fsck(1M)</code>	Raw	<code>fsck -p /dev/rdsk/c0t0d0s0</code>
<code>mount(1M)</code>	Block	<code>mount /dev/dsk/clt0d0s7 /export/home</code>

**TABLE 20-1** Device Interface Type Required by Some Frequently Used Commands *(continued)*

Command	Interface Type	Example of Use
<code>newfs(1M)</code>	Raw	<code>newfs /dev/rdisk/c0t0d1s1</code>
<code>prtvtoc(1M)</code>	Raw	<code>prtvtoc /dev/rdisk/c0t0d0s2</code>

## Specifying the Slice

The string you use to identify a specific slice on a specific disk depends on the controller type, either direct or bus-oriented. Table 20-2 describes the different types of direct or bus-oriented controllers on different platforms.

**TABLE 20-2** Controller Types


Direct controllers	Bus-Oriented Controllers
Xylogics (SPARC)	SCSI (SPARC/x86)
IDE (x86)	IPI (SPARC)

The conventions for both types of controllers are explained in the following subsections.

**Note** - Controller numbers are assigned automatically at system initialization. The numbers are strictly logical and imply no direct mapping to physical controllers.

## SPARC: Disks With Direct Controllers

To specify a slice on a disk with a direct controller on a SPARC system, follow the naming convention shown in Figure 20-1.




**Figure 20-1** Naming Convention for Disks With Direct Controllers on SPARC Systems

To indicate the whole disk, specify slice 2 (2).

If you have only one controller on your system, `x` will always be 0.

## x86: Disks With Direct Controllers

To specify a slice on a disk with an IDE controller on an x86 system, follow the naming convention shown in Figure 20-2.




**Figure 20-2** Naming Convention for Disks With IDE Controllers on x86 Systems

To indicate the entire Solaris `fdisk` partition, specify slice 2 (`s2`).

If you have only one controller on your system, `w` will always be 0.

## SPARC: Disks With Bus-Oriented Controllers

To specify a slice on a disk with a bus-oriented controller (SCSI, for instance) on a SPARC system, follow the naming convention shown in Figure 20-3.



**Figure 20-3** Naming Convention for Disks With Bus-Oriented Controllers on SPARC Systems

If you have only one controller on your system, *w* will always be 0.

For SCSI controllers, *x* is the target address as set by the switch on the back of the unit, and *y* is the logical unit number (LUN) of the drive attached to the target. If the disk has an embedded controller, *y* is usually 0.

To indicate the whole disk, specify slice 2 (*s2*).

## x86: Disks With SCSI Controllers

To specify a slice on a disk with a SCSI controller on an x86 system, follow the naming convention shown in Figure 20-4.




Figure 20-4 Naming Convention for Disks With SCSI Controllers on x86 Systems

If you have only one controller on your system, *v* will always be 0.


For SCSI controllers, *w* is the target address as set by the switch on the back of the unit, and *x* is the logical unit number (LUN) of the drive attached to the target. If the disk has an embedded controller, *x* is usually 0.

To indicate the entire Solaris `fdisk` partition, specify slice 2 (*s2*).

---

## Logical Tape Device Names

Logical tape device files are found in the `/dev/rmt/*` directory as symbolic links from the `/devices` directory.



The first tape device connected to the system is 0 (`/dev/rmt/0`), which may be one of the following types: QIC-11, QIC-24, QIC-150, or Exabyte. Tape density values (l, m, h, c, and u) are described in Chapter 38.

---

## Logical CD-ROM Device Names

The logical device name that represents the first CD-ROM device on a system is `/dev/dsk/c0t6d0s0`.

Since CD-ROMS are managed by Volume Management, the logical CD-ROM device name is usually not used unless you want to mount the CD manually. See Chapter 11 for information on accessing your CD-ROM device.



## PART VII Managing Disks

---

This part provides instructions for managing disks in the Solaris environment. This part contains these chapters.

Chapter 21	Provides an overview of Solaris disk slices and an introduction to the <code>format</code> utility.
Chapter 22	Provides step-by-step instructions for formatting a disk, examining disk labels, and repairing a defective disk sector.
Chapter 23	Provides step-by-step instructions for adding a disk to a SPARC system.
Chapter 24	Provides step-by-step instructions for adding a disk to an x86 system.
Chapter 25	Provides a description of the <code>format</code> utility's menu and commands. This chapter also includes information about the <code>format.dat</code> file, rules for providing input to <code>format</code> commands, and instructions on using the help facility.





## Disk Management (Overview)

---

This overview chapter provides conceptual information about Solaris disk slices and introduces the `format` utility.

This is a list of the overview information in this chapter.

- “Disk Terminology” on page 312
- “About Disk Slices” on page 312
- “SPARC: Disk Slices” on page 313
- “x86: Disk Slices” on page 314
- “Determining Which Slices to Use” on page 317
- “The `format` Utility” on page 318
- “Guidelines for Using the `format` Utility” on page 320
- “Formatting a Disk” on page 321
- “About Disk Labels” on page 322
- “Partition Table” on page 322

For instructions on how to add a disk drive to your system, see Chapter 23 or Chapter 24.

---

## Where to Find Disk Management Tasks

Use these references to find step-by-step instructions for managing disks.

- Chapter 23
- Chapter 24

---

## Introduction

Managing disks in the Solaris environment usually involves setting up the system and running the Solaris installation program to create the appropriate disk slices and install the operating system. Occasionally, you may need to use the `format` utility to add a new disk drive or replace a defective one.

---

## Disk Terminology

Before you can effectively use the information in this section, you should be familiar with basic disk architecture. In particular, you should be familiar with the following terms:

- Track
- Cylinder
- Sector
- Disk controller
- Disk label
- Device drivers

If you are unfamiliar with these terms, refer to the glossary (for a brief definition) or product information from the disk's manufacturer.

---

## About Disk Slices

Files stored on a disk are contained in file systems. Each file system on a disk is assigned to a *slice*—a group of cylinders set aside for use by that file system. Each disk slice appears to the operating system (and to the system administrator) as though it were a separate disk drive.

See for information about file systems.

---

**Note** - Slices are sometimes referred to as partitions. This book uses *slice*, but, certain interfaces, such as the `format` utility, refer to slices as partitions.

---

When setting up slices, remember these rules:

- Each disk slice holds only one file system.

- No file system can span multiple slices.

Slices are set up slightly differently on SPARC and x86 platforms. Table 21–1 summarizes the differences:

**TABLE 21–1** Slice Differences on Platforms

SPARC Platforms	x86 Platforms
Whole disk is devoted to Solaris environment	Disk is divided into <code>fdisk</code> partitions, one per operating environment
Disk is divided into eight slices, numbered 0-7	The Solaris <code>fdisk</code> partition is divided into 10 slices, numbered 0-9

## SPARC: Disk Slices

On SPARC systems, Solaris defines eight disk slices and assigns to each a conventional use. These slices are numbered 0 through 7. Table 21–2 summarizes the contents of the eight Solaris slices on a SPARC system.

**TABLE 21–2** SPARC: Customary Disk Slices

Slice	File System	Usually Found on Client or Server Systems?	Purpose
0	root	Both	Holds files and directories that make up the operating system.
1	swap	Both	Provides virtual memory, or <i>swap space</i> . Swap space is used when running programs are too large to fit in a computer's memory. The Solaris operating environment then “swaps” programs from memory to the disk and back as needed.
2	—	both	Refers to the entire disk, by convention. It is defined automatically by Sun's <code>format</code> and the Solaris installation programs. The size of this slice should not be changed.

**TABLE 21-2** SPARC: Customary Disk Slices *(continued)*

Slice	File System	Usually Found on Client or Server Systems?	Purpose
3	/export	Server only	Holds alternative versions of the operating system. These alternative versions are required by client systems whose architectures differ from that of the server. Clients with the same architecture type as the server obtain executables from the /usr file system, usually slice 6.
4	/export/ swap	Server only	Provides virtual memory space for client systems.
5	/opt	Both	Holds application software added to a system. If a slice is not allocated for this file system during installation, the /opt directory is put in slice 0.
6	/usr	Both	Holds operating system commands—also known as <i>executables</i> —designed to be run by users. This slice also holds documentation, system programs ( <i>init</i> and <i>syslogd</i> , for example) and library routines.
7	/home or /export/ home	Both	Holds files created by users.

## x86: Disk Slices

On x86 systems, disks are divided into *fdisk* partitions. An *fdisk* partition is a section of the disk reserved for a particular operating environment, such as Solaris.

Solaris places ten slices, numbered 0-9, on the Solaris *fdisk* partition on a disk in an x86 system, as shown in Table 21-3.

TABLE 21-3 x86: Customary Disk Slices

Slice	File System	Usually Found on Client or Server Systems?	Purpose
0	root	Both	Holds the files and directories that make up the operating system.
1	swap	Both	Provides virtual memory, or <i>swap space</i> . Swap space is used when running programs are too large to fit in a computer's memory. The Solaris operating environment then "swaps" programs from memory to the disk and back as needed.
2	—	Both	Refers to the entire disk, by convention. It is defined automatically by Sun's <code>format</code> utility and the Solaris installation programs. The size of this slice should not be changed.
3	/export	Server only	Holds alternative versions of the operating system. These alternative versions are required by client systems whose architectures differ from that of the server.
4	/export/ swap	Server only	Provides virtual memory space for the client systems.
5	/opt	Both	Holds application software added to a system. If a slice is not allocated for this file system during installation, the /opt directory is put in slice 0.
6	/usr	Both	Holds operating system commands—also known as <i>executables</i> —that are run by users. This slice also holds documentation, system programs ( <code>init</code> and <code>syslogd</code> , for example) and library routines.
7	/home or / export/ home	Both	Holds files created by users.

TABLE 21-3 x86: Customary Disk Slices *(continued)*

Slice	File System	Usually Found on Client or Server Systems?	Purpose
8	—	Both	Contains information necessary for Solaris to boot from the hard disk. It resides at the beginning of the Solaris partition (although the slice number itself does not indicate this), and is known as the boot slice.
9	—	Both	Provides an area reserved for alternate disk blocks. Slice 9 is known as the alternate sector slice.

## Using Raw Data Slices

The SunOS operating system stores the disk label in block 0, cylinder 0 of each disk. This means that using third-party database applications that create raw data slices must not start at block 0, cylinder 0, or the disk label will be overwritten and the data on the disk will be inaccessible.

Do not use the following areas of the disk for raw data slices, which are sometimes created by third-party database applications:

1. Block 0, cylinder 0, where the disk label is stored.
2. Avoid cylinder 0 entirely for improved performance.
3. Slice 2, which represents the entire disk.

## Slice Arrangements on Multiple Disks

Although a single disk that is large enough can hold all slices and their corresponding file systems, two or more disks are often used to hold a system's slices and file systems.

---

**Note** - A slice cannot be split between two or more disks. However, multiple swap slices on separate disks are allowed.

---

For instance, a single disk might hold the root (/) file system, a swap area, and the /usr file system, while a separate disk is provided for the /export/home file system and other file systems containing user data.

In a multiple disk arrangement, the disk containing the operating system software and swap space (that is, the disk holding the root (/) or /usr file systems or the

slice for swap space) is called the *system disk*. Disks other than the system disk are called *secondary disks* or *non-system disks*.

Locating a system's file systems on multiple disks allows you to modify file systems and slices on the secondary disks without having to shut down the system or reload operating system software.

Having more than one disk also increases input-output (I/O) volume. By distributing disk load across multiple disks, you can avoid I/O bottlenecks.

## Determining Which Slices to Use

When you set up a disk's file systems, you choose not only the size of each slice, but also which slices to use. Your decisions about these matters depend on the configuration of the system to which the disk is attached and the software you want to install on the disk.

There are five system configurations:

- Servers
- Diskless clients
- Standalone systems
- Dataless clients
- Solstice AutoClient systems

Each system configuration requires the use of different slices. Table 21-4 lists these requirements.

**TABLE 21-4** System Configurations and Slice Requirements

Slice	Servers	Diskless Clients	Standalone Systems	AutoClient Systems
0	root	(on server)	root	root
1	swap	(on server)	swap	swap
2	—	—	—	—
3	/export	—	—	—
4	/export/swap	—	—	—
5	/opt	(on server)	/opt	(on server)

**TABLE 21-4** System Configurations and Slice Requirements *(continued)*

Slice	Servers	Diskless Clients	Standalone Systems	AutoClient Systems
6	/usr	(on server)	/usr	(on server)
7	/export/home	(on server)	/home	(on server)

See Chapter 4 for more information about system configurations.

**Note** - The Solaris installation program provides slice size recommendations based on the software you select for installation.

## The `format` Utility

Read the following information if you want to see a conceptual view of the `format` utility and it uses before proceeding to the “how-to” or reference sections.

### Definition

The `format` utility is a system administration tool used to prepare hard disk drives for use on your Solaris system. The `format` utility cannot be used on diskette drives, CD-ROM drives, or tape drives.

### Features and Benefits

Table 21-5 shows the features and associated benefits that the `format` utility provides.



**TABLE 21-5** Features and Benefits of the `format` Utility

Feature	Benefit
Searches your system for all attached disk drives	Reports: <ul style="list-style-type: none"><li>■ Target location</li><li>■ Disk geometry</li><li>■ Whether the disk is formatted</li><li>■ If the disk has mounted partitions</li></ul>
Retrieves disk labels	Used in repair operations
Repairs defective sectors	Allows administrators to repair disk drives with recoverable errors instead of sending the drive back to the manufacturer
Formats and analyzes a disk	Creates sectors on the disk and verifies each sector
Partitions a disk	Divides a disk so individual file systems can be created on separate slices
Labels a disk	Writes disk name and configuration information to the disk for future retrieval (usually for repair operations)

All of the options of the `format` utility are fully described in Chapter 25.

## When to Use the `format` Utility

Disk drives are partitioned and labeled by the Solaris installation program as part of installing the Solaris release. You may need to use the `format` utility when:

- Displaying slice information
- Dividing a disk into slices
- Adding a disk drive to an existing system
- Formatting a disk drive
- Repairing a disk drive

The main reason a system administrator uses the `format` utility is to divide a disk into disk slices. These steps are covered in Chapter 23 and Chapter 24.

See Table 21-6 for guidelines on using the `format` utility.

## Guidelines for Using the `format` Utility

TABLE 21-6 The `format` Utility Guidelines

Use <code>format</code> To ...	Considerations ...	Where to Go ...
Format a disk	<ul style="list-style-type: none"><li>■ Any existing data will be destroyed when a disk is reformatted.</li><li>■ The need for formatting a disk drive has dropped as more and more manufacturers ship their disk drives formatted and partitioned. You may not need to use the <code>format</code> utility when adding a disk drive to an existing system.</li><li>■ If a disk has been relocated and is displaying a lot of disk errors, you can attempt to reformat it, which will automatically remap any bad sectors.</li></ul>	"How to Format a Disk" on page 332
Replace a system disk	<ul style="list-style-type: none"><li>■ Data from the damaged system disk must be restored from a backup medium; otherwise the system will have to be reinstalled by using the installation program.</li></ul>	Chapter 23 or Chapter 24 or if the system must be reinstalled, <i>Solaris Advanced Installation Guide</i>
Divide a disk into slices	<ul style="list-style-type: none"><li>■ Any existing data will be destroyed when a disk with existing slices is repartitioned and relabeled.</li><li>■ Existing data must be copied to backup media before the disk is repartitioned and restored after the disk is relabeled.</li></ul>	Chapter 23 or Chapter 24

**TABLE 21-6** The `format` Utility Guidelines (continued)

Use <code>format</code> To ...	Considerations ...	Where to Go ...
Add a secondary disk to an existing system	<ul style="list-style-type: none"> <li>Any existing data must be restored from backup media if the secondary disk is reformatted or repartitioned.</li> </ul>	Chapter 23 or Chapter 24
Repair a disk drive	<ul style="list-style-type: none"> <li>Some customer sites prefer to replace rather than repair defective drives. If your site has a repair contract with the disk drive manufacturer, you may not need to use the <code>format</code> utility to repair disk drives.</li> <li>Repairing a disk drive usually means that a bad sector is added to a defect list. New controllers remap bad sectors automatically with no system interruption.</li> <li>If the system has an older controller, you may need to remap a bad sector and restore any lost data.</li> </ul>	Chapter 25

## Formatting a Disk

In most cases, disks are formatted by the manufacturer or reseller and do not need to be reformatted when you install the drive. To determine whether or not a disk is formatted, use the `format` utility. See “How to Determine If a Disk is Formatted” on page 331 for more information.

If you determine that a disk is not formatted, use the `format` utility to format the disk.

Formatting a disk accomplishes two steps:

- Preparing disk media for use
- Compiling a list of disk defects based on a surface analysis



**Caution** - Formatting is a destructive process—it overwrites data on the disk. For this reason, disks are usually formatted only by the manufacturer or reseller. If you think disk defects are causing recurring problems, you can use the `format` utility to do a surface analysis, but be careful to use only the commands that do not destroy data. See “How to Format a Disk” on page 332 for details.

A small percentage of total disk space available for data is used to store defect and formatting information. This percentage varies according to disk geometry, and decreases as the disk ages and develops more defects.

Formatting may take anywhere from a few minutes to several hours, depending on the type and size of the disk.

# About Disk Labels

A special area of every disk is set aside for storing information about the disk's controller, geometry, and slices. That information is called the disk's *label*. Another term used to describe the disk label is the VTOC (Volume Table of Contents). To *label* a disk means to write slice information onto the disk. You usually label a disk after changing its slices.

If you fail to label a disk after creating slices, the slices will be unavailable because the operating system has no way of "knowing" about the slices.

# Partition Table

An important part of the disk label is the *partition table* which identifies a disk's slices, the slice boundaries (in cylinders), and total size of the slices. A disk's partition table can be displayed using the `format` utility. Table 21-7 describes partition table terminology.

TABLE 21-7 Partition Table Terminology

Partition Term	Value	Description
Number	0-7	Partition or (slice number). Valid numbers are 0-7.
Tag	0=UNASSIGNED 1=BOOT 2=ROOT 3=SWAP 4=USR 5=BACKUP 7=VAR 8=HOME	A numeric value that usually describes the file system mounted on this partition.
Flags		

**TABLE 21-7** Partition Table Terminology *(continued)*

Partition Term	Value	Description
	wm	The partition is writable and mountable.
	wu rm	The partition is writable and unmountable. This is the default state of partitions dedicated for swap areas. However, the <code>mount</code> command does not check the “not mountable” flag.
	rm	The partition is read only and mountable.

Partition flags and tags are assigned by convention and require no maintenance.

See “How to Display Disk Slice Information” on page 334 or “How to Examine a Disk Label” on page 338 for more information on displaying the partition table.

## Examples—Partition Tables

The following partition table example is displayed from a 535-Mbyte disk using the `format` utility:

Part	Tag	Flag	Cylinders	Size	Blocks
0	root	wm	0 - 292	80.12MB	(293/0/0) 164080
1	swap	wu	293 - 410	32.27MB	(118/0/0) 66080
2	backup	wm	0 - 1865	510.23MB	(1866/0/0) 1044960
3	unassigned	wm	0	0	(0/0/0) 0
4	unassigned	wm	0	0	(0/0/0) 0
5	home	wm	411 - 1311	246.37MB	(901/0/0) 504560
6	usr	wm	1312 - 1718	111.29MB	(407/0/0) 227920
7	unassigned	wm	1719 - 1865	40.20MB	(147/0/0) 82320

The partition table contains the following information:

Column Name	Description
Part	Partition (or slice number). See Table 21-7 for a description of this column.
Tag	Partition tag. See Table 21-7 for a description of this column.

Column Name	Description
Flags	Partition flag. See Table 21-7 for a description of this column.
Cylinders	The starting and ending cylinder number for the slice.
Size	The slice size in Mbytes.
Blocks	The total number of cylinders and the total number of sectors per slice in the far right column.

The following example displays a disk label using the `prtvtoc` command.

```
# prtvtoc /dev/rdisk/c0t3d0s0
* /dev/rdisk/c0t3d0s0 partition map
*
* Dimensions:
*   512 bytes/sector
*   80 sectors/track
*   9 tracks/cylinder
*   720 sectors/cylinder
*   2500 cylinders
*   1151 accessible cylinders
*
* Flags:
*   1: unmountable
*   10: read-only
*
*
* Partition Tag Flags First Sector Count Last Sector Mount Directory
* 0 2 00 0 66240 66239 /
* 1 3 01 66240 131760 197999
* 2 5 00 0 828720 828719
* 3 0 00 198000 66240 264239 /export
* 4 0 00 264240 66240 330479 /export/swap
* 5 0 00 330480 72000 402479 /opt
* 6 4 00 402480 385200 787679 /usr
* 7 8 00 787680 41040 828719 /export/home
#
```

The disk label includes the following information:

**Dimensions** – This section describes the physical dimensions of the disk drive.

**Flags** – This section describes the flags listed in the partition table section. See Table 21-7 for a description of partition flags.

**Partition (or Slice) Table** – This section contains the following information:

Column Name	Description
Partion	Partition (or slice number). See Table 21–7 for a description of this column.
Tag	Partition tag. See Table 21–7 for a description of this column.
Flags	Partition flag. See Table 21–7 for a description of this column.
First Sector	The first sector of the slice.
Sector Count	The total number of sectors in the slice.
Last Sector	The last sector number in the slice.
Mount Directory	The last mount point directory for the file system.

## Dividing a Disk Into Slices

The `format` utility is most often used by system administrators to divide a disk into slices. The steps are:

- Determining which slices are needed
- Determining the size of each slice
- Using the `format` utility to divide the disk into slices
- Labeling the disk with new slice information
- Creating the file system for each slice

The easiest way to divide a disk into slices is to use the `modify` command from the `partition` menu. The `modify` command allows you to create slices by specifying the size of each slice in megabytes without having to keep track of starting cylinder boundaries. It also keeps tracks of any disk space remainder in the “free hog” slice.

## Using the Free Hog Slice

When you use the `format` utility to change the size of one or more disk slices, you designate a temporary slice that will expand and shrink to accommodate the resizing operations.

This temporary slice donates, or “frees,” space when you expand a slice, and receives, or “hogs,” the discarded space when you shrink a slice. For this reason, the donor slice is sometimes called the *free hog*.

The donor slice exists only during installation or when you run the `format` utility. There is no permanent donor slice during day-to-day, normal operations.

See “SPARC: How to Create Disk Slices and Label a Disk” on page 356 or “x86: How to Create Disk Slices and Label a Disk” on page 376 for information on using the free hog slice.



## Administering Disks (Tasks)

---

This chapter contains disk administration procedures. Many of the procedures described in this chapter are optional if you are already familiar with how disks are managed on systems running the Solaris release.

This is a list of step-by-step instructions in this chapter.

- “How to Identify the Disks on a System” on page 329
- “How to Determine If a Disk is Formatted” on page 331
- “How to Format a Disk” on page 332
- “How to Display Disk Slice Information” on page 334
- “How to Label a Disk” on page 336
- “How to Examine a Disk Label” on page 338
- “How to Recover a Corrupted Disk Label” on page 339
- “How to Create a `format.dat` Entry” on page 343
- “How to Automatically Configure a SCSI Drive” on page 345
- “How to Identify a Defective Sector by Using Surface Analysis” on page 347
- “How to Repair a Defective Sector” on page 349

For overview information about disk management, see Chapter 21.

---

## Administering Disks Task Map

**TABLE 22-1** Administering Disks Task Map

Task	Description	For Instructions, Go To
1. Identify the Disks on a System	If you are not sure of the types of disks on a system, use the <code>format</code> utility to identify the disk types.	“How to Identify the Disks on a System” on page 329
2. Format the Disk	Determine whether a disk is already formatted by using the <code>format</code> utility.  In most cases, disks are already formatted. Use the <code>format</code> utility if you need to format a disk.	“How to Determine If a Disk is Formatted” on page 331  “How to Format a Disk” on page 332
3. Display Slice Information	Display slice information by using the <code>format</code> utility.	“How to Display Disk Slice Information” on page 334
4. Label the Disk	Create the disk label by using the <code>format</code> utility.	“How to Label a Disk” on page 336
5. Examine the Disk Label	Examine the disk label by using the <code>prvtoc</code> command.	“How to Examine a Disk Label” on page 338
6. Create a <code>format.dat</code> Entry	Create a <code>format.dat</code> entry to support a third-party disk.	“How to Create a <code>format.dat</code> Entry” on page 343
7. Repair a Defective Disk Sector	Identify a defective disk sector by using the <code>format</code> utility.	“How to Identify a Defective Sector by Using Surface Analysis” on page 347
8. If Necessary, Fix a Defective Disk Sector	Fix a defective disk sector by using the <code>format</code> utility.	“How to Repair a Defective Sector” on page 349

---

## Identifying Disks on a System

Use the `format` utility to discover the types of disks that are connected to a system. You can also use the `format` utility to verify that a disk is known to the system. See Chapter 25 for information on using the `format` utility.

### ▼ How to Identify the Disks on a System

1. **Become superuser.**
2. **Identify the disks that are recognized on the system with the `format` utility.**

```
# format
```

The `format` utility displays a list of disks that it recognizes under  
AVAILABLE DISK SELECTIONS.

### Examples—Identifying the Disks on a System

The following `format` output is from a system with two disks.

```
# format
Searching for disks...done
AVAILABLE DISK SELECTIONS:
  0. c0t1d0 <SUN1.05 cyl 2036 alt 2 hd 14 sec 72>
    /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/
sd@1,0
  1. c0t3d0 <SUN1.05 cyl 2036 alt 2 hd 14 sec 72>
    /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/
sd@3,0
Specify disk (enter its number):
```

The `format` output associates a disk's physical and local device name to the disk's marketing name which appears in brackets `<>`. This is an easy way to identify which local device names represent the disks connected to your system. See Chapter 20 for a description of local and physical device names.

The following example uses a wildcard to display the disks connected to a second controller.

```
# format /dev/rdisk/c2*
AVAILABLE DISK SELECTIONS:
  0. /dev/rdsk/c2t0d0s0 <SUN2.1G cyl 2733 alt 2 hd 19 sec 80>
    /io-unit@f,e0200000/sbi@0,0/QLGC,isp@2,10000/sd@0,0
  1. /dev/rdsk/c2t1d0s0 <SUN2.1G cyl 2733 alt 2 hd 19 sec 80>
    /io-unit@f,e0200000/sbi@0,0/QLGC,isp@2,10000/sd@1,0
  2. /dev/rdsk/c2t2d0s0 <SUN2.1G cyl 2733 alt 2 hd 19 sec 80>
    /io-unit@f,e0200000/sbi@0,0/QLGC,isp@2,10000/sd@2,0
  3. /dev/rdsk/c2t3d0s0 <SUN2.1G cyl 2733 alt 2 hd 19 sec 80>
    /io-unit@f,e0200000/sbi@0,0/QLGC,isp@2,10000/sd@3,0
  4. /dev/rdsk/c2t5d0s0 <SUN2.1G cyl 2733 alt 2 hd 19 sec 80>
    /io-unit@f,e0200000/sbi@0,0/QLGC,isp@2,10000/sd@5,0
Specify disk (enter its number):
```

The following example identifies the disks on a SPARC based system.

```
# format
AVAILABLE DISK SELECTIONS:
  0. c0t3d0 <SUN2.1G cyl 2733 alt 2 hd 19 sec 80>
    /iommu@0,10000000/sbus@0,10001000/espdma@5,8400000/esp@5,8800000/
    sd@3,0
Specify disk (enter its number):
```

The format output identifies that disk 0 (target 3) is connected to the first SCSI host adapter (espdma@. . .), which is connected to the first SBus device (sbus@0. . .). The output also associates both the physical and logical device name to the disk's marketing name, SUN02.1G.

The following example identifies the disks on an x86 based system.

```
# format
Searching for disks...done
AVAILABLE DISK SELECTIONS:
  0. c0t0d0 <DEFAULT cyl 507 alt 2 hd 64 sec 32>
    /eisa/dpt@5c88,0/cmdk@0,0
  1. c0t3d0 <DEFAULT cyl 1852 alt 2 hd 15 sec 74>
    /eisa/dpt@5c88,0/cmdk@3,0
Specify disk (enter its number):
```

The format output identifies that disk 0, target 0 (cmdk@0, 0) is connected to the first DPT host adapter (dpt@5. . .), which is connected to the EISA device (eisa). The format output on an x86 based system does not identify disks by their marketing names.

## Where to Go From Here

Check the following table if the format utility did not recognize the disk.

If the Disk ...	Then ...
Is newly added and you didn't perform a reconfiguration boot	Go to Chapter 23 or Chapter 24.
Is a third-party disk	Go to "Creating a <code>format.dat</code> Entry" on page 343.
Label was corrupted by a system problem, such as a power failure	Go to "How to Label a Disk" on page 336.
Is not properly connected to the system	Connect the disk to the system using your disk hardware documentation.

## Formatting a Disk

Disks are formatted by the manufacturer or reseller and usually do not need to be reformatted when you install the drive.

A disk must be formatted before:

- You can write data to it. However, most disks are already formatted.
- You can use the Solaris installation program to install the system.



**Caution** - Formatting is a destructive process—it overwrites data on the disk. For this reason, disks are usually formatted only by the manufacturer or reseller. If you think disk defects are causing recurring problems, you can use the `format` utility to do a surface analysis, but be careful to use only the commands that do not destroy data.

### ▼ How to Determine If a Disk is Formatted

1. **Become superuser.**
2. **Enter the `format` utility.**

```
# format
```

3. **Enter the number of the disk that you want to check from the list displayed on your screen.**

```
Specify disk (enter its number): 0
```

4. Verify that the disk you chose is formatted by identifying the following message.

```
[disk formatted]
```

## Example—Determining If a Disk Is Formatted

The following example shows that disk `c0t3d0` is formatted.

```
# format
AVAILABLE DISK SELECTIONS:
    0. c0t1d0 <SUN1.05 cyl 2036 alt 2 hd 14 sec 72>
       /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/
sd@1,0
    1. c0t3d0 <SUN1.05 cyl 2036 alt 2 hd 14 sec 72>
       /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/
sd@3,0
Specify disk (enter its number): 0
selecting c0t1d0
[disk formatted]
```

## ▼ How to Format a Disk

1. Become superuser.
2. Enter the `format` utility.

```
# format
```

3. Enter the number of the disk that you want to format from the list displayed on your screen.

```
Specify disk (enter its number): 0
```



---

**Warning** - Do not select the system disk. Formatting your system disk deletes your operating system and any data that you may have on this disk.

---

4. To begin formatting the disk, enter `format` at the `format>` prompt. Confirm the command by typing `y`.

```
format> format
Ready to format. Formatting cannot be interrupted
and takes 26 minutes (estimated). Continue? yes
```

**5. Verify that the disk format is successful by identifying the following messages.**

```
Formatting ...
done
Verifying media ...
pass 0 - pattern = 0xc6dec6de
2035/12/18
pass 1 - pattern = 0x6db6db6d
2035/12/18
total of 0 defective blocks repaired.
```

## Example—Formatting a Disk

The following example formats the disk c0t2d0.

```
# format
Searching for disks...done
AVAILABLE DISK SELECTIONS:
    0. c0t1d0 <SUN1.05 cyl 2036 alt 2 hd 14 sec 72>
        /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/
sd@1,0
    1. c0t3d0 <SUN1.05 cyl 2036 alt 2 hd 14 sec 72>
        /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/
sd@3,0
Specify disk (enter its number):0
Selecting c0t1d0
[disk unformatted]
format> format
Ready to format. Formatting cannot be interrupted
and takes 26 minutes (estimated). Continue? yes
Beginning format. The current time is Wed Jun 10 10:24:48 1998
Formatting ...
done
Verifying media ...
pass 0 - pattern = 0xc6dec6de
2035/12/18
pass 1 - pattern = 0x6db6db6d
2035/12/18
total of 0 defective blocks repaired.
```

(continued)

(Continuation)

```
format>
```

---

## Displaying Disk Slices

You can use the `format` utility to check whether or not a disk has the appropriate disk slices. If you determine that a disk does not contain the slices you want to use, use the `format` utility to re-create them and label the disk. See “SPARC: How to Create Disk Slices and Label a Disk” on page 356 or “x86: How to Create Disk Slices and Label a Disk” on page 376 for information on creating disk slices.

---

**Note** - The `format` utility uses the term *partition* in place of *slice*.

---

### ▼ How to Display Disk Slice Information

1. **Become superuser.**
2. **Enter the `format` utility.**

```
# format
```

3. **Identify the disk for which you want to display slice information by selecting a disk listed under AVAILABLE DISK SELECTIONS.**

```
Specify disk (enter its number):1
```

4. **Enter the partition menu by typing `partition` at the `format>` prompt.**

```
format> partition
```

5. **Display the slice information for the current disk drive by typing `print` at the `partition>` prompt.**

```
partition> print
```



6. Exit the `format` utility by typing `q` at the `partition>` prompt and typing `q` at the `format>` prompt.

```
partition> q
format> q
#
```

7. Verify displayed slice information by identifying specific slice tags and slices.

If the screen output shows that no slice sizes are assigned, the disk probably does not have slices.

## Examples—Displaying Disk Slice Information

The following example displays slice information for disk `/dev/rdisk/c0t3d0`.

```
# format
Searching for disks...done
Specify disk (enter its number):1
Selecting c0t3d0
format> partition
partition> print
Current partition table (original):
Total disk cylinders available: 1866 + 2 (reserved cylinders)
Part      Tag      Flag    Cylinders      Size      Blocks
 0         root      wm       0 - 292    80.12MB   (293/0/0)   164080
 1         swap      wu     293 - 410    32.27MB   (118/0/0)    66080
 2        backup      wm       0 - 1865   510.23MB   (1866/0/0) 1044960
 3 unassigned      wm         0           0         (0/0/0)         0
 4 unassigned      wm         0           0         (0/0/0)         0
 5         home      wm     411 - 1311   246.37MB   (901/0/0)   504560
 6         usr      wm    1312 - 1718   111.29MB   (407/0/0)   227920
 7 unassigned      wm    1719 - 1865    40.20MB   (147/0/0)    82320
partition> q
format> q
#
```

See Chapter 21 for a detailed description of the slice information displayed in these examples.

The following example displays the slice information on disk `/dev/rdisk/c0t0d0`.

```
# format
Searching for disks...done
Specify disk (enter its number): 0
selecting c0t0d0
[disk formatted]
format> partition
partition> print
Current partition table (original):
Total disk cylinders available: 1479 + 2 (reserved cylinders)
```

Part	Tag	Flag	Cylinders	Size	Blocks
0	root	wm	1 - 400	108.01MB	(400/0/0) 221200
1	swap	wu	401 - 556	42.12MB	(156/0/0) 86268
2	backup	wu	0 - 1479	399.63MB	(1480/0/0) 818440
3	unassigned	wm	0	0	(0/0/0) 0
4	unassigned	wm	0	0	(0/0/0) 0
5	unassigned	wm	557 - 734	48.06MB	(178/0/0) 98434
6	usr	wm	735 - 1401	180.10MB	(667/0/0) 368851
7	home	wm	1402 - 1476	20.25MB	(75/0/0) 41475
8	boot	wu	0 - 0	0.27MB	(1/0/0) 553
9	unassigned	wm	0	0	(0/0/0) 0

```
partition> q
format> q
```

## Creating and Examining a Disk Label

Labeling a disk is usually done during system installation or when you are creating new disk slices. You may need to relabel a disk if the disk label is corrupted (for example, from a power failure).

The format utility will attempt to automatically configure any unlabeled SCSI disk. If format is able to automatically configure an unlabeled disk, it will display a message like the following:

```
c1t0d0:configured with capacity of 404.65MB
```

### ▼ How to Label a Disk

1. **Become superuser.**
2. **Enter the format utility.**

```
# format
```

3. Enter the number of the disk that you want to label from the list displayed on your screen.

```
Specify disk (enter its number):1
```

4. Use the table below to determine how to label the disk.

If the Disk Is Unlabeled and Was Successfully Configured ...	If the Disk Was Labeled and You Want to Change the Type, or Format Was Not Able to Automatically Configure the Disk ...
Format will ask if you want to label the disk. Go to step 5 to label the disk.	You must specify the disk type. Go to steps 6-7 to set the disk type and label the disk.

5. Label the disk by typing **y** at the `Label it now?` prompt.

```
Disk not labeled. Label it now? y
```

The disk is now labeled. Go to step 10 to exit the `format` utility.

6. Enter **type** at the `format>` prompt.

```
format> type
```

Format displays the Available Drive Types menu.

7. Select a disk type from the list of possible disk types.

```
Specify disk type (enter its number)[8]: 8
```

8. Label the disk. If the disk is not labeled, the following message is displayed.

```
Disk not labeled. Label it now? y
```

Otherwise you are prompted with this message:

```
Ready to label disk, continue? y
```

9. Use the `verify` command from the `format` main menu to verify the disk label.

```
format> verify
```

**10. Exit the `format` utility by typing `q` at the `format>` prompt.**

```
partition> q
format> q
#
```

## Example—Labeling a Disk

The following example automatically configures and labels a 424-Mbyte disk.

```
# format
clt0d0: configured with capacity of 404.65MB

AVAILABLE DISK SELECTIONS:
  0. c0t3d0 <SUN0424 cyl 1151 alt 2 hd 9 sec 80>
    /sbus@1,f8000000/esp@0,8000000/sd@3,0
  1. clt0d0 <SUN0424 cyl 1151 alt 2 hd 9 sec 80>
    /sbus@1,f8000000/QLGC,isp@1,10000/sd@0,0
Specify disk (enter its number): 1
Disk not labeled. Label it now? yes
format> verify
#
```

## ▼ How to Examine a Disk Label

Examine disk label information by using the `prtvtoctoc(1M)` command. See Chapter 21 for a detailed description of the disk label and the information displayed by the `prtvtoctoc` command.

1. **Become superuser.**
2. **Display the disk label information by using the `prtvtoctoc` command.**

```
# prtvtoctoc /dev/rdisk/device-name
```

*device-name*

Raw disk device you want to examine.

## Example—Examining a Disk Label

The following example shows the disk label information for disk `/dev/rdisk/c0t0d0s0`.

```
# prtvtoc /dev/rdisk/c0t0d0s0
* c0t0d0s0 partition map
*
* Dimensions:
*   512 bytes/sector
*   36 sectors/track
*   9 tracks/cylinder
*   324 sectors/cylinder
*   1272 cylinders
*   1254 accessible cylinders
*
* Flags:
*   1: unmountable
*   10: read-only
*
*
* Partition Tag Flags First Sector Count Last Sector Mount Directory
* 0 2 00 0 37260 37259 /
* 1 3 01 37260 77760 115019
* 2 5 00 0 406296 406295
* 6 4 00 115020 283824 398843 /usr
* 7 6 00 398844 7452 406295 /export/home
#
```

## Recovering a Corrupted Disk Label

Sometimes a power or system failure will cause a disk's label to become unrecognizable. This doesn't always mean that the slice information or the disk's data will have to be recreated or restored.

The first step to recovering a corrupted disk label is to label the disk with the correct geometry and disk type information. This can be done through the normal disk labeling method, either automatic configuration or manual disk type specification.

If format recognizes the disk type, the next step is to search for a backup label to label the disk. Labeling the disk with the backup label will label the disk with the correct partitioning information, the disk type, and disk geometry.

### ▼ How to Recover a Corrupted Disk Label

1. **Boot the system to single-user mode. If necessary, boot the system from a local CD-ROM or the network in single-user mode to access the disk.**

See Chapter 8 or Chapter 9 for information on booting the system.

**2. Use the `format` utility to relabel the disk.**

```
# format
```

At this point, `format` attempts to automatically configure any unlabeled SCSI disk. If `format` is able to configure the unlabeled and corrupted disk, it will display:

```
cwtxdy: configured with capacity of abcMB
```

The `format` utility then displays the list of disks on the system.

**3. Enter the number of the disk that you need to recover from the list displayed on your screen.**

```
Specify disk (enter its number): 1
```

**4. Use the table below to determine how to label the disk.**

If the Disk was Successfully Configured ...	If the Disk was not Successfully Configured ...
Follow steps 5 and 6. Then go to step 12.	Follow steps 7-11. Then go to step 12.

**5. Search for the backup label by using the `verify` command.**

```
format> verify
Warning: Could not read primary label.
Warning: Check the current partitioning and 'label' the disk or
use the 'backup' command.
Backup label contents:
Volume name = <          >
ascii name  = <SUN0424 cyl 1151 alt 2 hd 9 sec 80>
pcyl        = 2500
ncyl        = 1151
acyl        = 2
nhead       = 9
nsect       = 80
Part   Tag   Flag   Cylinders      Size      Blocks
  0     root   wm      0 - 91      32.34MB   (92/0/0)   66240
  1     swap   wu      92 - 183    32.34MB   (92/0/0)   66240
  2    backup   wu      0 - 1150   404.65MB  (1151/0/0) 828720
  3 unassigned wm       0           0         (0/0/0)    0
  4 unassigned wm       0           0         (0/0/0)    0
```

(continued)

(Continuation)

5	unassigned	wm	0	0	(0/0/0)	0
6	usr	wm	184 - 1150	339.96MB	(967/0/0)	696240
7	unassigned	wm	0	0	(0/0/0)	0

6. If `format` was able to find a backup label and the backup label contents appear satisfactory, use the `backup` command to label the disk with the backup label.

```
format> backup
Disk has a primary label, still continue? y

Searching for backup labels...found.
Restoring primary label
```

The disk label has been recovered. Go to step 12.

7. If `format` was not able to automatically configure the disk, specify the disk type using the `type` command.

```
format> type
```

The `format` utility displays the Available Drives Type menu.

8. Select 0 to automatically configure the disk, or select a disk type from the list of possible disk types.

```
Specify disk type (enter its number)[8]: 8
```

9. If the disk was successfully configured, reply with `no` when `format` asks if you want to label the disk.

```
Disk not labeled. Label it now? no
```

10. Use the `verify` command to search for backup labels.

```
format> verify
Warning: Could not read primary label.
Warning: Check the current partitioning and 'label' the disk
or use the 'backup' command.
.
.
.
```

**11. If format was able to find a backup label and the backup label contents appear satisfactory, use the `backup` command to label the disk with the backup label.**

```
format> backup
Disk has a primary label, still continue? y

Searching for backup labels...found.
Restoring primary label
```

The disk label has been recovered.

**12. Exit the `format` utility by typing `q`.**

```
format> q
```

**13. Verify the file systems on the recovered disk by using the `fsck` command.**

See Chapter 31 for information about using the `fsck` command.

---

## Adding a Third-Party Disk

The Solaris environment supports many third-party disks. However, you may need to supply either a device driver, a `format.dat` entry, or both of these.

If the third-party disk was designed to work with standard SunOS operating system-compatible device drivers, creating an appropriate `format.dat` entry should be enough to allow the disk to be recognized by the `format` utility. In other cases, you'll need to load a third-party device driver to support the disk.



---

**Note** - Sun cannot guarantee that its `format` utility will work properly with all third-party disk drivers. If the disk driver is not compatible with the Solaris `format` utility, the disk drive vendor should supply you with a custom format program.

---

This section discusses what to do if some of this software support is missing. Typically, this occurs when you invoke the `format` utility and find that the disk type is not recognized.

Supply the missing software as described in this section, and then refer to the appropriate configuration procedure for adding system disks or secondary disks in Chapter 23 or Chapter 24.

## Creating a `format.dat` Entry

Unrecognized disks cannot be formatted without precise information about the disk's geometry and operating parameters. This information is supplied in the `/etc/format.dat` file.

---

**Note** - SCSI-2 drives do not require a `format.dat` entry. Starting with the Solaris 2.3 release, the `format` utility automatically configures the SCSI-2 drivers if the drives are powered on during a reconfiguration boot. See “How to Automatically Configure a SCSI Drive” on page 345 for step-by-step instructions on configuring a SCSI disk drive automatically.

---

If your disk was not recognized, use a text editor to create an entry in `format.dat` for the disk. You'll need to gather all the pertinent technical specifications about the disk and its controller before you start. This information should have been provided with the disk. If not, contact the disk manufacturer or your supplier. See Chapter 25 for more information on adding an entry to the `/etc/format.dat` file.

### ▼ How to Create a `format.dat` Entry

1. **Become superuser.**
2. **Make a copy of the `/etc/format.dat` file.**

```
# cp /etc/format.dat /etc/format.dat.gen
```

3. **Modify the `/etc/format.dat` file to include an entry for the third-party disk using the `format.dat` information described in Chapter 25.**

Use the disk's hardware product documentation to gather the required information.

## Automatically Configuring SCSI Disk Drives

In Solaris 2.3 release and compatible versions, the `format` utility automatically configures SCSI disk drives even if that specific type of drive is not listed in the `/etc/format.dat` file. This feature enables you to format, slice, and label any disk driver compliant with SCSI-2 specification for disk device mode sense pages.

The following steps are involved in configuring a SCSI drive using autoconfiguration:

- Shutting down the system
- Attaching the SCSI disk drive to the system
- Turning on the disk drive
- Performing a reconfiguration boot
- Using the `format` utility to automatically configure the SCSI disk drive

After the reconfiguration boot, invoke the `format` utility. The `format` utility will attempt to configure the disk and, if successful, alert the user that the disk was configured. See “How to Automatically Configure a SCSI Drive” on page 345 for step-by-step instructions on configuring a SCSI disk drive automatically.

Here are the default slice rules that `format` uses to create the partition table.

TABLE 22-2 SCSI Disk Slice Rules

Disk Size	Root File System	Swap Slice
0 - 180 Mbytes	16 Mbytes	16 Mbytes
180 Mbytes - 280 Mbytes	16 Mbytes	32 Mbytes
280 Mbytes - 380 Mbytes	24 Mbytes	32 Mbytes
380 Mbytes - 600 Mbytes	32 Mbytes	32 Mbytes
600 Mbytes - 1.0 Gbytes	32 Mbytes	64 Mbytes
1.0 Gbytes - 2.0 Gbytes	64 Mbytes	128 Mbytes
More than 2.0 Gbytes	128 Mbytes	128 Mbytes

In all cases, slice 6 (for the `/usr` file system) gets the remainder of the space on the disk.

Here's an example of a `format`-generated partition table for a 1.3-Gbyte SCSI disk drive.

Part	Tag	Flag	Cylinders	Size	Blocks
0	root	wm	0 - 96	64.41MB	(97/0/0)
1	swap	wu	97 - 289	128.16MB	(193/0/0)
2	backup	wu	0 - 1964	1.27GB	(1965/0/0)
6	usr	wm	290 - 1964	1.09GB	(1675/0/0)

See Chapter 25 for more information about using SCSI automatic configuration.

## ▼ How to Automatically Configure a SCSI Drive

1. **Become superuser.**

2. **Create the `/reconfigure` file that will be read when the system is booted.**

```
# touch /reconfigure
```

3. **Shut down the system.**

```
# shutdown -i0 -g30 -y
```

`-i0`                      Brings the system down to init state 0 (zero), the power-down state.

`-g30`                    Notifies logged-in users that they have *n* seconds before the system begins to shut down.

`-y`                        Specifies the command should run without user intervention.

The `ok` or `>` prompt is displayed after the operating environment is shut down.

4. **Turn off power to the system and all external peripheral devices.**

5. **Make sure the disk you are adding has a different target number than the other devices on the system.**

You will often find a small switch located at the back of the disk for this purpose.

6. **Connect the disk to the system and check the physical connections.**

Refer to the disk's hardware installation guide for installation details.

**7. Turn on the power to all external peripherals.**

**8. Turn on the power to the system.**

The system will boot and display the login prompt.

**9. Login as superuser, invoke the `format` utility, and select the disk to be configured automatically.**

```
# format
Searching for disks...done
clt0d0: configured with capacity of 404.65MB
AVAILABLE DISK SELECTIONS:
  0. c0t3d0 <SUN0424 cyl 1151 alt 2 hd 9 sec 80>
    /sbus@1,f8000000/esp@0,800000/sd@3,0
  1. clt0d0 <SUN0424 cyl 1151 alt 2 hd 9 sec 80>
    /sbus@1,f8000000/QLGC,isp@1,10000/sd@0,0
Specify disk (enter its number): 1
```

**10. Reply `yes` to the prompt to label the disk.**

Replying `y` will cause the disk label to be generated and written to the disk by the autoconfiguration feature.

```
Disk not labeled. Label it now? y
```

**11. Verify the disk label with the `verify` command.**

```
format> verify
```

**12. Exit the `format` utility.**

```
format> q
```

## Repairing a Defective Sector

If a disk on your system has a defective sector, you can repair it by using the instructions in the following procedures. You may become aware of defective sectors when you:

- Run surface analysis on a disk.

See “The analyze Menu” on page 386 for more information on the analysis functionality of the `format` utility.

The defective area reported while your system is running may not be accurate. Since the system does disk operations many sectors at a time, it is often hard to pinpoint exactly which sector caused a given error. Use “How to Identify a Defective Sector by Using Surface Analysis” on page 347 to find the exact sector(s).

- Get multiple error messages from the disk driver concerning a particular portion of the disk while your system is running.

Messages related to disk errors look like the following:

```
WARNING: /io-unit@f,e0200000/sbi@0,0/QLGC,isp@1,10000/sd@3,0 (sd33):
Error for command 'read' Error Level: Retryable
Requested Block 126, Error Block: 179
Sense Key: Media Error
Vendor 'SEAGATE':
ASC = 0x11 (unrecovered read error), ASCQ = 0x0, FRU = 0x0
```

The above console message indicates that block 179 may be bad. Relocate the bad block by using the `format` utility's `repair` command or use the `analyze` command with the `repair` option enabled.

### ▼ How to Identify a Defective Sector by Using Surface Analysis

1. **Become superuser.**
2. **Unmount the file system in the slice that contains the defective sector.**  
See `mount(1M)` for more information.

```
# umount /dev/disk/device-name
```

3. **Enter the `format` utility by typing `format`.**

```
# format
```

#### 4. Select the affected disk.

```
Specify disk (enter its number):1
selecting c0t2d0:
[disk formatted]
Warning: Current Disk has mounted partitions.
```

#### 5. Enter the analyze menu by typing **analyze** at the **format>** prompt.

```
format> analyze
```

#### 6. Set up the analysis parameters by typing **setup** at the **analyze>** prompt. Use the parameters shown here:

```
analyze> setup
Analyze entire disk [no]? n
Enter starting block number [0, 0/0/0]: 12330
Enter ending block number [584159, 1216/9/47]: 12360
Loop continuously [no]? y
Repair defective blocks [yes]? n
Stop after first error [no]? n
Use random bit patterns [no]? n
Enter number of blocks per transfer [31, 0/0/31]: 1
Verify media after formatting [yes]? y
Enable extended messages [no]? n
Restore defect list [yes]? y
Create defect label [yes]? y
```

#### 7. Use the **read** command to find the defect.

```
analyze> read
Ready to analyze (won't harm SunOS). This takes a long time,
but is interruptible with Control-C. Continue? y
    pass 0
      25/7/24
    pass 1
Block 12354 (18/4/18), Corrected media error (hard data ecc)
      25/7/24
^C
```

(continued)

(Continuation)

```
Total of 1 defective blocks repaired.
```

## ▼ How to Repair a Defective Sector

1. Become superuser.
2. Enter the `format` utility and select the disk that contains the defective sector.

```
# format
Searching for disks...done
AVAILABLE DISK SELECTIONS:
  0. c0t2d0 <SUN1.05 cyl 2036 alt 2 hd 14 sec 72>
    /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/sd@2,0
  1. c0t3d0 <SUN0535 cyl 1866 alt 2 hd 7 sec 80>
    /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/sd@3,0
Specify disk (enter its number): 1
selecting c0t3d0
[disk formatted]
format>
```

3. Enter the repair command at the `format>` prompt.

```
format> repair
```

4. Enter the defective block number.

```
Enter absolute block number of defect: 12354
Ready to repair defect, continue? y
Repairing block 12354 (18/4/18)...ok.
format>
```

If you are unsure of the format used to identify the defective sector, see “How to Identify a Defective Sector by Using Surface Analysis” on page 347 for more information.

---

## Tips and Tricks

Use the following tips to help you manage disks more efficiently.

### Debugging format Sessions

Invoke `format -M` to enable extended and diagnostic messages for using the `format` utility with SCSI devices only.

In this example, the series of numbers below `Inquiry:` represent the hexadecimal value of the inquiry data displayed to the right of the numbers.

```
# format -M
Searching for disks...done
AVAILABLE DISK SELECTIONS:
    0. c0t3d0 <SUN0535 cyl 1866 alt 2 hd 7 sec 80>
    /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/sd@3,0

Specify disk (enter its number): 0
selecting c0t3d0
[disk formatted]
format> inquiry
Inquiry:
00 00 02 02 27 00 00 12 43 4f 4e 4e 45 52 20 20    ....'...CONNER
43 50 33 30 35 34 30 20 20 53 55 4e 30 35 33 35    CP30540  SUN0535
42 30 42 42 39 33 30 38 46 39 30                  B0BB9308F90
Vendor:    CONNER
Product:   CP30540  SUN0535
Revision:  B0BB
format>
```

### Label Multiple Disks by Using the prtvtoc and fmthard Commands

Use the `prtvtoc` and `fmthard` commands to label multiple disks with the same disk geometry.

Use this `for` loop in a script to copy a disk label from one disk and replicate it on multiple disks.

```
# for i in x y z
> do
> prtvtoc /dev/rdisk/cwtxdysz | fmthard -s - /dev/rdisk/cwt${i}d0s2
> done
```



## Example—Labeling Multiple Disks

In this example, the disk label from `c2t0d0s0` is copied to four other disks.

```
# for i in 1 2 3 5
> do
> prtvtoc /dev/rdisk/c2t0d0s0 | fmthard -s - /dev/rdisk/c2t${i}d0s2
> done
fmthard: New volume table of contents now in place.
fmthard: New volume table of contents now in place.
fmthard: New volume table of contents now in place.
fmthard: New volume table of contents now in place.
#
```



## SPARC: Adding a Disk (Tasks)

---

This chapter provides the procedures for adding a disk to a SPARC system.

This is a list of the step-by-step instructions in this chapter.

- “SPARC: How to Connect a System Disk and Boot” on page 354
- “SPARC: How to Connect a Secondary Disk and Boot” on page 355
- “SPARC: How to Create Disk Slices and Label a Disk” on page 356
- “SPARC: How to Create File Systems” on page 361
- “SPARC: How to Install a Boot Block on a System Disk” on page 362

For overview information about disk management, see Chapter 21.

---

## SPARC: About System and Secondary Disks

A system disk contains the root (/) or /usr file systems, or both. If the disk containing either of these file systems becomes damaged, you have two ways to recover:

- You can reinstall the entire Solaris environment.
- Or, you can replace the system disk and restore your file systems from a backup medium.

A secondary disk doesn't contain the root (/) and /usr file systems. It usually contains space for user files. You can add a secondary disk to a system for more disk space or you can replace a damaged secondary disk. If you replace a secondary disk on a system, you can restore the old disk's data on the new disk.

## SPARC: Adding a System or Secondary Disk Task Map

TABLE 23-1 Adding a System or Secondary Disk Task Map

Task	Description	For Instructions, Go To
1. Connect the Disk and Boot	<i>System Disk</i> Connect the new disk and boot from a local or remote Solaris CD.  <i>Secondary Disk</i> Connect the new disk and perform a reconfiguration boot, so the system will recognize the disk.	"SPARC: How to Connect a System Disk and Boot" on page 354  "SPARC: How to Connect a Secondary Disk and Boot" on page 355
2. Create Slices and Label the Disk	Create disk slices and label the disk if it has not already been done by the disk manufacturer.	"SPARC: How to Create Disk Slices and Label a Disk" on page 356
3. Create File Systems	Create UFS file systems on the disk slices with the <code>newfs</code> command. You must create the root (/) or /usr file system (or both) for a system disk.	"SPARC: How to Create File Systems" on page 361
4. Restore File Systems	Restore the root (/) or /usr file system (or both) on the system disk. If necessary, restore file systems on the secondary disk.	Chapter 35
5. Install Boot Block	<i>System Disk Only.</i> Install the boot block on the root (/) file system, so the system can boot.	"SPARC: How to Install a Boot Block on a System Disk" on page 362

### ▼ SPARC: How to Connect a System Disk and Boot

This procedure assumes that the system is shut down.

1. **Disconnect the damaged system disk from the system.**

2. **Make sure the disk you are adding has a different target number than the other devices on the system.**

You will often find a small switch located at the back of the disk for this purpose.

3. **Connect the replacement system disk to the system and check the physical connections.**

Refer to the disk's hardware installation guide for installation details.

4. **Follow the instructions in the table below depending on whether you are booting from a local or remote Solaris CD.**

If You Are Booting From ...	Then ...
A Solaris CD from a local CD-ROM drive	1. Make sure the CD is in the CD-ROM drive. 2. Boot from the CD to single-user mode: <code>ok boot cdrom -s</code>
A Solaris CD from a CD-ROM drive over the network	Boot from the net to single-user mode: <code>ok boot net -s</code>

After a few minutes, the root prompt (#) is displayed.

## Where to Go From Here

After you boot the system, you can create slices and a disk label on the disk. Go to “SPARC: How to Create Disk Slices and Label a Disk” on page 356.

## ▼ SPARC: How to Connect a Secondary Disk and Boot

1. **Become superuser.**
2. **If the disk type is unsupported by the Solaris software, add the device driver for the disk by following the instructions included with the hardware.**  
If necessary, see “How to Create a `format.dat` Entry” on page 343 for information on creating a `format.dat` entry for the disk.
3. **Create the `/reconfigure` file that will be read when the system is booted.**

```
# touch /reconfigure
```

The `/reconfigure` file will cause the SunOS software to check for the presence of any newly installed peripheral devices when you power on or boot your system later.

#### 4. Shut down the system.

```
# shutdown -i0 -g30 -y
```

<code>-i0</code>	Brings the system down to init state 0 (zero), the power-down state.
<code>-gn</code>	Notifies logged-in users that they have <i>n</i> seconds before the system begins to shut down.
<code>-y</code>	Specifies the command should run without user intervention.

The `ok` or `>` prompt is displayed after the operating environment is shut down.

#### 5. Turn off power to the system and all external peripheral devices.

#### 6. Make sure the disk you are adding has a different target number than the other devices on the system.

You will often find a small switch located at the back of the disk for this purpose.

#### 7. Connect the disk to the system and check the physical connections.

Refer to the disk's hardware installation guide for installation details.

#### 8. Turn on the power to all external peripherals.

#### 9. Turn on the power to the system.

The system will boot and display the login prompt.

### Where to Go From Here

After you boot the system, you can create slices and a disk label on the disk. Go to "SPARC: How to Create Disk Slices and Label a Disk" on page 356.

## ▼ SPARC: How to Create Disk Slices and Label a Disk

#### 1. Become superuser.

#### 2. Start the `format(1M)` utility.

```
# format
```

A list of available disks is displayed.

3. Enter the number of the disk that you want to repartition from the list displayed on your screen.

```
Specify disk (enter its number): disk-number
```

*disk-number*

Is the number of the disk that you want to repartition.

4. Go into the `partition` menu (which lets you set up the slices).

```
format> partition
```

5. Display the current partition (slice) table.

```
partition> print
```

6. Start the modification process.

```
partition> modify
```

7. Set the disk to all free hog.

```
Choose base (enter number) [0]? 1
```

See “Using the Free Hog Slice” on page 325 for more information about the free hog slice.

8. Create a new partition table by answering `y` when prompted to continue.

```
Do you wish to continue creating a new partition table based on  
above table[yes]?y
```

**9. Identify the free hog partition (slice) and the sizes of the slices when prompted.**

When adding a system disk, you must set up slices for:

- root (slice 0) and swap (slice 1) and/or
- /usr (slice 6)

After you identify the slices, the new partition table is displayed.

**10. Make the displayed partition table the current partition table by answering `y` when asked.**

```
Okay to make this the current partition table[yes]? y
```

If you don't want the current partition table and you want to change it, answer `no` and go to Step 6 on page 357.

**11. Name the partition table.**

```
Enter table name (remember quotes): "partition-name"
```

*partition-name*

Is the name for the new partition table.

**12. Label the disk with the new partition table when you have finished allocating slices on the new disk.**

```
Ready to label disk, continue? yes
```

**13. Quit the partition menu.**

```
partition> q
```

**14. Verify the disk label using the `verify` command.**

```
format> verify
```

**15. Quit the `format` menu.**

```
format> q
```



## SPARC: Example—Creating Disk Slices and Labeling a System Disk

The following example uses the `format` utility to divide a 1-Gbyte disk into three slices: one for the root (`/`) file system, one for the swap area, and one for the `/usr` file system.

```
# format
Searching for disks...done
AVAILABLE DISK SELECTIONS:
  0. c0t1d0 <SUN1.05 cyl 2036 alt 2 hd 14 sec 72>
    /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/
sd@1,0
  1. c0t3d0 <SUN1.05 cyl 2036 alt 2 hd 14 sec 72>
    /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/
sd@3,0
Specify disk (enter its number): 0
selecting c0t1d0
[disk formatted]
format> partition
partition> print
partition> modify
Select partitioning base:
  0. Current partition table (original)
  1. All Free Hog
Choose base (enter number) [0]? 1

Part      Tag      Flag      Cylinders      Size      Blocks
  0       root      wm         0              0      (0/0/0)      0
  1       swap      wu         0              0      (0/0/0)      0
  2    backup      wu      0 - 2035    1002.09MB    (2036/0/0) 2052288
  3 unassigned      wm         0              0      (0/0/0)      0
  4 unassigned      wm         0              0      (0/0/0)      0
  5 unassigned      wm         0              0      (0/0/0)      0
  6        usr      wm         0              0      (0/0/0)      0
  7 unassigned      wm         0              0      (0/0/0)      0

Do you wish to continue creating a new partition
table based on above table[yes]? yes
Free Hog partition[6]? 6
Enter size of partition '0' [0b, 0c, 0.00mb]: 200mb
Enter size of partition '1' [0b, 0c, 0.00mb]: 200mb
Enter size of partition '3' [0b, 0c, 0.00mb]:
Enter size of partition '4' [0b, 0c, 0.00mb]:
Enter size of partition '6' [0b, 0c, 0.00mb]:
Enter size of partition '7' [0b, 0c, 0.00mb]:
```

Part	Tag	Flag	Cylinders	Size	Blocks
0	root	wm	0 - 406	200.32MB	(407/0/0) 410256
1	swap	wu	407 - 813	200.32MB	(407/0/0) 410256
2	backup	wu	0 - 2035	1002.09MB	(2036/0/0) 2052288
3	unassigned	wm	0	0	(0/0/0) 0
4	unassigned	wm	0	0	(0/0/0) 0
5	unassigned	wm	0	0	(0/0/0) 0
6	usr	wm	814 - 2035	601.45MB	(1222/0/0) 1231776
7	unassigned	wm	0	0	(0/0/0) 0

(continued)

(Continuation)

```
Okay to make this the current partition table[yes]? yes
Enter table name (remember quotes): "disk0"
Ready to label disk, continue? yes
partition> quit
format> verify
format> quit
```

## SPARC: Example—Creating Disk Slices and Labeling a Secondary Disk

The following example uses the `format` utility to divide a 1-Gbyte disk into one slice for the `/export/home` file system.

```
# format
Searching for disks...done
AVAILABLE DISK SELECTIONS:
  0. c0t1d0 <SUN1.05 cyl 2036 alt 2 hd 14 sec 72>
     /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/
sd@1,0
  1. c0t3d0 <SUN1.05 cyl 2036 alt 2 hd 14 sec 72>
     /iommu@f,e0000000/sbus@f,e0001000/espdma@f,400000/esp@f,800000/
sd@3,0
Specify disk (enter its number): 0
selecting c0t1d0
[disk formatted]
format> partition
partition> print
partition> modify
Select partitioning base:
  0. Current partition table (original)
  1. All Free Hog
Choose base (enter number) [0]? 1

Part      Tag      Flag      Cylinders      Size      Blocks
  0       root      wm         0                0      (0/0/0)      0
  1       swap      wu         0                0      (0/0/0)      0
  2  backup      wu    0 - 2035    1002.09MB    (2036/0/0) 2052288
  3 unassigned      wm         0                0      (0/0/0)      0
  4 unassigned      wm         0                0      (0/0/0)      0
  5 unassigned      wm         0                0      (0/0/0)      0
  6       usr      wm         0                0      (0/0/0)      0
  7 unassigned      wm         0                0      (0/0/0)      0

Do you wish to continue creating a new partition
table based on above table[yes]? y
Free Hog partition[6]? 7
Enter size of partition '0' [0b, 0c, 0.00mb, 0.00gb]:
Enter size of partition '1' [0b, 0c, 0.00mb, 0.00gb]:
Enter size of partition '3' [0b, 0c, 0.00mb, 0.00gb]:
```

(continued)

(Continuation)

```
Enter size of partition '4' [0b, 0c, 0.00mb, 0.00gb]:
Enter size of partition '5' [0b, 0c, 0.00mb, 0.00gb]:
Enter size of partition '6' [0b, 0c, 0.00mb, 0.00gb]:
Part      Tag      Flag      Cylinders      Size      Blocks
0         root      wm         0                0      (0/0/0)      0
1         swap      wu         0                0      (0/0/0)      0
2         backup      wu         0 - 2035      1002.09MB  (2036/0/0) 2052288
3 unassigned      wm         0                0      (0/0/0)      0
4 unassigned      wm         0                0      (0/0/0)      0
5 unassigned      wm         0                0      (0/0/0)      0
6         usr       wm         0                0      (0/0/0)      0
7 unassigned      wm         0 - 2035      1002.09MB  (2036/0/0) 2052288
Okay to make this the current partition table[yes]? yes
Enter table name (remember quotes): "home"
Ready to label disk, continue? y
partition> q
format> verify
format> q
#
```

## Where to Go From Here

After you create disk slices and label the disk, you can create file systems on the disk. Go to “SPARC: How to Create File Systems” on page 361.

## ▼ SPARC: How to Create File Systems

1. Become superuser.
2. Create a file system for each slice with the `newfs(1M)` command.

```
# newfs /dev/rdisk/cwtxdysz
```

`/dev/rdisk/cwtxdysx`

Raw device for the file system to be created.

See Chapter 27 for more information about the `newfs` command.

3. Verify the new file system by mounting it on an unused mount point.

```
# mount /dev/dsk/cwtxdysz/mnt
# ls
lost+found
```

## Where to Go From Here

If You Are Adding A ...	Then ...
System Disk	<p>You need to restore the root (/) and /usr file systems on the disk. Go to Chapter 35.</p> <p>After the root (/) and /usr file systems are restored, install the boot block. Go to “SPARC: How to Install a Boot Block on a System Disk” on page 362.</p>
Secondary Disk	<p>You may need to restore file systems on the new disk. Go to Chapter 35.</p> <p>If you are not restoring file systems on the new disk, you are finished adding a secondary disk. See Chapter 28 for information on making the file systems available to users.</p>

### ▼ SPARC: How to Install a Boot Block on a System Disk

1. **Become superuser.**
2. **Install a boot block on a system disk using the `installboot(1M)` command.**

```
# /usr/sbin/installboot /usr/platform/`uname -i`/lib/fs/ufs/bootblk  
/dev/rdsk/cwtxdys0
```

`/usr/platform/`uname -i`/lib/fs /ufs/  
bootblk`      Boot block code.

`/dev/rdsk/cwtxdys0`      Raw device of the root (/) file  
system.

3. **Verify the boot blocks are installed by rebooting the system to run level 3.**

```
# init 6
```

## SPARC: Example—Installing a Boot Block on a System Disk

The following example installs the boot block on a SPARCstation 10.

```
# installboot /usr/platform/sun4m/lib/fs/ufs/bootblk /dev/rdisk/c0t0d0s0
```



---

## x86: Adding a Disk (Tasks)

---

This chapter provides the procedures for adding a disk on an x86 system. This is a list of the step-by-step instructions in this chapter.

- “x86: How to Connect a System Disk and Boot” on page 367
- “x86: How to Connect a Secondary Disk and Boot” on page 368
- “x86: How to Create a Solaris `fdisk` Partition” on page 369
- “x86: How to Create Disk Slices and Label a Disk” on page 376
- “x86: How to Create File Systems” on page 379
- “x86: How to Install a Boot Block on a System Disk” on page 380

For overview information about disk management, see Chapter 21.

---

## x86: About System and Secondary Disks

A system disk contains the root (`/`) or `/usr` file systems, or both. If the disk containing either of these file systems becomes damaged, you have two ways to recover:

- You can reinstall the entire Solaris environment.
- Or, you can replace the system disk and restore your file systems from a backup medium.

A secondary disk doesn't contain the root (`/`) and `/usr` file systems. It usually contains space for user files. You can add a secondary disk to a system for more disk space or you can replace a damaged secondary disk. If you replace a secondary disk on a system, you can restore the old disk's data on the new disk.

## x86: Adding a System or Secondary Disk Task Map

TABLE 24-1 Adding a System or Secondary Disk Task Map

Task	Description	For Instructions, Go To
1. Connect the Disk and Boot	<p><i>System Disk</i></p> <p>Connect the new disk and boot from a local or remote Solaris CD.</p> <p><i>Secondary Disk</i></p> <p>Connect the new disk and perform a reconfiguration boot, so the system will recognize the disk.</p>	<p>“x86: How to Connect a System Disk and Boot” on page 367</p> <p>“x86: How to Connect a Secondary Disk and Boot” on page 368</p>
2. Create Slices and Label the Disk	Create disk slices and label the disk if it has not already been done by the disk manufacturer.	“x86: How to Create a Solaris <code>fdisk</code> Partition” on page 369 and “x86: How to Create Disk Slices and Label a Disk” on page 376
3. Create File Systems	Create UFS file systems on the disk slices with the <code>newfs</code> command. You must create the root ( <code>/</code> ) or <code>/usr</code> file system (or both) for a system disk.	“x86: How to Create File Systems” on page 379
4. Restore File Systems	Restore the root ( <code>/</code> ) or <code>/usr</code> file system (or both) on the system disk. If necessary, restore file systems on the secondary disk.	Chapter 35
5. Install Boot Block	<i>System Disk Only.</i> Install the boot block on the root ( <code>/</code> ) file system, so the system can boot.	“x86: How to Install a Boot Block on a System Disk” on page 380

## x86: Guidelines for Creating an `fdisk` Partition

Follow these guidelines when setting up the `fdisk` partition.



- The disk can be divided into a maximum of four `fdisk` partitions. One of these partitions must be a Solaris partition.
- The Solaris partition must be made the active partition on the disk. The active partition is the one whose operating system will be booted by default at system start-up.
- Solaris `fdisk` partitions must begin on cylinder boundaries.
- Solaris `fdisk` partitions must begin at cylinder 1, not cylinder 0, on the first disk because additional boot information, including the master boot record, is written in sector 0.
- The Solaris `fdisk` partition can be the entire disk or you may want to make it smaller to allow room for a DOS partition. You can also make a new `fdisk` partition on a disk without disturbing existing partitions (if there is enough room to create a new one).

---

**x86 platform only** - Solaris slices are sometimes called partitions. This user guide uses the term slice, but some Solaris documentation and programs may refer to a *slice* as a *partition*. To avoid confusion, Solaris documentation tries to distinguish between `fdisk` partitions (which are supported only on Solaris™ (Intel Platform Edition) and the divisions within the Solaris `fdisk` partition, which may be called slices or partitions.

---

## ▼ x86: How to Connect a System Disk and Boot

This procedure assumes that the system is down.

1. **Disconnect the damaged system disk from the system.**
2. **Make sure the disk you are adding has a different target number than the other devices on the system.**  
You will often find a small switch located at the back of the disk for this purpose.
3. **Connect the replacement system disk to the system and check the physical connections.**  
Refer to the disk's hardware installation guide for installation details. Also, refer to the *Solaris 7 (Intel Platform Edition) Device Configuration Guide* about hardware configuration requirements specific to the disk.
4. **Follow steps a-e if you are booting from a local or remote Solaris CD.**  
If you are booting from the network, skip step a.
  - a. **Insert the Solaris installation CD into the CD-ROM drive.**
  - b. **Insert the Solaris boot diskette into the primary diskette drive (DOS drive A).**

- c. **Press any key to reboot the system if the system displays the Type any key to reboot prompt. Or, use the reset button to restart the system if the system is shut down.**  
The Multiple Device Boot Subsystem menu is displayed after a few minutes.
- d. **Select the CD-ROM drive or net(work) as the boot device from the Multiple Device Boot menu.**  
The Secondary Boot Subsystem menu is displayed.
- e. **Boot the system in single-user mode.**

```
Select the type of installation: b -s
```

After a few minutes, the root prompt (#) is displayed.

## Where to Go From Here

After you boot the system, you can create slices and a disk label on the disk. Go to “x86: How to Create Disk Slices and Label a Disk” on page 376.

### ▼ x86: How to Connect a Secondary Disk and Boot

1. **Become superuser.**
2. **If the disk is unsupported by the Solaris software, add the device driver for the disk by following the instructions included with the hardware.**
3. **Create the `/reconfigure` file that will be read when the system is booted.**

```
# touch /reconfigure
```

The `/reconfigure` file will cause the SunOS software to check for the presence of any newly installed peripheral devices when you power on or boot your system later.

4. **Shut down the system.**

```
# shutdown -i0 -g30 -y
```

<code>-i0</code>	Brings the system down to init state 0 (zero), the power-down state.
<code>-gn</code>	Notifies logged-in users that they have <i>n</i> seconds before the system begins to shut down.
<code>-y</code>	Specifies the command should run without user intervention.

The `Type any key to reboot` prompt is displayed.

5. **Turn off power to the system and all external peripheral devices.**
6. **Make sure the disk you are adding has a different target number than the other devices on the system.**  
You will often find a small switch located at the back of the disk for this purpose.
7. **Connect the disk to the system and check the physical connections.**  
Refer to the disk's hardware installation guide for installation details. Also, refer to the *Solaris 7 (Intel Platform Edition) Device Configuration Guide* for hardware configuration requirements specific to the disk.
8. **Turn on the power to all external peripherals.**
9. **Turn on the power to the system.**  
The system will boot and display the login prompt.

## Where to Go From Here

After you boot the system, you can create slices and a disk label on the disk. Go to “x86: How to Create Disk Slices and Label a Disk” on page 376.

## ▼ x86: How to Create a Solaris `fdisk` Partition

1. **Make sure you have read “x86: Guidelines for Creating an `fdisk` Partition” on page 366.**
2. **Become superuser.**
3. **Start the `format(1M)` utility.**

```
# format
```

4. Enter the number of the disk on which to create a Solaris `fdisk` partition from the list displayed on your screen.

Specify disk (enter its number): *disk-number*

*disk-number* Is the number of the disk on which to create a Solaris `fdisk` partition.

5. Go into the `fdisk` menu.

format> **fdisk**

The `fdisk` menu displayed is dependent upon whether the disk has existing `fdisk` partitions. Determine the next step using the following table.

If You Want To ...	Go To ...	See ...
Create a Solaris <code>fdisk</code> partition to span the entire disk.	Step 6	“x86: Example—Creating a Solaris <code>fdisk</code> Partition That Spans the Entire Drive” on page 373
Create a Solaris <code>fdisk</code> partition and preserve existing non-Solaris <code>fdisk</code> partition(s).	Step 7	“x86: Example—Creating a Solaris <code>fdisk</code> Partition and Preserving an Existing <code>fdisk</code> Partition” on page 374
Create a Solaris <code>fdisk</code> partition and additional non-Solaris <code>fdisk</code> partition(s).	Step 7	“x86: Example—Creating a Solaris <code>fdisk</code> Partition and an Additional <code>fdisk</code> Partition” on page 375

**6. Create and activate a Solaris fdisk partition spanning the entire disk by specifying y at the prompt. Then go to step 14.**

```
The recommended default partitioning for your disk is:

a 100% ``SOLARIS System'' partition.

To select this, please type ``y''. To partition your disk
differently, type ``n'' and the ``fdisk'' program will
let you select other partitions. y
```

**7. Specify n at the prompt if you do not want the Solaris fdisk partition to span the entire disk.**

```
To select this, please type "y". To partition your disk
differently, type "n" and the "fdisk" program will let you
select other partitions. n
Total disk size is 2694 cylinders
      Cylinder size is 765 (512 byte) blocks
                        Cylinders
Partition  Status   Type      Start   End   Length   %
=====  =====  =====  =====
THERE ARE NO PARTITIONS CURRENTLY DEFINED SELECT ONE OF THE
FOLLOWING:

1.  Create a partition
2.  Change Active (Boot from) partition
3.  Delete a partition
4.  Exit (Update disk configuration and exit)
5.  Cancel (Exit without updating disk configuration)
Enter Selection:
```

**8. Select option 1, Create a partition, to create an fdisk partition.**

```
Total disk size is 2694 cylinders
      Cylinder size is 765 (512 byte) blocks
                        Cylinders
Partition  Status   Type      Start   End   Length   %
=====  =====  =====  =====
THERE ARE NO PARTITIONS CURRENTLY DEFINED SELECT ONE OF THE
FOLLOWING:
```

(continued)

(Continuation)

```
1. Create a partition
2. Change Active (Boot from) partition
3. Delete a partition
4. Exit (Update disk configuration and exit)
5. Cancel (Exit without updating disk configuration)
Enter Selection: 1
```

**9. Create a Solaris fdisk partition by selecting 1(=Solaris).**

```
Indicate the type of partition you want to create
(1=SOLARIS, 2=UNIX, 3=PCIXOS, 4=Other, 8=DOSBIG)
(5=DOS12, 6=DOS16, 7=DOSEXT, 0=Exit) ? 1
```

**10. Identify the percentage of disk to be reserved for the Solaris fdisk partition. Keep in mind the size of any existing fdisk partitions when calculating this percentage.**

```
Indicate the percentage of the disk you want this partition
to use (or enter "c" to specify in cylinders). nn
```

**11. Activate the Solaris fdisk partition by typing y at the prompt.**

```
Do you want this to become the Active partition? If so, it will be
activated each time you reset your computer or when you turn it on
again. Please type "y" or "n". y
```

The Enter Selection: prompt is displayed after the fdisk partition is activated.

**12. Select option 1, Create a partition, to create another fdisk partition.**

See steps 9-11 for instructions on creating an fdisk partition.

**13. Update the disk configuration and exit the fdisk menu from the selection menu.**

```
Selection: 4
```

**14. Relabel the disk using the label command.**

```
WARNING: Solaris fdisk partition changed - Please relabel the disk
format> label
Ready to label disk, continue? yes
format>
```

**15. Quit the format menu.**

```
format> quit
```

## Where to Go From Here

After you create a Solaris fdisk partition on the disk, you can create slices on the disk. Go to “x86: How to Create Disk Slices and Label a Disk” on page 376.

## x86: Example—Creating a Solaris fdisk Partition That Spans the Entire Drive

The following example uses the format’s utility’s fdisk option to create a Solaris fdisk partition that spans the entire drive.

```
# format
Searching for disks...done

AVAILABLE DISK SELECTIONS:
  0. c0t0d0 <DEFAULT cyl 1479 alt 2 hd 7 sec 79>
    /eisa/eha@1000,0/cmdk@0,0
  1. c0t2d0 <SUN1.05 cyl 2692 alt 2 hd 9 sec 85>
```

(continued)

(Continuation)

```

        /eisa/eha@1000,0/cmdk@2,0
Specify disk (enter its number): 1
selecting c0t2d0
[disk formatted]
format> fdisk
The recommended default partitioning for your disk is:

    a 100% "SOLARIS System" partition.

To select this, please type "y". To partition your disk
differently, type "n" and the "fdisk" program will let you
select other partitions. y

WARNING: Solaris fdisk partition changed - Please relabel the disk
format> label
Ready to label disk, continue? yes
format> quit
```

## x86: Example—Creating a Solaris fdisk Partition and Preserving an Existing fdisk Partition

The following example describes how to create a Solaris fdisk partition on a disk that has an existing DOS-BIG fdisk partition.

```
format> fdisk
        Total disk size is 2694 cylinders
        Cylinder size is 765 (512 byte) blocks
        Cylinders
Partition  Status  Type      Start  End  Length  %
=====  =====  =====  =====
         1          DOS-BIG      1    538    538   20
SELECT ONE OF THE FOLLOWING:
1.  Create a partition
2.  Change Active (Boot from) partition
3.  Delete a partition
4.  Exit (Update disk configuration and exit)
5.  Cancel (Exit without updating disk configuration)
Enter Selection: 1
Indicate the type of partition you want to create
(1=SOLARIS, 2=UNIX, 3=PCIXOS, 4=Other, 8=DOSBIG)
(5=DOS12, 6=DOS16, 7=DOSEXT, 0=Exit) ?1
Indicate the percentage of the disk you want this partition
to use (or enter "c" to specify in cylinders). 80
Do you want this to become the Active partition? If so, it will be
activated each time you reset your computer or when you turn it on
again. Please type "y" or "n". y
Partition 2 is now the Active partition Total disk size is 2694
cylinders
```

(continued)



(Continuation)

```

                Cylinder size is 765 (512 byte) blocks
                        Cylinders
Partition  Status  Type      Start  End  Length  %
=====  =====  =====  =====
      1              DOS-BIG      1   538    538    20
      2      Active  SOLARIS   539 2693   2155    80
SELECT ONE OF THE FOLLOWING:
  1. Create a partition
  2. Change Active (Boot from) partition
  3. Delete a partition
  4. Exit (Update disk configuration and exit)
  5. Cancel (Exit without updating disk configuration)
Enter Selection: Selection: 4
WARNING: Solaris fdisk partition changed - Please relabel the disk
format> label
Ready to label disk, continue? yes
format> q
```

## x86: Example—Creating a Solaris fdisk Partition and an Additional fdisk Partition

This following example describes how to create a Solaris fdisk partition and a DOSBIG fdisk partition.

```
format> fdisk
The recommended default partitioning for your disk is:
  a 100% "SOLARIS System" partition.
To select this, please type "y". To partition your disk
differently, type "n" and the "fdisk" program will let you
select other partitions. n
Total disk size is 2694 cylinders
Cylinder size is 765 (512 byte) blocks
                        Cylinders
Partition  Status  Type      Start  End  Length  %
=====  =====  =====  =====
THERE ARE NO PARTITIONS CURRENTLY DEFINED SELECT ONE OF THE FOLLOWING:
  1. Create a partition
  2. Change Active (Boot from) partition
  3. Delete a partition
  4. Exit (Update disk configuration and exit)
  5. Cancel (Exit without updating disk configuration)
Enter Selection: 1
Indicate the type of partition you want to create
(1=SOLARIS, 2=UNIX, 3=PCIXOS, 4=Other, 8=DOSBIG)
(5=DOS12, 6=DOS16, 7=DOSEXT, 0=Exit) ?8
Indicate the percentage of the disk you want this partition
to use (or enter "c" to specify in cylinders). 20
Do you want this to become the Active partition? If so, it will be
```

(continued)

(Continuation)

activated each time you reset your computer or when you turn it on again. Please type "y" or "n". **n**

Total disk size is 2694 cylinders  
Cylinder size is 765 (512 byte) blocks

Partition	Status	Type	Start	End	Length	%
=====	=====	=====	=====	=====	=====	=====
1		DOS-BIG	1	538	538	20

SELECT ONE OF THE FOLLOWING:

1. Create a partition
2. Change Active (Boot from) partition
3. Delete a partition
4. Exit (Update disk configuration and exit)
5. Cancel (Exit without updating disk configuration)Enter

Selection: **1**

Indicate the type of partition you want to create

(1=SOLARIS, 2=UNIX, 3=PCIXOS, 4=Other, 8=DOSBIG)

(5=DOS12, 6=DOS16, 7=DOSEXT, 0=Exit) ?**1**

Indicate the percentage of the disk you want this partition to use (or enter "c" to specify in cylinders). **80**

Do you want this to become the Active partition? If so, it will be activated each time you reset your computer or when you turn it on again. Please type "y" or "n". **y**

Partition 2 is now the Active partition Total disk size is 2694 cylinders

Cylinder size is 765 (512 byte) blocks

Partition	Status	Type	Start	End	Length	%
=====	=====	=====	=====	=====	=====	=====
1		DOS-BIG	1	538	538	20
2	Active	SOLARIS	539	2693	2155	80

SELECT ONE OF THE FOLLOWING:

1. Create a partition
2. Change Active (Boot from) partition
3. Delete a partition
4. Exit (Update disk configuration and exit)
5. Cancel (Exit without updating disk configuration)

Enter Selection: **4**

format> **q**

## ▼ x86: How to Create Disk Slices and Label a Disk

1. **Become superuser.**

2. **Start the format utility.**

```
# format
```

3. Enter the number of the disk that you want to repartition from the list displayed on your screen.

```
Specify disk (enter its number): disk-number
```

*disk-number* Is the number of the disk that you want to repartition.

4. Go into the partition menu (which lets you set up the slices).

```
format> partition
```

5. Display the current partition (slice) table.

```
partition> print
```

6. Start the modification process.

```
partition> modify
```

7. Set the disk to all free hog.

```
Choose base (enter number) [0]? 1
```

See “Using the Free Hog Slice” on page 325 for more information about the free hog slice.

8. Create a new partition table by answering **yes** when prompted to continue.

```
Do you wish to continue creating a new partition  
table based on above table[yes]? yes
```

9. Identify the free hog partition (slice) and the sizes of the slices when prompted.  
When adding a system disk, you must set up slices for:

- root (slice 0) and swap (slice 1) and/or
- /usr (slice 6)

After you identify the slices, the new partition table is displayed.

**10. Make the displayed partition table the current partition table by answering yes when asked.**

```
Okay to make this the current partition table[yes]? yes
```

If you don't want the current partition table and you want to change it, answer no and go to Step 6 on page 377.

**11. Name the partition table.**

```
Enter table name (remember quotes): "partition-name"
```

*partition-name*                      Is the name for the new partition table.

**12. Label the disk with the new partition table when you have finished allocating slices on the new disk.**

```
Ready to label disk, continue? yes
```

**13. Quit the partition menu.**

```
partition> quit
```

**14. Verify the new disk label with verify command.**

```
format> verify
```

**15. Quit the format menu.**

```
format> quit
```

## Where to Go From Here

After you create disk slices and label the disk, you can create file systems on the disk. Go to “x86: How to Create File Systems” on page 379.

### ▼ x86: How to Create File Systems

1. Become superuser.
2. Create a file system for each slice with the `newfs(1M)` command.

```
# newfs /dev/rdisk/cwtxdysz
```

`/dev/rdisk/cwtxdysz`

Raw device for the file system to be created.

See Chapter 28 for more information about the `newfs` command.

3. Verify the new file system by mounting it on an unused mount point.

```
# mount /dev/dsk/cwtxdysz /mnt
# ls /mnt
lost+found
```

## Where to Go From Here

If You Are Adding A ...	Then ...
System Disk	<p>You need to restore the root (/) and /usr file systems on the disk. Go to Chapter 35.</p> <p>After the root (/) and /usr file systems are restored, install the boot block. Go to “x86: How to Install a Boot Block on a System Disk” on page 380.</p>
Secondary Disk	<p>You may need to restore file systems on the new disk. Go to Chapter 35.</p> <p>If you are not restoring file systems on the new disk, you are finished adding a secondary disk. See Chapter 28 for information on making the file systems available to users.</p>

## ▼ x86: How to Install a Boot Block on a System Disk

1. Become superuser.

2. Install the boot block.

```
# /usr/sbin/installboot /usr/platform/`uname -i`/lib/fs/ufs/pboot /usr/platform/`uname -i`  
/lib/fs/ufs/bootblk /dev/rdisk/cwtxdys2
```

/usr/platform/`uname -i`/lib/  
fs/ufs/pboot

Is the partition boot file.

/usr/platform/`uname -i`/lib/  
fs/ufs/bootblk

Is the boot block code.

/dev/rdisk/cwtxdys2

Is the raw device name that represents the  
whole disk.

3. Verify the boot blocks are installed by rebooting the system to run level 3.

```
# init 6
```

## x86: Example—Installing a Boot Block on a System Disk

```
# /usr/sbin/installboot /usr/platform/i86pc/lib/fs/ufs/pboot  
/usr/platform/i86pc/lib/fs/ufs/bootblk /dev/rdisk/c0t6d0s2
```

## The `format` Utility (Reference)

---

This chapter describes the `format` utility's menu and commands.

This is a list of the overview information in this chapter.

- “Requirements or Restrictions for Using the `format` Utility” on page 381
- “Format Menu and Command Descriptions” on page 382
- “Files Used by `format`—`format.dat`” on page 389
- “Associated Man Pages” on page 396
- “Rules for Input to `format` Commands” on page 394

See Chapter 21 for a conceptual overview of when to use the `format` utility.

---

### Requirements or Restrictions for Using the `format` Utility

You must be superuser to use the `format` utility. If you are not superuser, you will see the following error message when you try to use `format`.

```
% format
Searching for disk...done

No permission (or no disk found)!
```

---

## Recommendations for Preserving Information When Using `format`

- Back up all files on the disk drive before doing anything else.
- Save all your defect lists in files by using `format`'s `dump` command. The file name should include the drive type, model number, and serial number.
- Save the paper copies of the manufacturer's defect list shipped with your drive.

---

## Format Menu and Command Descriptions

The `format` main menu looks like the following:

```
FORMAT MENU:
disk          - select a disk
type          - select (define) a disk type
partition     - select (define) a partition table
current       - describe the current disk
format        - format and analyze the disk
repair        - repair a defective sector
label         - write label to the disk
analyze       - surface analysis
defect        - defect list management
backup        - search for backup labels
verify        - read and display labels
save          - save new disk/partition definitions
inquiry       - show vendor, product and revision
volname       - set 8-character volume name
quit
format>
```

Table 25-1 describes the `format` main menu items.



**TABLE 25-1** The `format` Main Menu Item Descriptions

Item	Command or Menu?	Allows You To ...
<code>disk</code>	Command	Choose the disk that will be used in subsequent operations (known as the current disk). All of the system's drives are listed.
<code>type</code>	Command	Identify the manufacturer and model of the current disk. A list of known drive types is displayed. Choose the <code>Auto configure</code> option for all SCSI-2 disk drives.
<code>partition</code>	Menu	Create and modify slices. See "The <code>partition</code> Menu" on page 384 for more information.
<code>current</code>	Command	Display the following information about the current disk: <ul style="list-style-type: none"><li>■ Device name and type</li><li>■ Number of cylinders, alternate cylinders, heads and sectors</li><li>■ Physical device name</li></ul>
<code>format</code>	Command	Format the current disk, using one of these sources of information in this order: <ol style="list-style-type: none"><li>1. Information found in the <code>format.dat</code> file</li><li>2. Information from the automatic configuration process</li><li>3. Information you enter at the prompt if there is no <code>format.dat</code> entry</li></ol>
<code>fdisk</code>	Menu	Run the <code>fdisk</code> program to create a Solaris <code>fdisk</code> partition.
<code>repair</code>	Command	Repair a specific block on the disk.
<code>label</code>	Command	Write a new label to the current disk.
<code>analyze</code>	Menu	Run read, write, compare tests. See "The <code>analyze</code> Menu" on page 386 for more information.
<code>defect</code>	Menu	Retrieve and print defect lists. See "The <code>defect</code> Menu" on page 388 for more information.
<code>backup</code>	Command	Search for backup labels.

**TABLE 25-1** The format Main Menu Item Descriptions *(continued)*

Item	Command or Menu?	Allows You To ...
verify	Command	Print the following information about the disk: <ul style="list-style-type: none"><li>■ Device name and type</li><li>■ Number of cylinders, alternate cylinders, heads and sectors</li><li>■ Partition table</li></ul>
save	Command	Save new disk and partition information.
inquiry	Command	Print the vendor, product name, and revision level of the current drive (SCSI disks only).
volname	Command	Label the disk with a new eight-character volume name.
quit	Command	Exit the format menu.

## The partition Menu

The partition menu looks like this.

```
format> partition
PARTITION MENU:
      0      - change '0' partition
      1      - change '1' partition
      2      - change '2' partition
      3      - change '3' partition
      4      - change '4' partition
      5      - change '5' partition
      6      - change '6' partition
      7      - change '7' partition
select - select a predefined table
modify - modify a predefined partition table
name   - name the current table
print  - display the current table
label  - write partition map and label to the disk
quit
partition>
```

Table 25-2 describes the partition menu items.

**TABLE 25-2** The partition Menu Item Descriptions

The Command ...	Allows You To ...
change 'x' partition	Specify new slice: <ul style="list-style-type: none"> <li>■ Identification tag</li> <li>■ Permission flags</li> <li>■ Starting cylinder</li> <li>■ Size</li> </ul>
select	Choose a predefined slice table.
modify	Change all the slices in the slice table. This command is preferred over the individual change 'x' partition commands.
name	Specify a name for the current slice table.
print	View the current slice table.
label	Write the slice map and label to the current disk.
quit	Exit the partition menu.

## x86: The fdisk Menu

The fdisk menu appears on x86 systems only and looks like this.

```
format> fdisk
          Total disk size is 1855 cylinders
          Cylinder size is 553 (512 byte) blocks
                                Cylinders
Partition  Status  Type      Start  End    Length  %
=====  =====  =====  =====
          1              DOS-BIG      0    370     371    20
          2      Active  SOLARIS   370  1851    1482    80

SELECT ONE OF THE FOLLOWING:

1.  Create a partition
2.  Change Active (Boot from) partition
3.  Delete a partition
4.  Exit (Update disk configuration and exit)
5.  Cancel (Exit without updating disk configuration)
```

(continued)

(Continuation)

```
Enter Selection:
```

Table 25-3 describes the fdisk menu items.

**TABLE 25-3** The fdisk Menu Item Descriptions

The Command ...	Allows You To ...
Create a partition	Create an fdisk partition. You must create a separate partition for each operating environment such as Solaris or DOS. There is a maximum of 4 partitions per disk. You will be prompted for the size of the fdisk partition as a percentage of the disk.
Change Active partition	Specify which partition will be used for booting. This identifies where the first stage boot program will look for the second stage boot program.
Delete a partition	Delete a previously created partition. This command will destroy all the data in the partition.
Exit	Write a new version of the partition table and exit the fdisk menu.
Cancel	Exit the fdisk menu without modifying the partition table.

## The analyze Menu

The analyze menu looks like this.

```
format> analyze

ANALYZE MENU:
  read      - read only test   (doesn't harm SunOS)
  refresh   - read then write  (doesn't harm data)
  test      - pattern testing  (doesn't harm data)
  write     - write then read   (corrupts data)
  compare   - write, read, compare (corrupts data)
  purge     - write, read, write (corrupts data)
  verify    - write entire disk, then verify (corrupts data)
```

(continued)

(Continuation)

```
print      - display data buffer
setup      - set analysis parameters
config     - show analysis parameters
quit
analyze>
```

Table 25-4 describes the analyze menu items.

**TABLE 25-4** The analyze Menu Item Descriptions

The Command ...	Allows You To ...
read	Read each sector on this disk. Repairs defective blocks as a default.
refresh	Read then write data on the disk without harming the data. Repairs defective blocks as a default.
test	Write a set of patterns to the disk without harming the data. Repairs defective blocks as a default.
write	Write a set of patterns to the disk then read the data on the disk back. Destroys existing data on the disk. Repairs defective blocks as a default.
compare	Write a set of patterns to the disk, read the data back, and compare it to the data in the write buffer. Destroys existing data on the disk. Repairs defective blocks as a default.
purge	Remove all data from the disk so that the data can't be retrieved by any means. Data is removed by writing three distinct patterns over the entire disk (or section of the disk), then writing an hex-bit pattern if the verification passes. Repairs defective blocks as a default.
verify	Write unique data to each block on the entire disk in the first pass. Read and verify the data in the next pass. Destroys existing data on the disk. Repairs defective blocks as a default.
print	View the data in the read/write buffer.

TABLE 25-4 The analyze Menu Item Descriptions (continued)

The Command ...	Allows You To ...
setup	<p>Specify the following analysis parameters</p> <p>Analyze entire disk? <b>yes</b> Starting block number: <i>depends on drive</i> Ending block number: <i>depends on drive</i> Loop continuously? <b>no</b> Number of passes: <b>2</b> Repair defective blocks? <b>yes</b> Stop after first error? <b>no</b> Use random bit patterns? <b>no</b> Number of blocks per transfer: <b>126 (0/n/nn)</b> Verify media after formatting? <b>yes</b> Enable extended messages? <b>no</b> Restore defect list? <b>yes</b> Restore disk label? <b>yes</b></p> <p>Defaults are shown in bold.</p>
config	View the current analysis parameters.
quit	Exit the analyze menu.

# The defect Menu

The defect menu looks like this.

```
format> defect

DEFECT MENU:
  primary - extract manufacturer's defect list
  grown   - extract manufacturer's and repaired defects lists
  both    - extract both primary and grown defects lists
  print   - display working list
  dump    - dump working list to file
  quit
defect>
```

Table 25-5 describes the defect menu items.

**TABLE 25-5** The defect Menu Item Descriptions

The Command ...	Allows You To ...
<code>primary</code>	Read the manufacturer's defect list from the disk drive and update the in-memory defect list.
<code>grown</code>	Read the grown defect list (defects that have been detected during analysis) and update the in-memory defect list.
<code>both</code>	Read both the manufacturer's and grown defect list and update the in-memory defect list.
<code>print</code>	View the in-memory defect list.
<code>dump</code>	Save the in-memory defect list to a file.
<code>quit</code>	Exit the defect menu.

## Files Used by `format`—`format.dat`

The `format` data file, `/etc/format.dat`, contains:

- Disk types
- Default slice tables

The `format.dat` file shipped with the Solaris operating environment supports many standard disks. If your disk drive is not listed in the `format.dat` file, you can choose to add an entry for it or allow `format` to prompt you for the information it needs while it is performing operations.

Adding an entry to the `format.dat` file can save time if the disk drive will be used throughout your site. To use the `format.dat` file on other systems, copy the file to each system that will use the specific disk drive you added to the `format.dat` file.

You should modify the data file for your system if you have one of the following:

- A disk that is not supported by the Solaris operating environment
- A disk with a slice table that is different from the Solaris operating environment default configuration

---

**Note** - Do not alter default entries. If you want to alter the default entries, copy the entry, give it a different name, and make the modification to avoid confusion.

---

## Structure

The `format.dat` contains specific disk drive information used by the `format` utility. Three items are defined in the `format.dat` file:

- Search paths
- Disk types
- Slice tables

## Syntax

The following syntax rules apply to the data file:

- The pound sign (#) is the comment character. Any text on a line after a pound sign is not interpreted by `format`.
- Each definition in the `format.dat` file appears on a single logical line. If the definition is more than one line long, all but the last line of the definition must end with a backslash (\).
- A definition consists of a series of assignments that have an identifier on the left side and one or more values on the right side. The assignment operator is the equal sign (=). The assignments within a definition must be separated by a colon (:).
- White space is ignored by `format`. If you want an assigned value to contain white space, enclose the entire value in double quotes ("). This will cause the white space within the quotes to be preserved as part of the assignment value.
- Some assignments can have multiple values on the right hand side. Separate values by a comma.

## Keywords

The data file contains disk definitions that are read in by `format` when it is started. Each definition starts with one of the following keywords: `search_path`, `disk_type`, and `partition`, which are described in Table 25-6.



**TABLE 25-6** `format.dat` Keyword Descriptions

Keyword	Use
<code>search_path</code>	This keyword is no longer used in the <code>format.dat</code> file. Starting with the Solaris 2.0 release, the <code>format</code> utility searches the logical device hierarchy ( <code>/dev</code> ) so there is no need to set this keyword to find a system's disks.
<code>disk_type</code>	Defines the controller and disk model. Each <code>disk_type</code> definition contains information concerning the physical geometry of the disk. The default data file contains definitions for the controllers and disks that the Solaris operating environment supports. You need to add a new <code>disk_type</code> only if you have an unsupported disk. You can add as many <code>disk_type</code> definitions to the data file as you want.
<code>partition</code>	Defines a slice table for a specific disk type. The slice table contains the slice information, plus a name that lets you refer to it in <code>format</code> . The default data file contains default slice definitions for several kinds of disk drives. Add a slice definition if you recreated slices on any of the disks on your system. Add as many slice definitions to the data file as you need.

## Disk Type

`disk_type` defines the controller and disk model. Each `disk_type` definition contains the physical geometry of the disk. The default data file contains definitions for the controllers and disks that the Solaris operating environment supports. You need to add a new `disk_type` only if you have an unsupported disk. You can add as many `disk_type` definitions to the data file as you want.

The keyword itself is assigned the name of the disk type. This name appears in the disk's label, and is used to identify the disk type whenever `format` is run. Enclose the name in double quotes to preserve any white space in the name. Table 25-7 describes the identifiers that must also be assigned values in all `disk_type` definitions.

**TABLE 25-7** Required `disk_type` Identifiers

Identifier	Description
<code>ctlr</code>	Valid controller type for the disk type. Currently, the supported values for this assignment are SCSI and ISP-80 (IPI controller).
<code>ncyl</code>	The number of data cylinders in the disk type. This determines how many logical cylinders of the disk the system will be allowed to access.

**TABLE 25-7** Required `disk_type` Identifiers *(continued)*

Identifier	Description
<code>acyl</code>	The number of alternate cylinders in the disk type. These cylinders are used by <code>format</code> to store information such as the defect list for the drive. You should always leave at least two cylinders for alternates.
<code>pcyl</code>	The number of physical cylinders in the disk type. This number is used to calculate the boundaries of the disk media. This number is usually equal to <code>ncyl</code> plus <code>acyl</code> .
<code>nhead</code>	The number of heads in the disk type. This number is used to calculate the boundaries of the disk media.
<code>nsect</code>	The number of data sectors per track in the disk type. This number is used to calculate the boundaries of the disk media. Note that this is only the data sectors, any spares are not reflected in the assignment.
<code>rpm</code>	The rotations per minute of the disk type. This information is put in the label and later used by the file system to calculate the optimal placement of file data.

Other assignments may be necessary depending on the controller. Table 25-8 describes the assignments required for SCSI controllers.

**TABLE 25-8** `disk_type` Identifiers for SCSI Controllers

Identifier	Description
<code>fmt_time</code>	A number indicating how long it takes to format a given drive. See the controller manual for more information.
<code>cache</code>	A number that controls the operation of the onboard cache while <code>format</code> is operating. See the controller manual for more information.
<code>trks_zone</code>	A number that specified how many tracks you have per defect zone, to be used in alternate sector mapping. See the controller manual for more information.
<code>asect</code>	The number assigned to this parameter specifies how many sectors are available for alternate mapping within a given defect zone. See the controller manual for more information.

Below are some examples of `disk_type` definitions:

```

disk_type = "SUN0535" \
: ctrlr = SCSI : fmt_time = 4 \
: ncyl = 1866 : acyl = 2 : pcyl = 2500 : nhead = 7 : nsect = 80 \
: rpm = 5400
disk_type = "SUN0669" \
: ctrlr = SCSI : fmt_time = 4 \
: trks_zone = 15 : asect = 5 : atrks = 30 \
: ncyl = 1614 : acyl = 2 : pcyl = 1632 : nhead = 15 : nsect = 54 \
: rpm = 3600 : bpt = 31410
disk_type = "SUN1.0G" \
: ctrlr = SCSI : fmt_time = 4 \
: trks_zone = 15 : asect = 5 : atrks = 30 \
: ncyl = 1703 : acyl = 2 : pcyl = 1931 : nhead = 15 : nsect = 80 \
: rpm = 3597 : bpt = 41301

```

## Slice Tables

A partition definition keyword is assigned the name of the slice table. Enclose the name in double quotes to preserve any white space in the name. Table 25–9 describes the identifiers that must be assigned values in all slice tables.

**TABLE 25–9** Required Identifiers for Slice Tables

Identifier	Description
disk	The name of the <code>disk_type</code> that this slice table is defined for. This name must appear exactly as it does in the <code>disk_type</code> definition.
ctrlr	The disk controller type this slice table can be attached to. Currently, the supported values for this assignment are ISP-80 for IPI controllers and SCSI for SCSI controllers. The controller type specified here must also be defined for the <code>disk_type</code> chosen above.

The other assignments in a slice definition describe the actual slice information. The identifiers are the numbers 0 through 7. These assignments are optional. Any slice not explicitly assigned is set to 0 length. The value of each of these assignments is a pair of numbers separated by a comma. The first number is the starting cylinder for the slice, and the second is the number of sectors in the slice. Below are some examples of slice definitions:

```

partition = "SUN0535" \
: disk = "SUN0535" : ctrlr = SCSI \
: 0 = 0, 64400 : 1 = 115, 103600 : 2 = 0, 1044960 : 6 = 300, 876960
partition = "SUN0669" \
: disk = "SUN0669" : ctrlr = SCSI \
: 0 = 0, 32400 : 1 = 40, 64800 : 2 = 0, 1307340 : 6 = 120, 1210140
partition = "SUN1.0G" \

```

(continued)

```
: disk = "SUN1.0G" : ctrlr = SCSI \
: 0 = 0, 32400 : 1 = 27, 64800 : 2 = 0, 2043600 : 6 = 81, 1946400
```

## Location

The `format` utility learns of the location of your data file by the following methods.

1. If a filename is given with the `-x` command line option, that file is always used as the data file.
2. If the `-x` option is not specified, then `format` looks in the current directory for a file named `format.dat`. If the file exists, it is used as the data file.
3. If neither of these methods yields a data file, `format` uses `/etc/format.dat` as the data file. This file is shipped with the Solaris operating environment and should always be present.

## Rules for Input to `format` Commands

When using the `format` utility, you need to provide various kinds of information. This section describes the rules for this information. See “Help” on page 396 for information on using `format`’s help facility when inputting data.

## Numbers

Several places in `format` require an integer as input. You must either specify the data or select one from a list of choices. In either case, the `help` facility causes `format` to print the upper and lower limits of the integer expected. Simply enter the number desired. The number is assumed to be in decimal format unless a base is explicitly specified as part of the number (for example, `0x` for hexadecimal).

The following are examples of integer input:

```
Enter number of passes [2]: 34
Enter number of passes [34] 0xf
```

## Block Numbers

Whenever you are required to specify a disk block number, there are two ways to input the information:

- Block number as an integer
- Block number in the cylinder/head/sector format

You can specify the information as an integer representing the logical block number. You can specify the integer in any base, but the default is decimal. The maximum operator (a dollar sign, \$) can also be used here to let `format` select the appropriate value. Logical block format is used by the SunOS disk drivers in error messages.

The other way to specify a block number is by the cylinder/head/sector designation. In this method, you must specify explicitly the three logical components of the block number: the cylinder, head, and sector values. These values are still logical, but they allow you to define regions of the disk related to the layout of the media.

If any of the cylinder/head/sector numbers are not specified, the appropriate value is assumed to be zero. You can also use the maximum operator in place of any of the numbers and let `format` select the appropriate value. Below are some examples of cylinder, head, and sector entries:

```
Enter defective block number: 34/2/3
Enter defective block number: 23/1/
Enter defective block number: 457//
Enter defective block number: 12345
Enter defective block number: 0xabcd
Enter defective block number: 334/$/2
Enter defective block number: 892//
```

The `format` utility always prints block numbers, in both of the above formats. Also, the help facility shows you the upper and lower bounds of the block number expected, in both formats.

## Command Names

Command names are needed as input whenever `format` is displaying a menu prompt. You can *abbreviate* the command names, as long as what you enter is sufficient to uniquely identify the command desired.

For example, use `p` to enter the partition menu from the `format` menu. Then enter `p` to display the current slice table.

```
format> p
PARTITION MENU:
  0      - change '0' partition
  1      - change '1' partition
  2      - change '2' partition
  3      - change '3' partition
  4      - change '4' partition
  5      - change '5' partition
  6      - change '6' partition
  7      - change '7' partition
```

(continued)

(Continuation)

```
select - select a predefined table
modify - modify a predefined partition table
name    - name the current table
print   - display the current table
label   - write partition map and label to the disk
quit
partition> p
```

## Other Names

There are certain times in `format` when you must name something. In these cases, you are free to specify any string desired for the name. If the name has white space in it, the entire name must be enclosed in double quotes ("). Otherwise, only the first word of the name is used.

## Help

The `format` utility provides a help facility you can use whenever `format` is expecting input. You can request help about what information is expected by entering a question mark (?). The `format` utility displays a brief description of what type of input is needed.

If you enter a ? at a menu prompt, a list of available commands is displayed.

---

## Associated Man Pages

The man pages associated with the `format` utility is `format(1M)`, which describes the basic `format` utility capabilities and provides descriptions of all command line variables, and `format.dat(4)`, which describes disk drive configuration information for the `format` utility.

## PART **VIII** Managing File Systems

---

This part provides instructions for managing file systems in the Solaris operating environment. This part contains these chapters.

Chapter 26	Provides a high-level overview of file system concepts, including descriptions of the types of file systems, commonly used administration commands, and the basics of mounting and unmounting file systems.
Chapter 27	Provides step-by-step procedures to create a UFS file system, create and preserve a temporary file system (TMPFS), and create a loopback file system (LOFS).
Chapter 28	Provides step-by-step procedures to determine what file systems are mounted, how to mount files listed in the <code>/etc/vfstab</code> file, and how to mount UFS, NFS, and PCFS (DOS) file systems.
Chapter 29	Provides overview information and step-by-step instructions for using the Cache File System (CacheFS™).
Chapter 30	Provides step-by-step procedures for configuring additional swap space, monitoring swap resources, creating swap files and making them available, and removing extra swap space.

Chapter 31	Provides information on how the file system state is recorded, what is checked by the <code>fsck</code> program, how to modify automatic boot checking, and how to use the <code>fsck</code> program.
Chapter 32	Provides file system reference information, including default directories for the root ( <code>/</code> ) and <code>/usr</code> file systems, default directories contained within the <code>/kernel</code> directory, and specifics for the <code>mkfs</code> and <code>newfs</code> commands.



## File Systems (Overview)

---

This is a list of the overview information in this chapter.

- “What’s New in File Systems?” on page 399
- “Types of File Systems” on page 401
- “File System Administration Commands” on page 404
- “The Default Solaris File Systems” on page 406
- “Swap Space” on page 407
- “The UFS File System” on page 407
- “Mounting and Unmounting File Systems” on page 410
- “Determining a File System’s Type” on page 415

---

## What’s New in File Systems?

The Solaris 7 release provides two new file system features: UFS logging and a new mount option to ignore access time updates on files.

UFS logging is the process of storing transactions (changes that make up a complete UFS operation) into a log before the transactions are applied to the UFS file system. Once a transaction is stored, the transaction can be applied to the file system later.

UFS logging provides two advantages. It prevents file systems from becoming inconsistent, therefore eliminating the need to run the `fsck` command. And, because `fsck` can be bypassed, UFS logging reduces the time required to reboot a system if it crashes, or after an unclean halt.

UFS logging is not enabled by default. To enable UFS logging, you must specify the `-o logging` option with the `mount` command when mounting the file system. Also,

the `fsdb` command has been updated with new debugging commands to support UFS logging.

To ignore access time updates on files, you can specify the `-o noatime` option when mounting a UFS file system. This option reduces disk activity on file systems where access times are unimportant (for example, a Usenet news spool). See the `mount_ufs(1M)` man page for more details.

---

## Introduction

A file system is a structure of directories used to organize and store files. The term “file system” is used to describe:

- A particular type of file system: disk-based, network-based, or virtual
- The entire file tree from the root directory downward
- The data structure of a disk slice or other media storage device
- A portion of a file tree structure that is attached to a mount point on the main file tree so that it is accessible

Usually, you can tell from context which meaning is intended.

The Solaris operating environment uses the *virtual file system* (VFS) architecture, which provides a standard interface for different file system types. The VFS architecture enables the kernel to handle basic operations, such as reading, writing, and listing files, without requiring the user or program to know about the underlying file system type.

Administering file systems is one of your most important system administration tasks. Read this chapter for file system background and planning information. Refer to other chapters in the *System Administration Guide* for instructions about the following tasks:

- **Creating new file systems** – See Chapter 27 and Chapter 29 for detailed information.
- **Making local and remote files available to users** – See Chapter 28 for detailed information.
- **Connecting and configuring new disk devices** – See Chapter 21 for detailed information.
- **Designing and implementing a backup schedule and restoring files and file systems as needed** – See Chapter 33 for information about backing up and restoring files and file systems.
- **Checking for and correcting file system damage** – See Chapter 31 for detailed information on how to proceed if the automatic (boot time) checking fails.

---

## Types of File Systems

The Solaris operating environment supports three types of file systems:

- Disk-based
- Network-based
- Virtual

To identify the type for a particular file system, see “Determining a File System’s Type” on page 415.

## Disk-based File Systems

Disk-based file systems are stored on physical media such as hard disks, CD-ROMs, and diskettes. Disk-based file systems can be written in different formats. The available formats are:

- **UFS** – UNIX file system (based on the BSD Fast File system that was provided in the 4.3 Tahoe release). UFS is the default disk-based file system for the Solaris operating environment.

Before you can create a UFS file system on a disk, the disk must be formatted and divided into slices. A disk slice is a physical subset of a disk that is composed of a single range of contiguous blocks. A slice can be used either as a raw device that provides, for example, swap space, or to hold a disk-based file system. See Chapter 21 for complete information on formatting disks and dividing disks into slices.

- **HSFS** – High Sierra and ISO 9660 file system. High Sierra is the first CD-ROM file system; ISO 9660 is the official standard version of the High Sierra File System. The HSFS file system is used on CD-ROMs, and is a read-only file system. Solaris HSFS supports Rock Ridge extensions to ISO 9660, which, when present on a CD-ROM, provide all UFS file system semantics and file types except for writability and hard links.
- **PCFS** – PC file system, which allows read/write access to data and programs on DOS-formatted disks written for DOS-based personal computers.

Each type of disk-based file system is customarily associated with a particular media device:

- UFS with hard disk
- HSFS with CD-ROM
- PCFS with diskette

These associations are not, however, restrictive. For example, CD-ROMs and diskettes can have UFS file systems created on them.

## Network-based File Systems

Network-based file systems can be accessed over the network. Typically, network-based file systems reside on one system, typically a server, and are accessed by other systems across the network. The Network File System (NFS) is the only available network-based file system.

NFS is the distributed file system service for Solaris. With NFS, you can administer distributed *resources* (files or directories) by exporting them from a server and mounting them on individual clients. See “The Network File System (NFS)” on page 413 for more information.

## Virtual File Systems

Virtual file systems are memory-based file systems that provide access to special kernel information and facilities. Most virtual file systems do not use file system disk space. However, the Cache File System (CacheFS) uses a file system on the disk to contain the cache, and some virtual file systems, such as the Temporary File System (TMPFS), use the swap space on a disk.

### The Cache File System

The Cache File System (CacheFS™) can be used to improve performance of remote file systems or slow devices such as CD-ROM drives. When a file system is cached, the data read from the remote file system or CD-ROM is stored in a cache on the local system. See Chapter 29 for detailed information on setting up and administering CacheFS File Systems.

### The Temporary File System

The Temporary File System (TMPFS) uses local memory for file system reads and writes, which is typically much faster than a UFS file system. Using TMPFS file systems can improve system performance by saving the cost of reading and writing temporary files to a local disk or across the network. For example, temporary files are created when you compile a program, and the operating system generates a lot of disk or network activity while manipulating these files. Using TMPFS to hold these temporary files may significantly speed up their creation, manipulation, and deletion.

Files in TMPFS file systems are not permanent. They are deleted when the file system is unmounted and when the system is shut down or rebooted.

TMPFS is the default file system type for the `/tmp` directory in the Solaris operating environment. You can copy or move files into or out of the `/tmp` directory, just as you would in a UFS file system.

The TMPFS file system uses swap space as a temporary backing store. If a system with a TMPFS file system does not have adequate swap space, two problems can occur:

- The TMPFS file system can run out of space, just as a regular file system can fill up.
- Because TMPFS allocates swap space to save file data (if necessary), some programs may not execute because there is not enough swap space.

See Chapter 27 for information about creating TMPFS file systems. See Chapter 30 for information about increasing swap space.

## The Loopback File System

The Loopback File System (LOFS) lets you create a new virtual file system, so you can access files by using an alternative path name. For example, you can create a loopback mount of root / on `/tmp/newroot`, which will make the entire file system hierarchy look like it is duplicated under `/tmp/newroot`, including any file systems mounted from NFS servers. All files will be accessible either with a path name starting from (/), or with a path name starting from `/tmp/newroot`.

See Chapter 27 for information on how to create LOFS file systems.

## The Process File System

The Process File System (PROCFS) resides in memory. It contains a list of active processes, by process number, in the `/proc` directory. Information in the `/proc` directory is used by commands like `ps`. Debuggers and other development tools can also access the address space of the processes by using file system calls.



---

**Caution** - Do not delete the files in the `/proc` directory. Deleting processes from the `/proc` directory is not the best way to kill them. Remember, `/proc` files do not use disk space, so there is little reason to delete files from this directory.

---

The `/proc` directory does not require system administration.

## Additional Virtual File Systems

These additional types of virtual file systems are listed for your information. They do not require administration.

- **FIFOFS (first-in first-out)** – Named pipe files that give processes common access to data
- **FDFS (file descriptors)** – Provides explicit names for opening files using file descriptors

- **NAMEFS** – Used mostly by STREAMS for dynamic mounts of file descriptors on top of files
- **SPECFS (special)** – Provides access to character special and block devices
- **SWAPFS** – File system used by the kernel for swapping

## File System Administration Commands

Most file system administration commands have both a generic and a file system-specific component. You should use the generic commands whenever possible, which call the file system-specific component. Table 26-1 lists the generic file system administrative commands, which are located in the `/usr/sbin` directory.

**TABLE 26-1** Generic File System Administrative Commands

Command	Description
<code>clri(1M)</code>	Clears inodes
<code>df(1M)</code>	Reports the number of free disk blocks and files
<code>ff(1M)</code>	Lists file names and statistics for a file system
<code>fsck(1M)</code>	Checks the integrity of a file system and repairs any damage found
<code>fsdb(1M)</code>	Debugs the file system
<code>fstyp(1M)</code>	Determines the file system type
<code>labelit(1M)</code>	Lists or provides labels for file systems when copied to tape (for use by the <code>volcopy</code> command only)

TABLE 26-1 Generic File System Administrative Commands (continued)

Command	Description
<b>mkfs</b> (1M)	Makes a new file system
<b>mount</b> (1M)	Mounts local and remote file systems
<b>mountall</b> (1M)	Mounts all file systems specified in the virtual file system table (/etc/vfstab)
<b>ncheck</b> (1M)	Generates a list of path names with their i-numbers
<b>umount</b> (1M)	Unmounts local and remote file systems
<b>umountall</b> (1M)	Unmounts all file systems specified in a virtual file system table (/etc/vfstab)
<b>volcopy</b> (1M)	Makes an image copy of a file system

## How the File System Commands Determine the File System Type

The generic file system commands determine the file system type by following this sequence:

1. From the `-F` option, if supplied.
2. By matching a special device with an entry in `/etc/vfstab` file (if *special* is supplied). For example, `fsck` first looks for a match against the `fsck` device field; if no match is found, it then checks the *special* device field.
3. By using the default specified in `/etc/default/fs` for local file systems and in `/etc/dfs/fstypes` for remote file systems.

## Manual Pages for Generic and Specific Commands

Both the generic and specific commands have manual pages in the *man Pages(1M): System Administration Commands*. The specific manual page is a continuation of the generic manual page. To look at a specific manual page, append an underscore and the file system type abbreviation to the generic command name. For example, to see the specific manual page for mounting a UFS file system, type **man mount\_ufs(1M)**.

---

## The Default Solaris File Systems

The Solaris file system is hierarchical, starting with the root directory (/) and continuing downwards through a number of directories. The Solaris installation process enables you to install a default set of directories and uses a set of conventions to group similar types of files together. Table 26-2 provides a summary of the default Solaris file systems, and shows the type of each file system.

The root (/) and /usr file systems are both needed to run a system. Some of the most basic commands from the /usr file system (like mount) are included in the root (/) file system so that they are available when the system boots or is in single-user mode and /usr is not mounted. See Chapter 32 for more detailed information on the default directories for the root (/) and /usr file systems.

**TABLE 26-2** The Default Solaris File Systems

File System or Directory	File System Type	Description
root (/)	UFS	The top of the hierarchical file tree. The root directory contains the directories and files critical for system operation, such as the kernel, the device drivers, and the programs used to boot the system. It also contains the mount point directories where local and remote file systems can be attached to the file tree.
/usr	UFS	System files and directories that can be shared with other users. Files that run only on certain types of systems are in the /usr directory (for example, SPARC executables). Files (such as man pages) that can be used on all types of systems are in /usr/share.
/export/home or /home	NFS, UFS	The mount point for users home directories, which store users work files. By default /home is an automounted file system. On standalone systems, /home may be a UFS file system on a local disk slice.



**TABLE 26-2** The Default Solaris File Systems *(continued)*

File System or Directory	File System Type	Description
/var	UFS	System files and directories that are likely to change or grow over the life of the local system. These include system logs, <code>vi</code> and <code>ex</code> backup files, and <code>uucp</code> files.
/opt	NFS, UFS	Mount point for optional, third-party software. On some systems, <code>/opt</code> may be a UFS file system on a local disk slice.
/tmp	TMPFS	Temporary files, cleared each time the system is booted or the <code>/tmp</code> file system is unmounted.
/proc	PROCFS	A list of active processes, by number.

## Swap Space

The Solaris operating environment uses some disk slices for temporary storage rather than for file systems. These slices are called *swap* slices, or *swap space*. Swap space is used as virtual memory storage areas when the system does not have enough physical memory to handle current processes.

Since many applications rely on swap space, it is important to know how to plan for, monitor, and add more swap space when needed. For an overview about swap space and instructions for adding swap space, see Chapter 30.

## The UFS File System

UFS is the default disk-based file system in Solaris operating environment. Most of the time, when you administer a disk-based file system, you will be administering UFS file systems. UFS provides the following features:

- **State flags** – Show the state of the file system: clean, stable, active, logging, or unknown. These flags eliminate unnecessary file system checks. If the file system is “clean,” “stable,” or “logging,” file system checks are not run.

- **Extended fundamental types (EFT)** – 32-bit user ID (UID), group ID (GID), and device numbers.
- **Large file systems** – A UFS file system can be as large as 1 Tbyte (terabyte). The Solaris operating environment does not provide striping, which is required to make a logical slice large enough for a 1-Tbyte file system. However, the Solstice™ DiskSuite™ software, available from Sun, provides this capability.
- **Large files** – By default, a UFS file system can have regular files larger than 2 Gbytes (gigabytes). You must explicitly use the `nolargefiles` mount option to enforce a 2 Gbyte maximum file size limit.

See Chapter 32 for detailed information about the UFS file system.

## Parts of a UFS File System

When you create a UFS file system, the disk slice is divided into *cylinder groups*, which are made up of one or more consecutive disk cylinders. The cylinder groups are then further divided into addressable blocks to control and organize the structure of the files within the cylinder group. Each type of block has a specific function in the file system.

A UFS file system has these four types of blocks:

- **Boot block** – Stores information used when booting the system
- **Superblock** – Stores much of the information about the file system
- **Inode** – Stores all information about a file except its name
- **Storage or data block** – Stores data for each file

See “The Structure of UFS File System Cylinder Groups” on page 519 for more detailed information about each type of block.

If you want to customize a file system using arguments with the `newfs` command or the `mkfs` command, see Chapter 32 for information about altering these parameters.

## UFS Logging

UFS logging is the process of storing transactions (changes that make up a complete UFS operation) in a log before the transactions are applied to the UFS file system. Once a transaction is stored, the transaction can be applied to the file system later.

At reboot, the system discards incomplete transactions, but applies the transactions for completed operations. The file system remains consistent because only completed transactions are ever applied. This is true even when a system crashes, which normally interrupts system calls and introduces inconsistencies into a UFS file system.

UFS logging provides two advantages. It prevents file systems from becoming inconsistent, therefore eliminating the need to run `fsck`. And, because `fsck` can be bypassed, UFS logging reduces the time required to reboot a system if it crashes, or after an unclean halt (see “What `fsck` Checks and Tries to Repair” on page 494 for details on unclean halts). UFS logging can especially reduce the boot time on systems that have large file systems, which usually take a long time to read and verify with `fsck`.

The log created by UFS logging is continually flushed as it fills up. The log is totally flushed when the file system is unmounted or as a result of the `lockfs -f` command.

UFS logging is not enabled by default. To enable UFS logging, you must specify the `-o logging` option with the `mount` command when mounting the file system. The log is allocated from free blocks on the file system, and it is sized approximately 1 Mbyte per 1 Gbyte of file system, up to a maximum of 64 Mbytes. Logging can be enabled on any UFS, including the root (`/`) file system. Also, the `fsdb` command has been updated with new debugging commands to support UFS logging.

## Planning UFS File Systems

When laying out file systems, you need to consider possible conflicting demands. Here are some suggestions:

- Distribute the work load as evenly as possible among different I/O systems and disk drives. Distribute `/export/home` and swap space evenly across disks.
- Keep pieces of projects or members of groups within the same file system.
- Use as few file systems per disk as possible. On the system (or boot) disk, you should have three file systems: `/`, `/usr`, and swap space. On other disks, create one or, at most, two file systems. Fewer, roomier file systems cause less file fragmentation than many small, over-crowded file systems. Higher-capacity tape drives and the ability of `ufsdump` to handle multiple volumes make it easier to back up larger file systems.
- If you have some users who consistently create very small files, consider creating a separate file system with more inodes. However, most sites do not need to be concerned about keeping similar types of user files in the same file system.

See Chapter 27 for information on default file system parameters as well as procedures for creating new UFS file systems.

## Mounting and Unmounting File Systems

Before you can access the files on a file system, you need to mount the file system. Mounting a file system attaches that file system to a directory (*mount point*) and makes it available to the system. The root (/) file system is always mounted. Any other file system can be connected or disconnected from the root (/) file system.

When you mount a file system, any files or directories in the mount point directory are unavailable as long as the file system is mounted. These files are not permanently affected by the mounting process, and they become available again when the file system is unmounted. However, mount directories are typically empty, because you usually do not want to obscure existing files.

For example, Figure 26-1 shows a local file system, starting with a root (/) file system and subdirectories `sbin`, `etc`, and `opt`.




Figure 26-1 Sample root (/) File System

Now, say you wanted to access a local file system from the `/opt` file system that contains a set of unbundled products.

First, you must create a directory to use as a mount point for the file system you want to mount, for example, `/opt/unbundled`. Once the mount point is created, you can mount the file system (by using the `mount` command), which makes all of the files and directories in `/opt/unbundled` available, as shown in Figure 26-2. See Chapter 28 for detailed instructions on how to perform these tasks.




Figure 26-2 Mounting a File System

Unmounting a file system removes it from the file system mount point. Some file system administration tasks cannot be performed on mounted file systems. You should unmount a file system when:

- It is no longer needed or has been replaced by a file system that contains more current software.
- You check and repair it using the `fsck` command. See Chapter 31 for more information about the `fsck` command.

It is a good idea to unmount a file system before doing a complete backup of it. See Chapter 33 for more information about doing backups.

---

**Note** - File systems are automatically unmounted as part of the system shutdown process.

---

## The Mounted File System Table

Whenever you mount or unmount a file system, the `/etc/mnttab` (mount table) file is modified with the list of currently mounted file systems. You can display the contents of the mount table using the `cat` or `more` commands, but you cannot edit it. Here is an example of a `/etc/mnttab` file:

```
$ more /etc/mnttab
/dev/dsk/c0t3d0s0      /          ufs      rw,suid,dev=800018,largefiles 863804345
```

(continued)

(Continuation)

```
/dev/dsk/c0t3d0s6 /usr ufs rw,suid,dev=80001e,largefiles 863804345
/proc /proc proc rw,suid,dev=2900000 863804345
fd /dev/fd fd rw,suid,dev=29c0000 863804345
/dev/dsk/c0t3d0s3 /export ufs suid,rw,largefiles,dev=80001b 863804347
/dev/dsk/c0t3d0s7 /export/home ufs suid,rw,largefiles,dev=80001f 863804348
/dev/dsk/c0t3d0s4 /export/swap ufs suid,rw,largefiles,dev=80001c 863804348
/dev/dsk/c0t3d0s5 /opt ufs suid,rw,largefiles,dev=80001d 863804347
swap /tmp tmpfs dev=2a80000 863804347
$
```

## The Virtual File System Table

It would be a very time-consuming task to manually mount file systems every time you wanted to access them. To fix this, the virtual file system table (the `/etc/vfstab` file) was created to maintain a list of file systems and how to mount them. The `/etc/vfstab` file provides two important features: you can specify file systems to automatically mount when the system boots, and you can mount file systems by using only the mount point name, because the `/etc/vfstab` file contains the mapping between the mount point and the actual device slice name.

A default `/etc/vfstab` file is created when you install a system depending on the selections you make when installing system software; however, you can edit the `/etc/vfstab` file on a system whenever you want. To add an entry, the main information you need to specify is the device where the file system resides, the name of the mount point, the type of the file system, whether you want it to boot automatically when the system boots (by using the `mountall` command), and any mount options.

The following is an example of an `/etc/vfstab` file. Comment lines begin with `#`. This example shows an `/etc/vfstab` file for a system with two disks (`c0t0d0` and `c0t3d0`).

**CODE EXAMPLE 26-1** Sample `/etc/vfstab` File

```
$ more /etc/vfstab
#device      device      mount      FS      fsck      mount      mount
#to mount    to fsck     point      type     pass     at boot   options
/dev/dsk/c0t0d0s0 /dev/rdisk/c0t0d0s0 /      ufs      1        no        -
/proc        -           /proc      proc     -        no        -
/dev/dsk/c0t0d0s1 -           -          swap     -        no        -
swap        -           /tmp       tmpfs    -        yes       -
/dev/dsk/c0t0d0s6 /dev/rdisk/c0t0d0s6 /usr      ufs      2        no        -
/dev/dsk/c0t3d0s7 /dev/rdisk/c0t3d0s7 /test     ufs      2        yes       -
$
```

In Code Example 26-1, the last entry specifies that a UFS file system on the `/dev/dsk/c0t2d0s7` slice will be automatically mounted on the `/test` mount point when the system boots. Note that, for root (`/`) and `/usr`, the `mount` at boot field value is specified as `no`, because these file systems are mounted by the kernel as part of the boot sequence before the `mountall` command is run.

See Chapter 28 for descriptions of each of the `/etc/vfstab` fields and information on how to edit and use the file.

## The Network File System (NFS)

NFS is a distributed file system service that can be used to share *resources* (files or directories) from one system, typically a server, with other systems across the network. For example, you might want to share third-party applications or source files with users on other systems.

NFS makes the actual physical location of the resource irrelevant to the user. Instead of placing copies of commonly used files on every system, NFS allows you to place one copy on one system's disk and let all other systems access it across the network. Under NFS, remote files are virtually indistinguishable from local ones.

A system becomes an NFS server if it has resources to share or *export* over the network. A server keeps a list of currently exported resources and their access restrictions (such as read/write or read-only).

When you share a resource, you make it available for mounting by remote systems.

You can share a resource in these ways:

- By using the `share` or `shareall` command
- By adding an entry to the `/etc/dfs/dfstab` (distributed file system table) file

See Chapter 28 for information on how to share resources. See the *NFS Administration Guide* for a complete description of NFS.

## AutoFS

You can mount NFS file systems by using a client-side service called automounting, or AutoFS, which enables a system to automatically mount and unmount NFS file systems whenever you access them. The file system remains mounted as long as you remain in the file system and are using a file. If the file system is not accessed for a certain period of time, it is automatically unmounted.

AutoFS provides the following features:

- NFS file systems don't need to be mounted when the system boots, which saves booting time.

- Users don't need to know the root password to mount and unmount NFS file systems.
- Network traffic may be reduced, since NFS file systems are only mounted when they are in use.

The AutoFS service is initialized by `automount`, which is run automatically when a system is booted. The automount daemon, `automountd`, runs continuously and is responsible for the mounting and unmounting of the NFS file systems on an as-needed basis. By default, the Solaris operating environment automounts `/home`.

AutoFS works with file systems specified in the name service. This information can be maintained in NIS, NIS+, or local `/etc` files. With AutoFS, you can specify several multiple servers to provide the same file system. This way, if one of the servers is down, AutoFS can try to mount from another machine. You can specify which servers are preferred for each resource in the maps by assigning each server a weighting factor.

See the *NFS Administration Guide* for complete information on how to set up and administer AutoFS.

## The Cache File System (CacheFS)

If you want to improve the performance and scalability of your NFS-mounted file system, you should use the Cache File System (CacheFS). CacheFS is a general purpose file system caching mechanism that improves NFS server performance and scalability by reducing server and network load.

Designed as a layered file system, CacheFS provides the ability to cache one file system on another. In an NFS environment, CacheFS increases the client per server ratio, reduces server and network loads, and improves performance for clients on slow links, such as Point-to-Point Protocol (PPP). You can also combine CacheFS with the AutoFS service to help boost performance and scalability.

See Chapter 29 for detailed information about CacheFS.

## Deciding How to Mount File Systems

Table 26-3 provides guidelines on mounting file systems based on how you use them.



**TABLE 26-3** Determining How to Mount File Systems

If You Need to Mount ...	Then You Should Use ...
Local or remote file systems infrequently	The <code>mount</code> command entered manually from the command line.
Local file systems frequently	The <code>/etc/vfstab</code> file, which will mount the file system automatically when the system is booted in multi-user state.
Remote file systems frequently, such as home directories	<ul style="list-style-type: none"> <li>■ The <code>/etc/vfstab</code> file, which will automatically mount the file system when the system is booted in multi-user state.</li> <li>■ AutoFS, which will automatically mount or unmount the file system when you change into (mount) or out of (unmount) the directory.</li> </ul> <p>To enhance performance, you can also cache the remote file systems by using CacheFS.</p>

You can mount a CD-ROM containing a file system by simply inserting it into the drive (Volume Management will automatically mount it). You can mount a diskette containing a file system by inserting it into the drive and running the `volcheck` command. See for more information.

## Determining a File System's Type

You can determine a file system's type by using the following:

- The `FS type` field in the virtual file system table (`/etc/vfstab` file)
- The `/etc/default/fs` file for local file systems
- The `/etc/dfs/fstypes` file for NFS file systems

### ▼ How to Determine a File System's Type

This procedure works whether the file system is mounted or not.

Determine a file system's type by using the `grep` command.

```
$ grep mount-point fs-table
```

*mount-point*

Specifies the mount point name of the file system for which you want to know the type.

*fs-table*

Specifies the absolute path to the file system table in which to search for the file system's type. If the file system is mounted, *fs-table* should be */etc/mnttab*. If it isn't mounted, *fs-table* should be */etc/vfstab*.

Information for the mount point is displayed.

---

**Note** - If you have the raw device name of a disk slice, you can use the **fstyp(1M)** command to determine a file system's type (if the disk slice contains a file system).

---

## Example—Determining a File System's Type

The following example uses the */etc/vfstab* to determine the type of the */export* file system.

```
$ grep /export /etc/vfstab
/dev/dsk/c0t3d0s6    /dev/rdisk/c0t3d0s6    /export ufs      2          yes      -
$
```

The following example uses the */etc/mnttab* file to determine the file system type of the currently mounted diskette (mounted by volume management).

```
$ grep /floppy /etc/mnttab
/vol/dev/diskette0/unnamed_floppy    /floppy/
unnamed_floppy    pcfs      rw,nohidden,
nofoldcase,dev=16c0009      89103376
$
```

## Creating File Systems (Tasks)

---

This chapter describes how to create UFS, TMPFS, and LOFS file systems. For UFS file systems, this chapter shows you how to create a file system on a hard disk using the `newfs` command. Because TMPFS and LOFS are virtual file systems, you actually “create” them by mounting them.

This is a list of the step-by-step instructions in this chapter.

- “How to Create a UFS File System” on page 418
- “How to Create a TMPFS File System” on page 420
- “How to Create a LOFS File System” on page 422

---

**Note** - For instructions on how to create UFS and DOS file systems on removable media, see Chapter 11.

---

---

## Creating a UFS File System

Before you can create a UFS file system on a disk, the disk must be formatted and divided into slices. A disk slice is a physical subset of a disk that is composed of a single range of contiguous blocks. A slice can be used either as a raw device that provides, for example, swap space, or to hold a disk-based file system. See Chapter 21 for complete information on formatting disks and dividing disks into slices.

---

**Note** - Solaris device names use the term slice (and the letter `s` in the device name) to refer to the slice number. Slices used to be called “partitions” in the SunOS 4.0 or compatible releases.

---

You need to create UFS file systems only occasionally, because the Solaris operating environment automatically creates them as part of the installation process. You need to create (or re-create) a UFS file system when you:

- Add or replace disks
- Change the existing partitioning structure
- Do a full restoration on a file system

The `newfs` command is the standard way to create UFS file systems. The `newfs(1M)` command is a convenient front-end to the `mkfs(1M)` command, which actually creates the new file system. On Solaris systems, `newfs` parameter defaults, such as tracks per cylinder and sectors per track, are read from the disk label that will contain the new file system, and the options you choose are passed to the `mkfs` command to build the file system.

## File System Parameters

To make a new file system on a disk slice, you almost always use the `newfs` command. Table 27-1 shows the default parameters used by the `newfs` command.

TABLE 27-1 Default Parameters Used by the `newfs` Command

Parameter	Default Value
Block size	8 Kbytes
Fragment size	1 Kbyte
Minimum free space	((64 Mbytes/partition size) * 100), rounded down to the nearest integer and limited between 1% and 10%, inclusively
Rotational delay	Device-dependent
Optimization type	Space
Number of inodes	1 for each 2 Kbytes of disk space

## ▼ How to Create a UFS File System

### 1. Make sure you have met the following prerequisites:

- The disk must be formatted and divided into slices before you can create UFS file systems on it. See Chapter 21 for complete information on formatting disks and dividing disks into slices.

- You need to know the device name of the slice that will contain the file system. See Chapter 22 for information on finding disks and disk slice numbers.
- If you are re-creating an existing UFS file system, unmount it.
- You must be superuser.

## 2. Create the UFS file system.

```
# newfs [-N] [-b size] [-i bytes] /dev/rdsk/device-name
```

<code>-N</code>	Displays what parameters <code>newfs</code> would pass to <code>mkfs</code> without actually creating the file system. This is a good way to test the <code>newfs</code> command.
<code>-b size</code>	Specifies the file system block size. Default is 8192 blocks.
<code>-i bytes</code>	Specifies the number of bytes per inode. Default is 2048 bytes.
<code>device-name</code>	Specifies the disk device name on which to create the new file system.




---

**Caution** - Be sure you have specified the correct device name for the slice before performing the next step. If you specify the wrong slice, you will erase its contents when the new file system is created.

---

The system asks for confirmation.

## 3. To verify the creation of the UFS file system, check the new file system with the `fsck(1M)` command.

```
# fsck /dev/rdsk/device-name
```

<code>device-name</code>	Specifies the name of the disk device containing the new file system.
--------------------------	---

The `fsck` command checks the consistency of the new file system, reports problems it finds, and prompts you before repairing the problems. See Chapter 31 for more information on `fsck`.

## Example—Creating a UFS File System

The following example creates a UFS file system on `/dev/rdisk/c0t3d0s7`.

```
# newfs /dev/rdisk/c0t3d0s7
newfs: construct a new file system /dev/rdisk/c0t3d0s7 (y/n)? y
/dev/rdisk/c0t3d0s7: 163944 sectors in 506 cylinders of 9 tracks,
36 sectors 83.9MB in 32 cyl groups (16 c/g, 2.65MB/g, 1216 i/g)
super-block backups (for fsck -b #) at:
32, 5264, 10496, 15728, 20960, 26192, 31424, 36656, 41888,
47120, 52352, 57584, 62816, 68048, 73280, 78512, 82976, 88208,
93440, 98672, 103904, 109136, 114368, 119600, 124832, 130064,
135296, 140528, 145760, 150992, 156224, 161456,
```

## Where to Go From Here

To mount the file system and make it available, go to Chapter 28.

---

# Creating a Temporary File System (TMPFS)

The Temporary File System (TMPFS) uses local memory for file system reads and writes, which is typically much faster than a UFS file system. Using TMPFS file systems can improve system performance by saving the cost of reading and writing temporary files to a local disk or across the network. Files in TMPFS file systems do not survive across reboots or unmounts.

If you create multiple TMPFS file systems, be aware that they all use the same system resources. Files created under one TMPFS file system use up the space available for any other TMPFS, unless you limit TMPFS sizes using the `-o size` option of the `mount` command.

See the `tmpfs(7FS)` man page for more information.

## ▼ How to Create a TMPFS File System

1. **Become superuser.**
2. **If necessary, create the directory where you want to mount the TMPFS file system and set permissions and ownership as necessary.**
3. **Create a TMPFS file system.**

To set up the system to automatically create a TMPFS file system when it boots, see “Example—Creating a TMPFS File System at Boot Time” on page 421.

```
# mount -F tmpfs -o size=number swap mount-point
```

*size=number* Specifies the size of the TMPFS file system in Mbytes.

*mount-point* The directory on which the TMPFS file system is mounted.

4. Look at the output from the `mount` command to verify that the TMPFS file system has been created.

```
# mount -v
```

## Example—Creating a TMPFS File System

The following example creates a new directory, `/export/reports`, and mounts a TMPFS file system at that point, limiting it to 50 Mbytes.

```
# mkdir /export/reports
# chmod 777 /export/reports
# mount -F tmpfs -o size=50 swap /export/reports
```

## Example—Creating a TMPFS File System at Boot Time

You can set up the system to automatically create a TMPFS file system when it boots by adding an entry to the `/etc/vfstab` file. The following example shows an entry in the `/etc/vfstab` file that will create a TMPFS file system on `/export/test` when the system boots. Since the `size=number` option is not specified, the size of the TMPFS file system on `/export/test` is limited only by the available system resources.

```
swap - /export/test tmpfs - yes -
```

For more information the `/etc/vfstab` file, see “`/etc/vfstab` Field Descriptions” on page 430.

# Creating a Loopback File System (LOFS)

A LOFS file system is a virtual file system that provides an alternate path to an existing file system. When other file systems are mounted onto a LOFS file system, the original file system does not change.

See the `lofs(7FS)` man page for more information.



---

**Caution** - Be careful when creating LOFS file systems. Because these are virtual file systems, the potential for confusing both users and applications is enormous.

---

## ▼ How to Create a LOFS File System

1. **Become superuser.**
2. **Create the directory where you want to mount the LOFS file system and give it the appropriate permissions and ownership.**
3. **Create a LOFS file system.**

To set up the system to automatically create a TMPFS file system when it boots, see “Example—Creating a LOFS File System at Boot Time” on page 423.

```
# mount -F lofs loopback-directory mount-point
```

<i>loopback-directory</i>	Specifies the file system to be mounted on the loopback mount point.
---------------------------	--

<i>mount-point</i>	Specifies the directory on which to mount the LOFS file system.
--------------------	---

4. **Look at the output from the `mount` command to verify that the LOFS file system has been created.**

```
# mount -v
```



## Example—Creating a LOFS File System

The following example shows how to use a new LOFS file system with the **chroot**(1M) command to provide a complete virtual file system view of a process or family of processes.

```
# mkdir /tmp/newroot
# mount -F lofs / /tmp/newroot
# chroot /tmp/newroot command
```

## Example—Creating a LOFS File System at Boot Time

You can set up the system to automatically create a LOFS file system when it boots by adding an entry to the end of the `/etc/vfstab` file. The following example shows an entry in the `/etc/vfstab` file that will create a LOFS file system for the root (`/`) file system on `/tmp/newroot`.

```
/ - /tmp/newroot lofs - yes -
```



**Caution** - Make sure the loopback entry is the last entry in the `/etc/vfstab` file. Otherwise, if the `/etc/vfstab` entry for the loopback file system precedes the file systems to be included in it, the loopback file system cannot be created.

For more information the `/etc/vfstab` file, see “`/etc/vfstab` Field Descriptions” on page 430.



## Mounting and Unmounting File Systems (Tasks)

---

This chapter describes how to mount and unmount file systems. This is a list of the step-by-step instructions in this chapter.

- “How to Determine Which File Systems Are Mounted” on page 429
- “How to Add an Entry to the `/etc/vfstab` File” on page 431
- “How to Mount Multiple File Systems Listed in the `/etc/vfstab` File” on page 433
- “How to Mount a File System Listed in the `/etc/vfstab` File” on page 434
- “How to Mount a UFS File System” on page 435
- “How to Mount an NFS File System” on page 437
- “x86: How to Mount a System V (S5FS) File System” on page 438
- “How to Mount a PCFS (DOS) File System From a Hard Disk” on page 438
- “How to Stop All Processes for a File System” on page 440
- “How to Unmount a File System” on page 441
- “How to Unmount File Systems Listed in the `/etc/vfstab` File” on page 442

---

## Mounting File Systems

After you create a file system, you need to make it available to the system so you can use it. You make a file system available by mounting it, which attaches the file system to the system directory tree at the specified mount point. The root (`/`) file

system is always mounted. Any other file system can be connected or disconnected from the root (/) file system.

Table 28–1 provides guidelines on mounting file systems based on how you use them.

**TABLE 28–1** Determining How to Mount File Systems

If You Need to Mount ...	Then You Should Use ...
Local or remote file systems infrequently	The <code>mount</code> command entered manually from the command line.
Local file systems frequently	The <code>/etc/vfstab</code> file, which will mount the file system automatically when the system is booted in multi-user state.
Remote file systems frequently, such as home directories	<ul style="list-style-type: none"><li>■ The <code>/etc/vfstab</code> file, which will automatically mount the file system when the system is booted in multi-user state.</li><li>■ AutoFS, which will automatically mount or unmount the file system when you change into (mount) or out of (unmount) the directory.</li></ul> To enhance performance, you can also cache the remote file systems by using CacheFS.

You can mount a CD-ROM containing a file system by simply inserting it into the drive (Volume Management will automatically mount it). You can mount a diskette containing a file system by inserting it into the drive and running the `volcheck(1)` command. See Chapter 11 for more information.

## Commands Used to Mount and Unmount File Systems

Table 28–2 lists the commands in the `/usr/sbin` directory that you use to mount and unmount file systems.

**TABLE 28-2** Commands for Mounting and Unmounting File Systems

Command	Description
<code>mount(1M)</code>	Mounts file systems and remote resources.
<code>mountall(1M)</code>	Mounts all file systems specified in the <code>/etc/vfstab</code> file. The <code>mountall</code> command is run automatically when entering multiuser run states.
<code>umount(1M)</code>	Unmounts file systems and remote resources.
<code>umountall(1M)</code>	Unmounts all file systems specified in the <code>/etc/vfstab</code> file.

The `mount` commands will not mount a read/write file system that has inconsistencies. If you receive an error message from the `mount` or `mountall` command, you may need to check the file system. See Chapter 31 for information on how to check the file system.

The `umount` commands will not unmount a file system that is busy. A file system is considered busy if a user is in a directory in the file system, or if a program has a file open in that file system.

## Commonly Used Mount Options

Table 28-3 describes the commonly used mount options that you can specify with the `-o` option of the `mount` command. If you specify multiple options, separate them with commas (no spaces). For example, `-o ro,nosuid`.

For a complete list of mount options for each file system type, refer to the specific mount command man pages (for example, `mount_ufs(1M)`).

**TABLE 28-3** Commonly Used `-o` Mount Options

Option	File System	Description
<code>bg</code>   <code>fg</code>	NFS	If the first attempt fails, retries in the background ( <code>bg</code> ) or in the foreground ( <code>fg</code> ). The default is <code>fg</code> .
<code>f</code>	UFS	Fakes an entry in <code>/etc/mnttab</code> , but doesn't really mount any file systems.
<code>hard</code>   <code>soft</code>	NFS	Specifies the procedure if the server does not respond. <code>soft</code> indicates that an error is returned. <code>hard</code> indicates that the retry request is continued until the server responds. The default is <code>hard</code> .
<code>intr</code>   <code>nointr</code>	NFS	Specifies whether keyboard interrupts are allowed to kill a process hung while waiting for a response on hard-mounted file systems. The default is <code>intr</code> (interrupts allowed).
<code>largefiles</code>   <code>nolargefiles</code>	UFS	Enables you to create file systems containing files larger than 2 Gbytes. The <code>largefiles</code> option means that a filesystem mounted with this option <i>may</i> contain files larger than 2 Gbytes, but it is not a requirement. The default is <code>largefiles</code> .
<code>logging</code>   <code>nologging</code>	UFS	Enables logging for the file system. UFS logging is the process of storing transactions (changes that make up a complete UFS operation) into a log before the transactions are applied to the UFS file system. Because the file system can never become inconsistent, <code>fsck</code> can be bypassed, which reduces the time to reboot a system if it crashes, or after an unclean halt.  The log is allocated from free blocks on the file system, and is sized approximately 1 Mbyte per 1 Gbyte of file system, up to a maximum of 64 Mbytes. The default is <code>nologging</code> .
<code>m</code>	CacheFS, NFS, PCFS, S5FS, UFS	Mounts the file system without making an entry in <code>/etc/mnttab</code> .

**TABLE 28-3** Commonly Used `-o` Mount Options *(continued)*

Option	File System	Description
<code>noatime</code>	UFS	Ignores access time updates on files, except when they coincide with updates to the <code>ctime</code> or <code>mtime</code> . See <code>stat(2)</code> . This option reduces disk activity on file systems where access times are unimportant (for example, a Usenet news spool). The default is normal access time ( <code>atime</code> ) recording.
<code>remount</code>	NFS, S5FS, UFS	Remounts a read-only file system as read-write (using the <code>rw</code> option). This option can be used only in conjunction with the <code>f</code> , <code>logging</code>   <code>nologging</code> , and <code>m</code> options. This option works only on currently mounted read-only file systems.
<code>retry=<i>n</i></code>	NFS	Retries the mount operation when it fails. <i>n</i> is the number of times to retry.
<code>ro</code>   <code>rw</code>	CacheFS, NFS, PCFS, UFS, S5FS	Specifies read/write or read-only. If you do not specify this option, the default is read/write.
<code>suid</code>   <code>nosuid</code>	CacheFS, HSFS, NFS, S5FS, UFS	Allows or disallows <code>setuid</code> execution. The default is to allow <code>setuid</code> execution.

## ▼ How to Determine Which File Systems Are Mounted

You can determine which file systems are mounted by using the `mount` command.

```
$ mount -v
```

`-v` Displays the list of mounted file systems in verbose mode.

### Example—Determining Which File Systems Are Mounted

```
$ mount
/ on /dev/dsk/c0t3d0s0 read/write/setuid/largefiles on ...
/usr on /dev/dsk/c0t3d0s6 read/write/setuid/largefiles on ...
/proc on /proc read/write/setuid on Mon Jun 8 10:28:31 1998
```

(continued)

(Continuation)

```
/dev/fd on fd read/write/setuid on Mon Jun 8 10:28:31 1998
/export on /dev/dsk/c0t3d0s3 setuid/read/write/largefiles on ...
/export/home on /dev/dsk/c0t3d0s7 setuid/read/write/largefiles on ...
/export/swap on /dev/dsk/c0t3d0s4 setuid/read/write/largefiles on ...
/opt on /dev/dsk/c0t3d0s5 setuid/read/write/largefiles on ...
/tmp on swap read/write on Mon Jun 8 10:28:31 1998
$
```

## Mounting File Systems Using the /etc/vfstab File

### /etc/vfstab Field Descriptions

An entry in the `/etc/vfstab` file has seven fields, which are described in Table 28-4.

TABLE 28-4 `/etc/vfstab` Field Descriptions

Field Name	Description
device to mount	<ul style="list-style-type: none"><li>■ The block device name for a local UFS file system (for example, <code>/dev/dsk/c0t0d0s0</code>).</li><li>■ The resource name for a remote file system (for example, <code>myserver:/export/home</code>). For more information about NFS, see the <i>NFS Administration Guide</i>.</li><li>■ The block device name of the slice on which to swap (for example, <code>/dev/dsk/c0t3d0s1</code>).</li><li>■ The <code>/proc</code> directory and <code>proc</code> file system type.</li></ul>
device to fsck	The raw (character) device name that corresponds to the file system identified by the device to mount field (for example, <code>/dev/rdsk/c0t0d0s0</code> ). This determines the raw interface that is used by <code>fsck</code> . Use a dash (-) when there is no applicable device, such as for a read-only file system or a remote file system.
mount point	The default mount point directory (for example, <code>/usr</code> ).
FS type	The type of file system identified by the device to mount field.



**TABLE 28-4** /etc/vfstab Field Descriptions (continued)

Field Name	Description
fsck pass	<p>The pass number used by <code>fsck</code> to decide whether to check a file system. When the field contains a dash (-), the file system is not checked.</p> <p>When the field contains a zero, UFS file systems are not checked; non-UFS file systems are checked. When the field contains a value greater than zero, the file system is checked.</p> <p>When the field contains a value of 1, the file system is checked sequentially. When <code>fsck</code> is run on multiple UFS file systems that have <code>fsck pass</code> values greater than one and the <code>preen</code> option (-o p) is used, <code>fsck</code> automatically checks the file systems on different disks in parallel to maximize efficiency. Otherwise, the value of the pass number does not have any effect.</p> <p>The <code>fsck pass</code> field does not explicitly specify the order in which file systems are checked.</p>
mount at boot	Set to <code>yes</code> or <code>no</code> for whether the file system should be automatically mounted by <code>mountall</code> when the system is booted. Note that this field has nothing to do with AutoFS.
mount options	A list of comma-separated options (with no spaces) that are used in mounting the file system. Use a dash (-) to show no options. See Table 28-3 for a list of commonly used mount options.

**Note** - You must have an entry in each field in the `/etc/vfstab` file. If there is no value for the field, be sure to enter a dash (-).

## ▼ How to Add an Entry to the /etc/vfstab File

### 1. Become superuser.

Also, there must be a mount point on the local system to mount a file system. A mount point is a directory to which the mounted file system is attached.

### 2. Edit the /etc/vfstab file and add an entry.

**Note** - Since the root (/) file system is mounted read-only by the kernel during the boot process, only the `remount` option (and options that can be used in conjunction with `remount`) affect the root (/) entry in the `/etc/vfstab` file.

See Table 28-4 for detailed information about the `/etc/vfstab` field entries. Make sure that you:

- Separate each field with white space (a space or a tab).
- Enter a dash (-) if a field has no contents.

### 3. Save the changes.

## Examples—Adding an Entry to the /etc/vfstab File

The following example mounts the disk slice /dev/dsk/c0t3d0s7 as a UFS file system attached to the mount point directory /files1 with the default mount options (read/write). It specifies the raw character device /dev/rdisk/c0t3d0s7 as the device to fsck. The fsck pass value of 2 means that the file system will be checked, but not sequentially.

#device	device	mount	FS	fsck	mount	mount
#to mount	to fsck	point	type	pass	at boot	options
#						
/dev/dsk/c0t3d0s7	/dev/rdisk/c0t3d0s7	/files1	ufs	2	yes	-
/	-	/tmp/				
newroot lofs -	yes	-				

The following example mounts the directory /export/man from the system pluto as an NFS file system on mount point /usr/man. It does not specify a device to fsck or a fsck pass because it's an NFS file system. In this example, mount options are ro (read-only) and soft. For greater reliability, specify the hard mount option for read/write NFS file systems.

#device	device	mount	FS	fsck	mount	mount
#to mount	to fsck	point	type	pass	at boot	options
#						
pluto:/export/man	-	/usr/man	nfs	-	yes	ro,soft

The following example mounts the root (/) file system on a loopback mount point named /tmp/newroot. It specifies yes for mount at boot, no device to fsck, and no fsck pass number. LOFS file systems must always be mounted after the file systems used to make up the LOFS file system.

#device	device	mount	FS	fsck	mount	mount
#to mount	to fsck	point	type	pass	at boot	options
#						
/	-	/tmp/				
newroot lofs -	yes	-				

## ▼ How to Mount Multiple File Systems Listed in the /etc/vfstab File

### 1. Become superuser.

Also, there must be a mount point on the local system to mount a file system. A mount point is a directory to which the mounted file system is attached.

### 2. Mount the file systems listed in the /etc/vfstab file.

```
# mountall [-l | -r] [-F fstype]
```

If no options are specified, all file systems listed in the /etc/vfstab file with `yes` in the `mount at boot` field are mounted.

<code>-l</code>	Mounts all the local file systems listed in the /etc/vfstab file with <code>yes</code> in the <code>mount at boot</code> field.
<code>-r</code>	Mounts all the remote file systems listed in the /etc/vfstab file with <code>yes</code> in the <code>mount at boot</code> field.
<code>-F fstype</code>	Mounts all file systems of the specified type listed in the /etc/vfstab file with <code>yes</code> in the <code>mount at boot</code> field.

All the file systems with a `device to fsck` entry are checked and fixed, if necessary, before mounting.

## Examples—Mounting Multiple File Systems Listed in the /etc/vfstab File

The following example shows the messages displayed if file systems are already mounted when you use the `mountall` command.

```
# mountall
mount: /tmp already mounted
nfs mount: mount: /usr/openwin: Device busy
nfs mount: mount: /usr/man: Device busy
```

The following example mounts all the local systems listed in the /etc/vfstab file.

```
# mountall -l
# mount
/ on /dev/dsk/c0t3d0s0 read/write/setuid/largefiles on ...
/usr on /dev/dsk/c0t3d0s6 read/write/setuid/largefiles on ...
/proc on /proc read/write/setuid on Wed May 27 09:11:50 1998
/dev/fd on fd read/write/setuid on Wed May 27 09:11:50 1998
```

(Continuation)

```
/tmp on swap read/write on Wed May 27 09:11:50 1998
```

The following example mounts all the remote file systems listed in the `/etc/vfstab` file.

```
# mountall -r
# mount
/ on /dev/dsk/c0t3d0s0 read/write/setuid/largefiles on ...
/usr on /dev/dsk/c0t3d0s6 read/write/setuid/largefiles on ...
/proc on /proc read/write/setuid on Mon Jun  8 10:28:31 1998
/dev/fd on fd read/write/setuid on Mon Jun  8 10:28:31 1998
/tmp on swap read/write on Mon Jun  8 10:28:31 1998
/nfs/mars.dist on mars:/usr/dist intr/remote on ...
/nfs/mars.mail on mars:/var/mail intr/noac/remote on ...
```

## ▼ How to Mount a File System Listed in the `/etc/vfstab` File

### 1. Become superuser.

Also, there must be a mount point on the local system to mount a file system. A mount point is a directory to which the mounted file system is attached.

### 2. Mount a file system listed in the `/etc/vfstab` file.

```
# mount mount-point
```

*mount-point*

Specifies an entry in the `mount point` or device to `mount` field in the `/etc/vfstab` file. It is usually easier to specify the mount point.

## Example—Mounting a File System Listed in the `/etc/vfstab` File

The following example mounts the `/usr/openwin` file system listed in the `/etc/vfstab` file.

```
# mount /usr/openwin
```

# Mounting File Systems Using the mount Command

## ▼ How to Mount a UFS File System

### 1. Become superuser.

Also, there must be a mount point on the local system to mount a file system. A mount point is a directory to which the mounted file system is attached.

### 2. Mount the UFS file system by using the `mount` command.

```
# mount [-o mount-options] /dev/dsk/device-name mount-point
```

*-o mount-options*

Specifies mount options that you can use to mount a UFS file system. See Table 28–3 for the list of general mount options or `mount_ufs(1M)` for a commonly used list of options.

*/dev/dsk/device-name*

Specifies the disk device name for the slice holding the file system (for example, `/dev/dsk/c0t3d0s7`). See “How to Display Disk Slice Information” on page 334 to get slice information for a disk.

*mount-point*

Specifies the directory on which to mount the file system.

## Example—Mounting a UFS File System

The following example mounts `/dev/dsk/c0t3d0s7` on the `/files1` directory.

```
# mount /dev/dsk/c0t3d0s7 /files1
```

## Example—Mounting a UFS File System With Logging Enabled

UFS logging eliminates file system inconsistency, which can significantly reduce the time of system reboots. The following example mounts `/dev/dsk/c0t3d0s7` on the `/files1` directory with logging enabled.

```
# mount -o logging /dev/dsk/c0t3d0s7 /files1
```

## ▼ How to Remount a UFS File System Without Large Files

When you mount a file system, the `largefiles` option is selected by default, which enables you to create files larger than 2 Gbytes. Once a file system contains large files, you cannot remount the file system with the `nolargefiles` option until you remove any large files and run `fsck` to reset the state to `nolargefiles`.

This procedure assumes that the file system is in the `/etc/vfstab` file.

1. **Become superuser.**
2. **Make sure there are no large files in the file system.**

```
# cd mount-point
# find . -xdev -size +2000000 -exec ls -l {} \;
```

*mount-point*

Specifies the mount point of the file system you want to check for large files.

If large files exist within this file system, they must be removed or moved to another file system.

3. **Unmount the file system.**

```
# umount mount-point
```

4. **Reset the file system state.**

```
# fsck mount-point
```

5. **Remount the file system with the `nolargefiles` option.**

```
# mount -o nolargefiles mount-point
```

## Example—Mounting a File System Without Large Files

The following example checks the `/datab` file system and remounts it with the `nolargefiles` option.

```
# cd /datab
# find . -xdev -size +2000000 -exec ls -l {} \;
# umount /datab
# fsck /datab
# mount -o nolargefiles /datab
```

## ▼ How to Mount an NFS File System

### 1. Become superuser.

Also, there must be a mount point on the local system to mount a file system. A mount point is a directory to which the mounted file system is attached.

### 2. Make sure the resource (file or directory) is available from a server.

To mount an NFS file system, the resource must be made available on the server by using the `share` command. See *NFS Administration Guide* for information on how to share resources.

### 3. Mount the NFS file system by using the `mount` command.

```
# mount -F nfs [-o mount-options] server:/directory mount-point
```

*-o mount-options*

Specifies `mount` options that you can use to mount an NFS file system. See Table 28–3 for the list of commonly used mount options or `mount_nfs(1M)` for a complete list of options.

*server:/directory*

Specifies the server's host name that contains the shared resource, and the path to the file or directory to mount.

*mount-point*

Specifies the directory on which to mount the file system.

## Example—Mounting an NFS File System

The following example mounts the `/export/packages` directory on `/mnt` from the server `pluto`.

```
# mount -F nfs pluto:/export/packages /mnt
```

## ▼ x86: How to Mount a System V (S5FS) File System

### 1. Become superuser.

Also, there must be a mount point on the local system to mount a file system. A mount point is a directory to which the mounted file system is attached.

### 2. Mount the S5FS file system by using the `mount` command.

```
# mount -F s5fs [-o mount-options] /dev/dsk/device_name mount-point
```

<i>-o mount-options</i>	Specifies mount options that you can use to mount a S5FS file system. See Table 28-3 for the list of commonly used mount options or <code>mount_s5fs(1M)</code> for a complete list of options.
<i>/dev/dsk/device-name</i>	Specifies the disk device name of the slice holding the file system (for example, <code>/dev/dsk/c0t3d0s7</code> ). See “How to Display Disk Slice Information” on page 334 to get slice information for a disk.
<i>mount-point</i>	Specifies the directory on which to mount the file system.

## Example—Mounting an S5FS File System

The following example mounts `/dev/dsk/c0t3d0s7` on the `/files1` directory.

```
# mount -F s5fs /dev/dsk/c0t3d0s7 /files1
```

## ▼ How to Mount a PCFS (DOS) File System From a Hard Disk

Use the following procedure to mount a PCFS (DOS) file system from a hard disk.

### 1. Become superuser.

Also, there must be a mount point on the local system to mount a file system. A mount point is a directory to which the mounted file system is attached.

### 2. Mount the PCFS file system by using the `mount` command.



```
# mount -F pcfs [-o rw | ro] /dev/dsk/device-name:logical-drive mount-point
```

<code>-o rw   ro</code>	Specifies that you can mount a PCFS file system read/write or read-only. If you do not specify this option, the default is read/write.
<code>/dev/dsk/device-name</code>	Specifies the device name of the whole disk (for example, <code>/dev/dsk/c0t0d0p0</code> ).
<code>logical-drive</code>	Specifies either the DOS logical drive letter (c through z) or a drive number 1 through 24. Drive c is equivalent to drive 1 and represents the Primary DOS slice on the drive; all other letters or numbers represent DOS logical drives within the Extended DOS slice.
<code>mount-point</code>	Specifies the directory on which to mount the file system.

Note that the *device-name* and *logical-drive* must be separated by a colon.

## Examples—Mounting a PCFS (DOS) File System From a Hard Disk

The following example mounts the logical drive in the Primary DOS slice on the `/pcfs/c` directory.

```
# mount -F pcfs /dev/dsk/c0t0d0p0:c /pcfs/c
```

The following example mounts the first logical drive in the Extended DOS slice read-only on `/pcfs/d`.

```
# mount -F pcfs -o ro /dev/dsk/c0t0d0p0:2 /pcfs/d
```

---

## Unmounting File Systems

Unmounting a file system removes it from the file system mount point, and deletes the entry from the `/etc/mnttab` file. Some file system administration tasks cannot be performed on mounted file systems. You should unmount a file system when:

- It is no longer needed or has been replaced by a file system that contains more current software.

- You need to check and repair it using the `fsck` command. See Chapter 31 for more information about the `fsck` command.

It is a good idea to unmount a file system before doing a complete backup. See Chapter 34 for more information about doing backups.

---

**Note** - File systems are automatically unmounted as part of the system shutdown procedure.

---

## Prerequisites

The prerequisites to unmount file systems are:

- You must be superuser.
- A file system must be available for unmounting. You cannot unmount a file system that is busy. A file system is considered busy if a user is in a directory in the file system, or if a program has a file open in that file system. You can make a file system available for unmounting by:
  - Changing to a directory in a different file system.
  - Logging out of the system.
  - Using the `fuser` command to list all processes accessing the file system and to stop them if necessary. See “How to Stop All Processes for a File System” on page 440 for more details.

Notify users if you need to unmount a file system they are using.

## Verifying an Unmounted File System

To verify that you unmounted a file system or a number of file systems, look at the output from the `mount` command. This is described in “How to Determine Which File Systems Are Mounted” on page 429.

### ▼ How to Stop All Processes for a File System

1. **Become superuser.**
2. **List all the processes that are using the file system, so you know which processes you are going to stop.**

```
# fuser -c [ -u ] mount-point
```

<code>-c</code>	Reports on files that are mount points for file systems and any files within those mounted file systems.
<code>-u</code>	Displays the user login name for each process ID.
<i>mount-point</i>	The name of the file system for which you want to stop processes.

### 3. Stop all processes for the file system.

---

**Note** - You should not stop a user's processes without warning.

---

```
# fuser -c -k mount-point
```

A SIGKILL is sent to each process using the file system.

### 4. Verify that there are no processes using the file system.

```
# fuser -c mount-point
```

## Example—Stopping All Processes for a File System

The following example stops process 4006c that is using the `/export/home` file system.

```
# fuser -c /export/home
/export/home:      4006c
# fuser -c -k /export/home
/export/home:      4006c
# fuser -c /export/home
/export/home:
```

## ▼ How to Unmount a File System

Use the following procedure to unmount a file system (except `/` or `/usr`):

---

**Note** - The root (/) and /usr file systems are special cases. The root (/) file system can be unmounted only during a shutdown, since the system needs the root (/) file system to function.

---

1. **Make sure you have met the prerequisites listed on “Prerequisites” on page 440.**
2. **Unmount the file system.**

```
# umount mount-point
```

*mount-point*

The name of the file system that you want to unmount. This can either be the directory name where the file system is mounted, the device name path of the file system, the resource for an NFS file system, or the loopback directory for LOFS file systems.

## Examples—Unmounting a File System

The following example unmounts a local home file system.

```
# umount /export/home
```

The following example unmounts the file system on slice 7.

```
# umount /dev/dsk/c0t0d0s7
```

## ▼ How to Unmount File Systems Listed in the /etc/vfstab File

Use the following procedure to unmount all the file systems listed in the /etc/vfstab file, except for the /, /proc, /var, and /usr file systems.

1. **Make sure you have met the prerequisites listed on “Prerequisites” on page 440.**
2. **Unmount all the file systems listed in the /etc/vfstab file.**

```
# umountall
```

All systems that are unmounted, except those that are busy.

3. For the file systems that were busy and not unmounted, make them available to be unmounted as described in “How to Stop All Processes for a File System” on page 440.
4. Repeat Step 2 as needed until all file systems are unmounted.



## The Cache File System (Tasks)

---

The Cache File System (CacheFS) is a general purpose file system caching mechanism that improves NFS server performance and scalability by reducing server and network load. Designed as a layered file system, CacheFS provides the ability to cache one file system on another. In an NFS environment, CacheFS increases the client per server ratio, reduces server and network loads and improves performance for clients on slow links, such as Point-to-Point Protocol (PPP).

The following is a list of the step-by-step instructions in this chapter.

- “How CacheFS Works” on page 446
- “Setting Up a Cached File System Task Map” on page 447
- “How to Create a Cache” on page 448
- “How to Specify a File System to Be Mounted in a Cache With `mount`” on page 449
- “How to Mount a File System in a Cache by Editing the `/etc/vfstab` File” on page 452
- “How to Mount a File System in a Cache With AutoFS” on page 453
- “How to Modify File Systems in a Cache” on page 455
- “How to Display Information About Cached File Systems” on page 456
- “How to Specify Consistency Checking on Demand” on page 457
- “How to Delete a Cached File System” on page 457
- “How to Check the Integrity of Cached File Systems” on page 459
- “CacheFS Statistics” on page 472
- “Prerequisites for Setting Up and Viewing the CacheFS Statistics” on page 473
- “Setting Up CacheFS Statistics Task Map” on page 474
- “How to Set Up the Logging Process” on page 474

- “Viewing the Cache Size” on page 476
- “How to View the Working Set (Cache) Size” on page 476
- “Viewing the Statistics” on page 477
- “How to View Cache Statistics” on page 478
- “The Cache Structure and Behavior” on page 479
- “Consistency Checking of Cached File Systems With the Back File System” on page 480
- “Consistency Checking on Demand” on page 480

---

## How CacheFS Works

You create a cache, using the `cfsadmin(1M)` command, on the client so that file systems you specify to be mounted in the cache can be accessed by the user locally instead of across the network. Figure 29-1 shows the relationship of the components involved in using CacheFS.

The back file system is the file system that you specify to be mounted in the cache, which can be either an NFS or HSFS (High Sierra File System) file system. When the user attempts to access files that are part of the back file system, those files are placed in the cache. To the user, the initial request to access a file may seem slow, but subsequent uses of the same file will be faster.

---

**Note** - You can mount only file systems that are shared. See `share(1M)` for information on sharing file systems.

---






Figure 29-1 How CacheFS Works

## Setting Up a Cached File System Task Map

TABLE 29-1 Task Map: Setting Up a Cached File System

Task	Description	For Instructions, Go To
1. Create a Cache	Use the <code>cfsadmin</code> command to create a cache.	"How to Create a Cache" on page 448
2. Mount File Systems in the Cache	Mount a file system in a cache by using the <code>mount</code> command.	"How to Specify a File System to Be Mounted in a Cache With <code>mount</code> " on page 449

**TABLE 29-1** Task Map: Setting Up a Cached File System *(continued)*

Task	Description	For Instructions, Go To
	Cache a file system by editing the <code>/etc/vfstab</code> file.	“How to Mount a File System in a Cache by Editing the <code>/etc/vfstab</code> File” on page 452
	Cache a file system by using AutoFS.	“How to Mount a File System in a Cache With AutoFS” on page 453

## Creating a Cache

### ▼ How to Create a Cache

1. **Become superuser.**
2. **Create a cache using the `-c` option of the `cfsadmin` command.**

```
# cfsadmin -c cache-directory
```

*cache-directory*

Indicates the name of the directory where the cache resides. For more information, see the `cfsadmin` man page.

---

**Note** - After you have created the cache, do not perform any operations within the cache directory itself. This causes conflicts within the CacheFS software.

---

### Example—Creating a Cache

The following example creates a cache in the `/local/mycache` directory by using the default cache parameter values.

```
# mkdir /local
# cfsadmin -c /local/mycache
```

---

## Specifying a File System to Be Mounted in the Cache

You specify file systems to be mounted in the cache so that users can locally access files in the file system you've specified. The files do not actually get placed in the cache until the user accesses the files.

There are three ways to specify file systems to be cached:

- Using the `mount(1M)` command – you need to use the `mount` command every time the system reboots in order to access the same file system.
- Editing the `/etc/vfstab` file – you only need to do this once. The `/etc/vfstab` file will remain unaltered after the system reboots.
- Using AutoFS – you only need to do this once. AutoFS maps remain unaltered after the system reboots.

Choose the method of mounting file systems you are most familiar with.

---

**Note** - Caching of the root (/) and /usr file systems is not supported in CacheFS. To cache the root (/) and /usr file systems, you must purchase the Solstice AutoClient product. For more information about the AutoClient product, see the *Solstice AutoClient 2.1 Administration Guide*.

---

### ▼ How to Specify a File System to Be Mounted in a Cache With `mount`

**1. Become superuser.**

**2. Create a mount point.**

The mount point allows user access to the file system specified under that mount point. You can create the mount point from anywhere. The CacheFS options used with the `mount` command, as shown in the next step, will determine that the mount point you created will be cached in the cache directory you specified.

**3. Mount a file system in a cache with the `mount` command.**

```
# mount -F cachefs -o backfstype=fstype,cachedir=cache-directory[ , options]
back-filesystem mount-point
```

<i>fstype</i>	Indicates the file system type of the back file system (can be either <i>nfs</i> or <i>hsfs</i> ).
<i>cache-directory</i>	Indicates the name of the directory where the cache resides. This is the same name you specified when you created the cache in “How to Create a Cache” on page 448.
<i>options</i>	Specifies other mount options that you can include when mounting a file system in a cache. See <b>mount_cachefs(1M)</b> for a list of CacheFS mount options.
<i>back-filesystem</i>	The mount point of the back file system to cache. If the back file system is an NFS file system, you must specify the host name of the server from which you are mounting the file system and the name of the file system to cache (separated by a colon), for example, <i>merlin: /usr/openwin</i>
<i>mount-point</i>	Indicates the directory where the file system is mounted.

**4. Verify that the cache you created was actually mounted by using the **cachefsstat(1M)** command, as follows:**

```
# cachefsstat mount-point
```

For example:

```
# cachefsstat /docs
/docs
      cache hit rate:    100% (0 hits, 0 misses)
      consistency checks: 1 (1 pass, 0 fail)
      modifies:         0
      garbage collection: 0
```

The mount point is the cached file system you created. For more information about the **cachefsstat** command, see “CacheFS Statistics” on page 472.

If the file system was not mounted in the cache, you will receive an error message similar to the following:

```
# cacheostat mount-point
cacheostat: mount-point: not a cache mountpoint
```

## Examples—Specifying a File System to be Mounted in a Cache With mount

The following example creates the mount point `/docs`, and mounts the NFS file system `merlin:/docs` as a cached file system named `/docs` in the cache named `/local/mycache`.

```
# mkdir /docs
# mount -F cache -o backfstype=nfs,cachedir=/local/mycache merlin:/docs /docs
```

The following example makes a CD-ROM (HSFS file system) available as a cached file system named `/docs`. Because you cannot write to the CD-ROM, the `ro` argument is specified to make the cached file system read-only. You must specify the `backpath` option because Volume Management automatically mounts the CD-ROM when it is inserted. The mount point is in the `/cdrom` directory and is determined by the name of the CD-ROM. The special device to mount is the same as the value for the `backpath` command.

```
# mount -F cache -o backfstype=hsfs,cachedir=/local/mycache,ro backpath=/cdrom/cdrom_name /cdrom/cdrom_name /docs
```

The following example uses the `demandconst` option to specify consistency checking on demand for the NFS cached file system `/docs`, whose back file system is `merlin:/docs`. See “Consistency Checking of Cached File Systems With the Back File System” on page 480 for more information.

```
# mount -F cachefs -o backfstype=nfs,cachedir=/local/mycache,demandconst merlin:/docs /docs
```

## ▼ How to Mount a File System in a Cache by Editing the `/etc/vfstab` File

1. Become superuser.
2. Using an editor, specify the file systems to be mounted in the `/etc/vfstab` file:

```
#device      device          mount FS    fsck mount  mount
#to mount    to fsck             point type  pass  at boot options
#
/dev/dsk/devicename /dev/rdisk/devicename /mount-point cachefs 2    yes  -
```

This line represents the new entry.

3. Mount the cached file system using the `mount` command, as follows:

```
# mount /mount-point
```

or reboot.

### Example—Mounting a File System in a Cache by Editing the `/etc/vfstab` File

The following example shows the `/etc/vfstab` entry for the cache file system.

```
#device      device          mount FS    fsck mount  mount
#to mount    to fsck             point type  pass  at boot options
#
/dev/dsk/c0t1d0s0 /dev/rdisk/c0t1d0s0 /usr/local cachefs 2    yes  -
```

The `/usr/local` directory is mounted in the cache directory.

```
# mount /usr/local
```

## ▼ How to Mount a File System in a Cache With AutoFS

You can mount a file system in a cache with AutoFS by specifying the `-fstype=cachefs` mount option in your automount map. Note that CacheFS mount options (for example, `backfstype` and `cachedir`) are also specified in the automount map. See `automount(1M)` for details on automount maps. Also see the *NFS Administration Guide*.

1. Become superuser.

2. Using an editor, add the following line to the `auto_direct` map:

```
/mount-point -fstype=cachefs,cachedir=/directory,backfstype=nfs
server:/file-system
```

3. Using an editor, add the following line to the `auto_master` map:

```
/-
```

The `/-` entry is a pointer to check the `auto_direct` map.

4. Reboot the system.

5. Verify that the entry was made correctly by changing to the file system you mounted in the cache, and then list the contents, as follows:

```
# cd filesystem
# ls filesystem
```

For more information about AutoFS and how to edit the maps, refer to the AutoFS chapter of the *NFS Administration Guide*.

### Example—Mounting a File System in a Cache With AutoFS

The following `auto_master` entry automatically mounts the cache file system in the `/docs` directory.

```
/docs -fstype=cachefs,cachedir=/local/mycache,backfstype=nfs
merlin:/docs
```

## Maintaining a Cached File System Task Map

**TABLE 29-2** Maintaining a Cached File System Task Map

Task	Description	For Instructions, Go To
1. Modify the Cache	Modify the cache behavior.	"How to Modify File Systems in a Cache" on page 455
2. Display Cache Information	Display information about cached file systems by using the <code>cfsadmin</code> command.	"How to Display Information About Cached File Systems" on page 456
3. Perform Consistency Checking	Perform consistency checking on demand by using the <code>cfsadmin</code> command.	"How to Specify Consistency Checking on Demand" on page 457
4. Delete a Cache	Delete cached file systems by using the <code>umount</code> command and the <code>cfsadmin</code> command.	"How to Delete a Cached File System" on page 457
5. Check File System Integrity	Check the integrity of cached file systems by using the <code>fsck_cachefs</code> command.	"How to Check the Integrity of Cached File Systems" on page 459

## Maintaining the Cache

After you set up the cache, you can perform the following maintenance tasks on it:



- Modify file systems in the cache (by unmounting, deleting, recreating, and remounting the cache)
- Display cache information
- Check cache consistency
- Delete a file system from the cache
- Check cached file system integrity

---

**Note** - If you are using the `/etc/vfstab` file to mount file systems, you modify the cache by editing the file systems options in the `/etc/vfstab` file. If you are using AutoFS, you modify the cache by editing the file systems options in the AutoFS maps.

---

## ▼ How to Modify File Systems in a Cache

For information on how to modify specific options of a file system, refer to Chapter 28. When you modify a file system in the cache, you need to delete the cache and then recreate it. You may also need to reboot your machine in single user mode, depending on how your file systems are shared and accessed.

The following example shows some of the steps involved in this procedure.

### Example—Modifying File Systems in a Cache

In the following example, the cache is deleted, then re-created, and then mounted again with the `demandconst` option specified for the file system `/docs`. This example shows the steps including rebooting to single user mode. You may have other commands you prefer to use to accomplish some of the tasks shown in this example.

```
$ su
password:

# shutdown -g30 -y
.
.
.
Type Cntrl-d to proceed with normal startup,
(or give root password for system maintenance):
# enter password:
.
.
.
Here is where you may be prompted from system to run fsck on the
file system where the cache is located.

# fsck /local
```

(continued)

(Continuation)

```
# mount /local
# cfsadmin -d all /local/mycache
# cfsadmin -c /local/mycache
# init 6
.
.
.
console login:
password:
# mount -F cachefs -o backfstype=nfs,cachedir=/local/cache1, demandconst merlin:/docs /docs
#
```

If you did not successfully remount the file system in the cache, the system displays an error message similar to the following:

```
cachefsstat: /doc: not a cachefs mount point
```

## ▼ How to Display Information About Cached File Systems

1. Become superuser.
2. Display information about all file systems cached under a specified cache.

```
# cfsadmin -l cache-directory
```

*cache-directory* is the name of the directory where the cache resides.

### Example—Displaying Information About Cached File Systems

The following example shows information about the cache directory named `/local/mycache`. In this example, the file system `/docs` is cached in `/local/mycache`. The last line displays the name of the cached file system.

```
# cfsadmin -l /local/mycache
cfsadmin: list cache FS information
maxblocks      90%
minblocks      0%
threshblocks    85%
maxfiles       90%
minfiles       0%
threshfiles     85%
```

(continued)

(Continuation)

```
maxfilesize      3MB
merlin:_docs:_docs
#
```

## ▼ How to Specify Consistency Checking on Demand

1. **Become superuser.**
2. **Mount the file system in the cache specifying the `demandconst` option of the `mount` command, as follows:**

```
# mount -F cachefs -o backfstype=nfs,cachedir=/directory,demandconst
server:/file-system /mount-point
```

3. **To initiate consistency checking on a specific cached file system, use the `cfsadmin` command with the `-s` option as follows:**

```
# cfsadmin -s /mount-point
```

For more information about consistency checking, see “Consistency Checking of Cached File Systems With the Back File System” on page 480.

## ▼ How to Delete a Cached File System

1. **Become superuser.**
2. **Unmount the cached file system.**

```
# umount mount-point
```

*mount-point* specifies the cached file system that you want to delete.

3. **Determine the cache ID from the `cfsadmin -l` output, as follows:**

```
# cfsadmin -l cache-directory
cfsadmin: list cache FS information
maxblocks      90%
minblocks      0%
threshblocks    85%
maxfiles       90%
minfiles       0%
threshfiles     85%
maxfilesize    3MB
cache-ID
#
```

#### 4. Delete a cached file system from a specified cache.

```
# cfsadmin -d cache-id cache-directory
```

*cache-id* Indicates the name of the cached file system, which is the last line of the `cfsadmin -l` output. See “How to Display Information About Cached File Systems” on page 456 for more information. You can delete all the cached file systems in a particular cache by specifying `all` for *cache-id*.

*cache-directory* Specifies the directory where the cache resides.

#### 5. Verify that the file system has been deleted.

The cache ID of the file system you just deleted should be missing from the output of the following command. Refer to `cfsadmin(1M)` for more information about the fields specified in the command output.

```
# cfsadmin -l cache-directory
cfsadmin: list cache FS information
maxblocks      90%
minblocks      0%
threshblocks    85%
maxfiles       90%
minfiles       0%
threshfiles     85%
maxfilesize    3MB
#
```

## Examples—Deleting a Cached File System

The following example unmounts a cached file system and deletes the cached file system from the cache.

```
# umount /docs
# cfsadmin -d merlin:_docs:_docs /local/mycache
```

The following example deletes all the cached file systems in the `/local/mycache` cache. This also deletes the cache.

```
# cfsadmin -d all /local/mycache
```

## ▼ How to Check the Integrity of Cached File Systems

Use the `fsck` command to check the integrity of cached file systems. The CacheFS version of `fsck` automatically corrects problems without requiring user interaction. You should not need to run `fsck` manually for cached file systems; `fsck` is run automatically at boot time or when the file system is mounted. If you want to manually check the integrity, you can use the following procedure.

See `fsck_cachefs(1M)` for more information.

1. **Become superuser.**
2. **Check the cached file systems under a specified cache.**

```
# fsck -F cachefs [-m] [-o noclean] cache-directory
```

<code>-m</code>	Causes <code>fsck</code> to check the cached file systems without making any repairs.
<code>-o noclean</code>	Forces a check on the cached file systems only. Does not make any repairs.
<code>cache-directory</code>	Indicates the name of the directory where the cache resides.

## Example—Checking the Integrity of Cached File Systems

The following example checks the cached file systems that are part of the `/local/mycache` cache.

```
# fsck -F cachefs /local/mycache
#
```

---

## Managing Your Cache File Systems With cachefspack

For general use, CacheFS operates automatically, without requiring any action from the user. Files are cached on a most recently used basis. With the *packing* feature, you can take a more active role in managing your cache by ensuring that certain files or directories are always updated in the cache.

Packing enables you to specify files and directories to be loaded in the cache. It ensures that current copies of these files are available in the cache.

The *packing list* contains the names of specific files and directories. It can also contain other packing lists. This saves you having to specify individual files and directories in case you have many items to pack in your cache.

The `cachefspack` command provides you with added control of your CacheFS file systems, employing the packing functionality.

### ▼ How to Pack Files in the Cache

Pack files in the cache using the `cachefspack` command.

```
$ cachefspack -p filename
```

`-p`

Specifies that you want the file or files packed. This is also the default.

*filename*

Specifies the name of the file or directory you want packed in the cache. When you specify a directory, all of its subdirectories are also packed. For more information, see `cachefspack(1M)`.

### Examples—Packing Files in the Cache

The following example shows the file `projects` specified to be packed in the cache.

```
$ cachefspack -p projects
```

The following example shows several files specified to be packed in the cache.

```
$ cachefspack -p projects updates master_plan
```

The following example shows a directory specified to be packed in the cache.

```
$ cachefspack -p /usr/openwin/bin
```

---

## Packing Lists

One of the features of the `cachefspack` command is the ability to pack packing lists. This saves the time of having to specify each individual file that you want packed in the cache.

A packing list contains files or directories to be packed in the cache. If a directory is in the packing list, all of its subdirectories and files will also be packed.

### ▼ How to Create a Packing List

To create a packing list, open a file by using `vi` or the editor of your choice. The packing list file format uses the same format as the `filesync` command. See `filesync(1)` for more information.

#### Example—Creating a Packing List

The following example shows the contents of a packing list file.

```
BASE /home/ignatz
LIST plans
LIST docs
IGNORE *.ps
```

- The path identified with the `BASE` statement is the directory where you have items you wish to pack.
- The two `LIST` statements identify specific files within that directory to pack.
- The `IGNORE` statement identifies the file type of `.ps`, which you do not wish to pack.

## ▼ How to Pack Files in the Cache as Specified in a Packing List

To pack files using the packing list, use the `cachefspack -f` command, as follows:

```
$ cachefspack -f packing-list
```

This means you want the software to read the packing list and pack files based on the information specified in the packing list.

`-f` Specifies that you want to use a packing list.

`packing-list` Specifies the name of the packing list.

### Example—Packing Files in the Cache as Specified in a Packing List

This examples uses the `list.pkg` file as the packing list for the `cachefspack` command.

```
$ cachefspack -f list.pkg
```

## ▼ How to Specify Files in the Packing List to be Treated as Regular Expressions

To specify that one or more files in the packing list should be treated as regular expressions (not as literal file names), use the `-r` option with the `-f` option of the `cachefspack` command. The `-r` option cannot be used alone.

```
$ cachefspack -rf packing_list
```

where `packing_list` contains a `LIST` command defined as follows:

```
LIST *.doc
```



<code>-r</code>	Specifies that you want the file or files defined in the <code>LIST</code> command treated as regular expressions, and not as literal file names.
<code>-f</code>	Specifies that you want the packing list packed in the cache.
<i>packing_list</i>	Indicates the name of the packing list that contains the <code>LIST</code> command with the file or files you want treated as regular expressions.

## Example—Specifying Files in the Packing List to be Treated as Regular Expressions

The following example shows the packing list `list.pkg` specified to be packed in the cache. `list.pkg` contains a `LIST` command that defines a regular expression.

```
$ cachefspack -rf list.pkg
```

The software will pack the file `list.pkg` into the cache and treat the file names defined in the `LIST` command as regular expressions, and not as literal file names.

## ▼ How to Pack Files From a Shared Directory

1. To pack files from a shared directory, and to ensure that you pack only those files that you own, define the `LIST` command within the packing list file as follows:

```
LIST !find . -user your_user_name -print
```

2. Pack the packing list in the cache using the `cachefspack -sf` command.

```
$ cachefspack -sf packing_list
```

<code>-s</code>	Adjusts the output of the <code>find</code> command to be suitable for the packing list.
<code>-f</code>	Specifies a packing list to read.
<i>filename</i>	Specifies the name of the packing list to read.

---

**Note** - The `-s` option must be used with the `-f` option. The `-s` option cannot be used alone.

---

### Example—Packing Files From a Shared Directory

The following example shows how to define a `LIST` command in the packing list to pack only the files from the base directory that you own:

```
LIST !find . -user jones -print
```

The following example shows how you would then specify packing the packing list.

```
$ cachefspack -sf /projects/proj_1
```

---

## Unpacking Files

You may need to remove, or unpack, a file from the cache. Perhaps you have some files or directories that are a higher priority than others, so you need to unpack the less critical files. For example, you finished up a project and have archived the files associated with that project. You are now working on a new project, and therefore, a new set of files.

### ▼ How to Unpack Files or Packing Lists From the Cache

Unpack files or packing lists from the cache using the `-u` or `-U` option of the `cachefspack` command.

```
$ cachefspack -u filename | -U cache-directory
```

<code>-u</code>	Specifies that you want the file or files unpacked. You must specify a filename with this option.
<i>filename</i>	Specifies the name of the file or packing list you want unpacked in the cache. For more information about the <code>cachefspack</code> command, see the man page.
<code>-U</code>	Specifies that you want to unpack all files in the cache.

## Examples—Unpacking Files or Packing Lists From the Cache

The following example shows the file `/usr/openwin/bin/xlogo` specified to be unpacked from the cache.

```
$ cachefspack -u /usr/openwin/bin/xlogo
```

The following example shows several files specified to be unpacked from the cache.

```
$ cd /usr/openwin/bin
$ cachefspack -u xlogo xview xcolor
```

You can also unpack a packing list, which is a file that contains the path to a directory of files, as follows:

```
$ cachefspack -uf list.pkg
```

The following example uses the `-U` option to specify all files in a cache directory to be unpacked.

```
$ cachefspack -U /local/mycache
```

You cannot unpack a cache that does not have at least one file system mounted. With the `-U` option, if you specify a cache that does not contain mounted filesystems, you will see output similar to the following:

```
$ cachefspack -U /local/mycache
cachefspack: Could not unpack cache /local/mycache, no mounted
filesystems in the cache.
```

---

## Displaying Packed Files Information

You may want to view information about the files that you've specified to be packed, and what their packing status is.

### ▼ How to Display Packed Files Information

To display packed files information, use `cachefspack -i` command.

```
$ cachefspack -i[v] cached-filename-or-directory
```

`-i` Specifies you want to view information about your packed files.

`-v` The verbose option.

*cached-filename-or-directory* Specifies the name of the file or directory for which to display information.

### Example—Displaying Packed Files Information

The following example shows that a file called `doc_file` is successfully packed.

```
$ cachefspack -i doc_file
cachefspack: file doc_file marked packed YES, packed YES
```

The following example shows a directory called `/usr/openwin`, which contains a subdirectory `bin`. The subdirectory `bin` has three files: `xterm`, `textedit`, and `resize`. Although the files `xterm` and `resize` are specified to be packed, they are not. The file `textedit` is successfully packed.

```
$ cd /usr/openwin
$ cachefspack -i bin
.
.
.
cachefspack: file /bin/xterm marked packed YES, packed NO
cachefspack: file /bin/textedit marked packed YES,
packed YES
cachefspack: file /bin/resize marked packed YES,
packed NO
.
```

(continued)

(Continuation)

```
.  
.
```

If you use the `-v` option in combination with the `-i` option, you will get additional information as to whether or not the file or directory specified has been flushed from the cache. For example:

```
$ cd /usr/openwin  
$ cachefspack -iv bin  
.  
.  
.  
cachefspack: file /bin/xterm marked packed YES, packed NO,  
nocache YES  
cachefspack: file /bin/textedit marked packed YES,  
packed YES, nocache NO  
cachefspack: file /bin/resize marked packed YES,  
packed NO  
nocache NO  
.  
.  
.
```

The last line of the example above shows that the directory contents have not been flushed from the cache.

---

## Viewing Help on the cachefspack Command

You can print out a brief help summary of all the cachefspack options and what they mean by using the `-h` option as follows:

```
$ cachefspack -h  
Must select 1 and only 1 of the following 5 options  
-d Display selected filenames  
-i Display selected filenames packing status  
-p Pack selected filenames  
-u Unpack selected filenames  
-U Unpack all files in directory 'dir'  
  
-f Specify input file containing rules  
-h Print usage information
```

(Continuation)

```
-r Interpret strings in LIST rules as regular expressions
-s Strip './' from the beginning of a pattern name
-v Verbose option
files - a list of filenames to be packed/unpacked
```

---

## cachefspack Errors

You may see the following error messages when you use the `cachefspack` command.

```
cachefspack: pathname - can't open directory: permission denied
```

### Reason Error Occurred

You may not have the correct permissions to access the file or directory.

### How to Fix the Problem

Obtain the proper permissions.

```
cachefspack: pathname - can't open directory: no such file or
directory
```

### Reason Error Occurred

You may not have the correct file or directory.

### How to Fix the Problem

Check for a possible typo.

```
cachefspack: pathname - can't open directory: stale NFS file handle
```

### Reason Error Occurred

The file or directory may have been moved or deleted from the server at the time you attempted to access it.

### How to Fix the Problem

Check with your system administrator.

```
cachefspack: pathname - can't open directory: interrupted system call
```

**Reason Error Occurred****How to Fix the Problem**

You may have issued Control-c during the process of using the command.

Reissue the command.

```
cachefspack: pathname - can't open directory: I/O error
```

**Reason Error Occurred****How to Fix the Problem**

A hardware problem.

Check your hardware connections.

```
cachefspack: error opening dir
```

**Reason Error Occurred****How to Fix the Problem**

You may not have the correct file or directory.

Check for a possible typo.

The path identified after the BASE command in the file format could be a file and not a directory. The path specified must be a directory.

Check the path identified after the BASE command in your file format. Make sure it is a directory, and not a file.

```
cachefspack: unable to get shared objects
```

**Reason Error Occurred****How to Fix the Problem**

The executable may be corrupt or it's a format that is not recognizable.

No corrective action can be taken.

```
cachefspack: filename - can't pack file: permission denied
```

**Reason Error Occurred****How to Fix the Problem**

You may not have the correct permissions to access the file or directory.

Obtain the proper permissions.

```
cachefspack: filename - can't pack file: no such file or directory
```

**Reason Error Occurred****How to Fix the Problem**

You may not have the correct file or directory.

Check for a possible typo.

```
cachefspack: filename - can't pack file: stale NFS file handle
```

**Reason Error Occurred****How to Fix the Problem**

The file or directory may have been moved or deleted from the server at the time you attempted to access it.

Check with your system administrator.

```
cachefspack: filename - can't pack file: interrupted system call
```

**Reason Error Occurred****How to Fix the Problem**

You may have issued Control-c during the process of using the command.

Reissue the command.

```
cachefspack: filename - can't pack file: I/O error
```

**Reason Error Occurred****How to Fix the Problem**

A hardware problem.

Check your hardware connections.

```
cachefspack: filename - can't pack file: no space left on device.
```



Reason Error Occurred	How to Fix the Problem
You are out of disk space.	You need to increase disk space.
The cache is at maximum capacity.	Increase the size of the cache.

```
cachefspack: filename - can't unpack file: permission denied
```

Reason Error Occurred	How to Fix the Problem
You may not have the correct permissions to access the file or directory.	Obtain the proper permissions.

```
cachefspack: filename - can't unpack file: no such file or directory
```

Reason Error Occurred	How to Fix the Problem
You may not have the correct file or directory.	Check for a possible typo.

```
cachefspack: filename - can't unpack file: stale NFS file handle
```

Reason Error Occurred	How to Fix the Problem
The file or directory may have been moved or deleted from the server at the time you attempted to access it.	Check with your system administrator.

```
cachefspack: filename - can't unpack file: interrupted system call
```

Reason Error Occurred	How to Fix the Problem
You may have issued Control-c during the process of using the command.	Reissue the command.

```
cachefspack: filename - can't unpack file I/O error
```

**Reason Error Occurred**

A hardware problem.

**How to Fix the Problem**

Check your hardware connections.

```
cachefspack: only one 'd', 'i', 'p', or 'u' option allowed
```

**Reason Error Occurred**

You entered more than one of the above options in a command session.

**How to Fix the Problem**

Select one option for the command session.

```
cachefspack: can't find environment variable.
```

**Reason Error Occurred**

You forgot to set a corresponding environment variable to match the \$ in your configuration file.

**How to Fix the Problem**

Define the environment variable in the proper location.

```
cachefspack: skipping LIST command - no active base
```

**Reason Error Occurred**

A LIST command is present in your configuration file that has no corresponding BASE command.

**How to Fix the Problem**

Define the BASE command.

---

## CacheFS Statistics

CacheFS statistics enable you to:

- Determine an appropriate cache size
- Observe the performance of the cache

These two pieces of information will help you determine the trade-off between your cache size and the desired performance of the cache.

The CacheFS statistics consist of three commands:

---

<code>cachefslog</code>	Specifies the location of the log file. This command also displays where the statistics are currently being logged, and enables you to halt logging. See <code>cachefslog(1M)</code> for more information.
<code>cachefswssize</code>	Interprets the log file to give a recommended cache size. See <code>cachefswssize(1M)</code> for more information.
<code>cachefsstat</code>	Displays statistical information about a specific file system or all cached file systems. The information provided in the output of this command is taken directly from the cache. See <code>cachefsstat(1M)</code> for more information.

---



---

**Note** - The CacheFS statistics commands can be issued from any directory. You must be superuser to issue the `cachefswssize(1M)` command.

---

The statistics begin accumulating when you create the log file. When the work session length of time is up, stop the logging by using the `cachefslog -h` command, as described in “How to Stop the Logging Process” on page 476.

---

## Prerequisites for Setting Up and Viewing the CacheFS Statistics

Before using the CacheFS statistics commands, you must:

- Set up your cache using the `cfscadmin(1M)` command.
- Decide on an appropriate length of time to allow statistical information to collect in the log file you create. The length of time should equal a typical work session; for example, a day, a week, or a month.
- Select a location or path for the log file. Make sure there is enough space to allow for the growth of the log file. The longer you intend to allow statistical information to collect in the log file, the more space you will need.

---

**Note** - The following procedures are presented in a recommended order. The order is not required.

---

---

# Setting Up CacheFS Statistics Task Map

Table 29–3 shows the steps involved in setting up CacheFS statistics.

**TABLE 29–3** Setting Up CacheFS Statistics Task Map

Task	Description	For Instructions, Go To
1. Set Up Logging	Set up logging on a cached file system using the <code>cachefslog</code> command.	“How to Set Up the Logging Process” on page 474
2. Locate the Log File	Locate the log file with the <code>cachefslog</code> command.	“How to Locate the Log File” on page 475
3. Stop the Logging Process	Stop the logging process with the <code>cachefslog</code> command.	“How to Stop the Logging Process” on page 476
4. View the Cache Size	View the cache size using the <code>cachefswssize</code> command.	“How to View the Working Set (Cache) Size” on page 476
5. View the Cache Statistics	View the statistics using the <code>cachefsstat</code> command.	“How to View Cache Statistics” on page 478

---

## CacheFS Logging

This section describes how to set up and view CacheFS logging.

### ▼ How to Set Up the Logging Process

1. Set up the logging process with the `cachefslog` command.

```
$ cachefslog -f log-file-path mount-point
```

<code>-f</code>	Sets up the logging process.
<code>log-file-path</code>	Specifies the location of the log file. The log file is a standard file you create with an editor, such as vi.
<code>mount-point</code>	Designates the mount point (cached file system) for which statistics are being collected.

2. Verify that you set up the log file correctly by using the `cachefslog` command, as follows:

```
$ cachefslog mount-point
```

## Example—Setting Up the Logging Process

The following example sets up the log file `samlog` to collect statistics about `/home/sam`. The location of `samlog` is `/var/tmp/samlog`.

```
$ cachefslog -f /var/tmp/samlog /home/sam
/var/tmp/samlog: /home/sam
```

## How to Locate the Log File

You can also use the `cachefslog(1M)` command with no options to locate a log file for a particular mount point.

```
$ cachefslog mount-point
```

<code>mount-point</code>	Specifies the cached file system for which you want to view the statistics.
--------------------------	---

## Examples—Locating the Log File

The following example shows what you would see if a log file has been set up. The location of the log file is `/var/tmp/stufflog`.

```
$ cacheofslog /home/stuff
/var/tmp/stufflog: /home/stuff
```

The following example shows that no log file has been set up for the specified file system.

```
$ cacheofslog /home/zap
not logged: /home/zap
```

## How to Stop the Logging Process

Use the `-h` option of the `cacheofslog(1M)` command to stop the logging process.

```
$ cacheofslog -h mount-point
```

### Example—Stopping the Logging Process

The following example halts logging on `/home/stuff`.

```
$ cacheofslog -h /home/stuff
not logged: /home/stuff
```

If you get a system response other than the one specified in the above example, you did not successfully stop the logging process. Check to see if you are using the correct log file name and mount point.

---

## Viewing the Cache Size

You may want to check if you need to increase the size of the cache or determine what the ideal cache size is based on your activity since you last used the `cacheofslog(1M)` command for a particular mount point.

### ▼ How to View the Working Set (Cache) Size

1. **Become superuser.**
2. **View the current and highest logged cache size with the `cacheofswssize(1M)` command.**

```
# cacheofswssize log-file-path
```

## Example—Viewing the Working Set (Cache) Size

In the following example, the end size is the size of the cache at the time you issued the `cachefswssize` command. The high water size is the largest size of the cache during the time frame in which logging has occurred.

```
# cachefswssize /var/tmp/samlog

/home/sam
    end size: 10688k
high water size: 10704k

/
    end size: 1736k
high water size: 1736k

/opt
    end size: 128k
high water size: 128k

/nfs/saturn.dist
    end size: 1472k
high water size: 1472k

/usr/openwin
    end size: 7168k
high water size: 7168k

/nfs/venus.svr4
    end size: 4688k
high water size: 5000k

/usr
    end size: 4992k
high water size: 4992k

total for cache
initial size: 110960k
    end size: 30872k
high water size: 30872k
```

---

## Viewing the Statistics

You may want to view certain information about a specific cached file system. The following table explains the terminology displayed in the statistics output.

**TABLE 29-4** Statistics Output Terminology

Output Term	Description
hit rate	The rate of cache hits versus cache misses, followed by the actual number of hits and misses. A cache hit occurs when the user wants to perform an operation on a file or files, and the file or files are actually in the cache. A cache miss occurs when the file was not in the cache. The load on the server is the sum of cache misses, consistency checks, and modifications (modifies).
checks	The number of consistency checks performed, followed by the number that passed, and the number that failed.
modifies	The number of modify operations; for example, writes or creates.

## ▼ How to View Cache Statistics

View the statistics with the **cachefsstat(1M)** command. You can do this at any time. For example, you do not have to set up logging in order to view the statistics.

```
$ cachefsstat mount-point
```

*mount-point*

Specifies the cached file system for which you want to view the statistics.

If you do not specify the mount point, statistics for all mounted CacheFS file systems will be displayed.

## Example—Viewing Cache Statistics

```
$ cachefsstat /home/sam
  cache hit rate: 73% (1234 hits, 450 misses)
consistency checks: 700 (650 pass, 50 fail)
      modifies: 321
garbage collection: 0
```



## The Cache Structure and Behavior

Each cache has a set of parameters that determines how it behaves and its structure. The parameters are set to default values which are listed in Table 29–5. The default values specify that the entire front file system is used for caching, which is the recommended method of caching file systems.

**TABLE 29–5** Cache Parameters and Their Default Values

Cache Parameter	Default Value	Definition
maxblocks	90%	Sets the maximum number of blocks that CacheFS is allowed to claim within the front file system.
minblocks	0%	Sets the minimum number of blocks that CacheFS is allowed to claim within the front file system.
threshblocks	85%	Sets the number of blocks that must be available in the front file system before CacheFS can claim more than the blocks specified by minblocks.
maxfiles	90%	Sets the maximum number of available inodes (number of files) that CacheFS is allowed to claim within the front file system.
minfiles	0%	Sets the minimum number of available inodes (number of files) that CacheFS is allowed to claim within the front file system.
threshfiles	85%	Sets the number of inodes (number of files) that must be available in the front file system before CacheFS can claim more than the files specified in minfiles.

Typically, you should not change any of these parameter values. They are set to default values to achieve optimal cache behavior. However, you may want to modify the `maxblocks` and `maxfiles` settings if you have some room in the front file system that is not used by the cache, and you wish to use it for some other file system. You do this using the `cfsadmin(1M)` command. For example:

```
$ cfsadmin -o maxblocks=60
```

---

## Consistency Checking of Cached File Systems With the Back File System

To ensure that the cached directories and files are kept up to date, CacheFS periodically checks consistency of files stored in the cache. To check consistency, CacheFS compares the current modification time to the previous modification time. If the modification times are different, all data and attributes for the directory or file are purged from the cache and new data and attributes are retrieved from the back file system.

When a user requests an operation on a directory or file, CacheFS checks if it is time to verify consistency. If it is, CacheFS obtains the modification time from the back file system and performs the comparison.

### Consistency Checking on Demand

By specifying the `demandconst` option of the `mount(1M)` command, consistency checks can be performed only when you explicitly request them for file systems mounted with this option. After specifying the `demandconst` option when you mount a file system in a cache, you use the `cfsadmin(1M)` command with the `-s` option to request a consistency check. By default, consistency checking is performed file by file as the files are accessed. If no files are accessed, no checks are performed. Use of the `demandconst` option will avoid the situation where the network is flooded with consistency checks. For more information about consistency checking on demand, refer to the `cfsadmin` command.

## Configuring Additional Swap Space (Tasks)

---

This is a list of the overview conceptual information and step-by-step instructions in this chapter.

- “Swap Space and Virtual Memory” on page 482
- “Swap Space and the TMPFS File System” on page 483
- “How Do I Know If I Need More Swap Space?” on page 483
- “How Swap Space Is Allocated” on page 484
- “Planning for Swap Space” on page 485
- “Monitoring Swap Resources” on page 486
- “Adding More Swap Space” on page 487
- “Removing a Swap File From Use” on page 489

---

## About Swap Space

This section provides a conceptual overview of swap space and briefly discusses the differences between the SunOS 4.0/4.1 and the SunOS 5.7 swap requirements. If you are already familiar with the SunOS 5.7 swap mechanism, proceed to the section called “Planning for Swap Space” on page 485.

It is important for administrators to understand the features of the SunOS 5.7 swap mechanism in determining:

- Swap space requirements
- The relationship with the TMPFS file system

- Recovery from error messages related to swap space

## Swap Space and Virtual Memory

The SunOS 5.7 system software uses some disk slices for temporary storage rather than for file systems. These slices are called *swap* slices. Swap slices are used as virtual memory storage areas when the system does not have enough physical memory to handle current processes.

The SunOS 5.7 virtual memory system maps physical copies of files on disk to virtual addresses in memory. Physical memory pages which contain the data for these mappings can be backed by regular files in the file system, or by swap space. If the memory is backed by swap space it is referred to as *anonymous* memory because the user doesn't know the names of the files backing the memory.

SunOS 4.0/4.1 anonymous memory pages are mapped using randomly assigned names from the system's swap space pool. These memory pages are used for:

- Private copies of data created during copy-on-write operations
- Process and stack segments
- The TMPFS file system storage resources

The limitations of the SunOS 4.0/4.1 anonymous memory implementation are:

- Physical storage (disk-backed swap) must always be reserved for anonymous memory mappings even if the application doesn't use it.

For example, applications with large data segments must be configured with lots of swap space even if the pages are not written out to physical storage.

- The formula used to associate an anonymous memory page with physical storage is limited and inflexible because the backing store is chosen at random and can never be changed.

The SunOS 5.7 software environment introduces the concept of *virtual swap space*, a layer between anonymous memory pages and the physical storage (or disk-backed swap space) that actually back these pages. A system's virtual swap space is equal to the sum of all its physical (disk-backed) swap space plus a portion of the currently available physical memory.

Virtual swap space has these advantages:

- The need for large amounts of physical swap space is reduced because virtual swap space does not necessarily correspond to physical (disk) storage.
- A pseudo file system called SWAPFS provides addresses for anonymous memory pages. Because SWAPFS controls the allocation of memory pages, it has greater flexibility in deciding what happens to a page. For example, it may change the page's requirements for disk-backed swap storage.

## Swap Space and the TMPFS File System

The TMPFS file system is activated automatically in the SunOS 5.7 environment by an entry in the `/etc/vfstab` file. The TMPFS file system stores files and their associated information in memory (in the `/tmp` directory) rather than on disk, which speeds access to those files. This results in a major performance enhancement for applications such as compilers and DBMS products that use `/tmp` heavily.

The TMPFS file system allocates space in the `/tmp` directory from the system's swap resources. This means that as you use up space in `/tmp`, you are also using up swap space. So if your applications use `/tmp` heavily and you do not monitor swap space usage, your system could run out of swap space.

Use the following if you want to use TMPFS but your swap resources are limited:

- Mount the TMPFS file system with the size option (`-o size`) to control how much of the swap resources TMPFS can use.
- If you are close to running out of swap space, you can use your compiler's `TMPDIR` environment variable to point to a larger temporary directory.

Using your compiler's `TMPDIR` variable only controls whether the compiler is using `/tmp` or not. It has no effect on other programs' use of `/tmp`.

---

## How Do I Know If I Need More Swap Space?

This section lists several possible error messages displayed when you run out of swap space.

### Swap-Related Error Messages

These messages indicate that an application was trying to get more anonymous memory and there was no swap space left to back it.

```
application is out of memory  
malloc error 0  
WARNING: Sorry, no swap space to grow stack for pid
```

## TMPFS-Related Error Messages

```
directory: File system full, swap space limit exceeded
```

This message is displayed if a page could not be allocated when writing a file. This can occur when TMPFS tries to write more than it is allowed or if currently executed programs are using a lot of memory.

```
directory: File system full, memory allocation failed
```

This messages means TMPFS ran out of physical memory while attempting to create a new file or directory.

See **TMPFS(7FS)** for information on recovering from the TMPFS-related error messages.

---

## How Swap Space Is Allocated

Initially, swap space is allocated as part of the Solaris installation process. If you use the installation program's automatic layout of disk slices and do not manually change the size of the swap slice, the Solaris installation program allocates default swap slices as shown in Table 30-1.

**TABLE 30-1** Default Swap Space Allocations

If Your System Has <i>n</i> Mbytes of Physical Memory ...	Then the Default Swap Space Allocated Is ...
16-64	32 Mbytes
64-128	64 Mbytes
128-512	128 Mbytes
greater than 512	256 Mbytes

## The `/etc/vfstab` File

After the system is installed, swap slices and files are listed in the `/etc/vfstab` file and are activated by the `/sbin/swapadd` script when the system is booted.

An entry for a swap device in the `/etc/vfstab` file contains:

- The full path name of the swap slice or file
- File system type of swap

Because the file system containing a swap file must be mounted before the swap file is activated, make sure that the entry that mounts the file system comes before the entry that activates the swap file in the `/etc/vfstab` file.

---

## Planning for Swap Space

The most important factors in determining swap space size are the requirements of the system's software applications. For example, large applications such as computer-aided-design simulators, database-management products, transaction monitors, and geologic analysis systems can consume as much as 200-1000 Mbytes of swap space in very large memory systems.

Consult your application vendor for swap space requirements for any application whose data files typically exceed 10-20 Mbytes in size.

If you are unable to determine swap space requirements from the application vendor, use the following guidelines to allocate swap space:

- To support your applications, allocate:
  - 1 Mbyte per trivial application such as `xterm`.
  - 2-3 Mbytes per lightweight application such as a calendar or mail application.
  - 20-50 Mbytes for large applications such as desktop publishing software.
- To save crash dumps, allocate 100% of physical memory to save a worst-case crash dump.
- If you are unsure of system or application requirements, allocate 50 to 100% of the system's physical memory. For example, allocate 16-32 Mbytes of swap space for a system with 32 Mbytes of physical memory. This will provide 48-64 Mbytes of total virtual swap space.
- Determine whether large applications (like compilers) will be using the `/tmp` directory. Then allocate additional swap space to be used by TMPFS. See "Swap Space and the TMPFS File System" on page 483 for information about TMPFS.

---

## Monitoring Swap Resources

The `/usr/sbin/swap` command is used to manage swap areas. Two options, `-l` and `-s`, are used to display information about swap resources.

Use the `swap -l` command to identify a system's swap areas. Activated swap devices or files are listed under the `swapfile` column.

```
# swap -l
swapfile          dev  swaplo blocks   free
/dev/dsk/c0t2d0s1 32,17      8 205624 192704
```

Use the `swap -s` command to monitor swap resources.

```
# swap -s
total: 10492k bytes allocated + 7840k reserved = 18332k used, 21568k available
```

The `used` plus `available` figures equals total swap space on the system, which includes a portion of physical memory and swap devices (or files).

You can use the amount of swap space available and used (in the `swap -s` output) as a way to monitor swap space usage over time. If a system's performance is good, use `swap -s` to see how much swap space is available. When the performance of a system slows down, check the amount of swap space available to see if it has decreased. Then you can identify what changes to the system might have caused swap space usage to increase.

Keep in mind when using this command that the amount of physical memory available for swap usage changes dynamically as the kernel and user processes lock down and release physical memory.

---

**Note** - The `swap -l` command displays swap space in 512-byte blocks and the `swap -s` command displays swap space in 1024-byte blocks. If you add up the blocks from `swap -l` and convert them to Kbytes, it will be less than `used + available` (in the `swap -s` output) because `swap -l` does not include physical memory in its calculation of swap space.

---

The output from the `swap -s` command is summarized in Table 30-2.



**TABLE 30-2** Output of the `swap -s` Command

Keyword	Description
bytes allocated	The total amount of swap space in 1024-byte blocks that is currently allocated as backing store (disk-backed swap space).
reserved	The total amount of swap space in 1024-byte blocks not currently allocated, but claimed by memory for possible future use.
used	The total amount of swap space in 1024-byte blocks that is either allocated or reserved.
available	The total amount of swap space in 1024-byte blocks that is currently available for future reservation and allocation.

## Adding More Swap Space

As system configurations change and new software packages are installed, you might need to add more swap space. The preferred way to add more swap space is to use the `mkfile` and `swap` commands to designate a part of an existing UFS or NFS file system as a supplementary swap area. These commands, described below, enable you to add more swap space without repartitioning a disk.

An alternative way to add more swap space is to repartition a disk. See Chapter 21 for information on how to repartition a disk.

## Creating a Swap File

The following general steps are involved in creating a swap file:

- Creating a swap file using the `mkfile` command.
- Activating the swap file with the `swap` command.
- Adding an entry for the swap file in the `/etc/vfstab` file so that it's activated automatically when the system is booted.

# The mkfile Command

The `mkfile` command creates a file that is suitable for use either as an NFS-mounted or local swap area. The sticky bit is set, and the file is padded with zeros. You can specify the size of the swap file in bytes (the default) or in kilobytes, blocks, or megabytes using the `k`, `b`, or `m` suffixes, respectively.

Table 30-3 shows the options to the `mkfile` command.

TABLE 30-3 Options to the `mkfile` Command

Option	Description
<code>-n</code>	Creates an empty file. The size is noted, but the disk blocks are not allocated until data is written to them.
<code>-v</code>	Verbose. Reports the names and sizes of created files.



**Caution** - Use the `-n` option only when creating an NFS swap file.

## ▼ How to Create a Swap File and Make It Available

### 1. Become superuser.

You can create a swap file without root permissions, but it is a good idea for root to be the owner of the swap file to avoid accidental overwriting.

### 2. Create the swap file.

```
# mkfile nnn[k|b|m] filename
```

The swap file of the size `nnn` (in Kbytes, bytes, or Mbytes) and name you specify is created.

### 3. Activate the swap file.

```
# /usr/sbin/swap -a /path/filename
```

You must use the absolute path name to specify the swap file. The swap file is added and available until the file system is unmounted or the system is rebooted.

### 4. Add an entry for the swap file to the `/etc/vfstab` file that specifies the full path name of the file, and designates `swap` as the file system type, like this:

```
/path/filename - - swap - no -
```

5. Verify that the swap file is added.

```
/usr/sbin/swap -l
```

## Example—Creating a Swap File and Making It Available

The following examples shows how to create a 24 Mbyte swap file called /files/swapfile.

```
# mkdir /files
# mkfile 24m /files/swapfile
# swap -a /files/swapfile
# vi /etc/vfstab
(An entry is added for the swap file):
/files/swapfile - - swap - no -
# swap -l
swapfile          dev  swaplo blocks  free
/dev/dsk/c0t2d0s1 32,17    8 205624 192704
/files/swapfile   -      8 40952  40952
```

---

## Removing a Swap File From Use

If the user no longer needs the extra swap space, you can remove it.

### ▼ How to Remove Extra Swap Space

1. Become superuser.
2. Use the `swap -d` command to remove swap space.

```
# /usr/sbin/swap -d /path/filename
```

The swap file name is removed from the list so that it is no longer available for swapping. The file itself is not deleted.

3. Edit the `/etc/vfstab` file and delete the entry for the swap file.

#### 4. Recover the disk space so that you can use it for something else.

```
# rm swap-filename
```

If the swap space is a file, remove it. Or, if the swap space is on a separate slice and you are sure you will not need it again, make a new file system and mount the file system.

See Chapter 28 for more information.

### Example—Removing Extra Swap Space

The following examples shows how to delete the `/files/swapfile` swap file.

```
# swap -d /files/swapfile  
# swap -l  
swapfile          dev  swaplo  blocks  free  
/dev/dsk/c0t2d0s1 32,17    8  205624 192720
```

## Checking File System Integrity

---

This is a list of the conceptual information and step-by-step instructions in this chapter.

- “Understanding How the File System State Is Recorded” on page 492
- “What `fsck` Checks and Tries to Repair” on page 494
- “Modifying Automatic Boot Checking” on page 500
- “Interactively Checking and Repairing a UFS File System” on page 502
- “Restoring a Bad Superblock” on page 505
- “Syntax and Options for the `fsck` Command” on page 507

See “Troubleshooting File System Problems” in *System Administration Guide, Volume II* for information about `fsck` error messages.

The UFS file system relies on an internal set of tables to keep track of inodes used and available blocks. When these internal tables are not properly synchronized with data on a disk, inconsistencies result and file systems need to be repaired.

File systems can be damaged or become inconsistent because of abrupt termination of the operating system in these ways:

- Power failure
- Accidental unplugging of the system
- Turning the system off without proper shutdown procedure
- A software error in the kernel

File system corruption, while serious, is not common. When a system is booted, a file system consistency check is automatically performed (with the `fsck` program). Most of the time, this file system check repairs problems it encounters.

This chapter describes what the `fsck` program checks, and repairs and the `fsck` options. It also describes the following tasks:

- How to modify the automatic checking done during booting
- How to find out if a file system needs to be checked
- How to check and repair a UFS file system interactively
- How to restore a bad superblock
- How to fix a UFS file system that `fsck` cannot repair

The `fsck` error messages are covered in “Troubleshooting File System Problems” in *System Administration Guide, Volume II*.

The `fsck` program places files and directories that are allocated but unreferenced in the `lost+found` directory. The inode number of each file is assigned as the name. If the `lost+found` directory does not exist, `fsck` creates it. If there is not enough space in the `lost+found` directory, `fsck` increases its size.

## Understanding How the File System State Is Recorded

The `fsck` command uses a state flag, which is stored in the superblock, to record the condition of the file system. This flag is used by the `fsck` command to determine whether or not a file system needs to be checked for consistency. The flag is used by the `/sbin/rcS` script during booting and by the `fsck` command when run from a command line using the `-m` option. If you ignore the result from the `-m` option to `fsck`, all file systems can be checked regardless of the setting of the state flag.

The possible state flag values are described in Table 31-1.

TABLE 31-1 State Flag Values

State Flag Value	Description
FSACTIVE	When a file system is mounted and then modified, the state flag is set to FSACTIVE. The file system may contain inconsistencies. A file system will be marked as FSACTIVE before any modified metadata is written to the disk. When a file system is unmounted gracefully, the state flag is set to FSCLEAN. A file system with the FSACTIVE flag must be checked by <code>fsck</code> because it may be inconsistent.
FSBAD	If the root (/) file system is mounted when its state is not FSCLEAN or FSSTABLE, the state flag is set to FSBAD. The kernel will not change this file system state to FSCLEAN or FSSTABLE. If a root (/) file system is flagged FSBAD as part of the boot process, it will be mounted read-only. You can run <code>fsck</code> on the raw root device. Then remount the root (/) file system as read/write.

**TABLE 31-1** State Flag Values *(continued)*

State Flag Value	Description
FSCLEAN	If the file system was unmounted properly, the state flag is set to FSCLEAN. Any file system with an FSCLEAN state flag is not checked when the system is booted.
FSLOG	If the file system was mounted with UFS logging, the state flag is set to FSLOG. Any file system with an FSLOG state flag is not checked when the system is booted.
FSSTABLE	The file system is (or was) mounted but has not changed since the last checkpoint ( <code>sync</code> or <code>fsflush</code> ) which normally occurs every 30 seconds. For example, the kernel periodically checks if a file system is idle and, if so, flushes the information in the superblock back to the disk and marks it FSSTABLE. If the system crashes, the file system structure is stable, but users may lose a small amount of data. File systems that are marked FSSTABLE can skip the checking before mounting. The <code>mount(2)</code> system call will not mount a file system for read/write if the file system state is not FSCLEAN or FSSTABLE.

Table 31-2 shows how the state flag is modified by the `fsck` command, based on its initial state.

**TABLE 31-2** How the State Flag is Modified by `fsck`

Initial State: Before <code>fsck</code>	State After <code>fsck</code>		
	No Errors	All Errors Corrected	Uncorrected Errors
unknown	FSSTABLE	FSSTABLE	unknown
FSACTIVE	FSSTABLE	FSSTABLE	FSACTIVE
FSSTABLE	FSSTABLE	FSSTABLE	FSACTIVE
FSCLEAN	FSCLEAN	FSSTABLE	FSACTIVE
FSBAD	FSSTABLE	FSSTABLE	FSBAD
FSLOG	FSLOG	FSLOG	FSLOG

TABLE 31-2 How the State Flag is Modified by `fsck` (continued)

---

## What `fsck` Checks and Tries to Repair

This section describes what happens in the normal operation of a file system, what can go wrong, what problems `fsck` (the checking and repair utility) looks for, and how it corrects the inconsistencies it finds.

### Why Inconsistencies May Occur

Every working day hundreds of files may be created, modified, and removed. Each time a file is modified, the operating system performs a series of file system updates. These updates, when written to the disk reliably, yield a consistent file system.

When a user program does an operation to change the file system, such as a write, the data to be written is first copied into an internal in-core buffer in the kernel. Normally, the disk update is handled asynchronously; the user process is allowed to proceed even though the data write may not happen until long after the write system call has returned. Thus at any given time, the file system, as it resides on the disk, lags behind the state of the file system represented by the in-core information.

The disk information is updated to reflect the in-core information when the buffer is required for another use or when the kernel automatically runs the `fsflush` daemon (at 30-second intervals). If the system is halted without writing out the in-core information, the file system on the disk will be in an inconsistent state.

A file system can develop inconsistencies in several ways. The most common causes are operator error and hardware failures.

Problems may result from an *unclean halt*, if a system is shut down improperly, or when a mounted file system is taken offline improperly. To prevent unclean halts, the current state of the file systems must be written to disk (that is, “synchronized”) before halting the CPU, physically taking a disk pack out of a drive, or taking a disk offline.

Inconsistencies can also result from defective hardware. Blocks can become damaged on a disk drive at any time, or a disk controller can stop functioning correctly.



## The UFS Components That Are Checked for Consistency

This section describes the kinds of consistency checks the `fsck` applies to these UFS file system components: superblock, cylinder group blocks, inodes, indirect blocks, and data blocks.

### Superblock

The superblock stores summary information, which is the most commonly corrupted item in a UFS file system. Each change to the file system inodes or data blocks also modifies the superblock. If the CPU is halted and the last command is not a sync command, the superblock will almost certainly be corrupted.

The superblock is checked for inconsistencies in:

- File system size
- Number of inodes
- Free-block count
- Free-inode count

### *File System and Inode List Size*

The file system size must be larger than the number of blocks used by the superblock and the number of blocks used by the list of inodes. The number of inodes must be less than the maximum number allowed for the file system. The file system size and layout information are the most critical pieces of information for `fsck`. Although there is no way to actually check these sizes, because they are statically determined when the file system is created, `fsck` can check that the sizes are within reasonable bounds. All other file system checks require that these sizes be correct. If `fsck` detects corruption in the static parameters of the primary superblock, it requests the operator to specify the location of an alternate superblock.

### *Free Blocks*

Free blocks are stored in the cylinder group block maps. `fsck` checks that all the blocks marked as free are not claimed by any files. When all the blocks have been accounted for, `fsck` checks to see if the number of free blocks plus the number of blocks claimed by the inodes equal the total number of blocks in the file system. If anything is wrong with the block allocation maps, `fsck` rebuilds them, leaving out blocks already allocated.

The summary information in the superblock contains a count of the total number of free blocks within the file system. The `fsck` program compares this count to the

number of free blocks it finds within the file system. If the counts do not agree, `fsck` replaces the count in the superblock with the actual free-block count.

### *Free Inodes*

The summary information in the superblock contains a count of the free inodes within the file system. The `fsck` program compares this count to the number of free inodes it finds within the file system. If the counts do not agree, `fsck` replaces the count in the superblock with the actual free inode count.

## Inodes

The list of inodes is checked sequentially starting with inode 2 (inode 0 and inode 1 are reserved). Each inode is checked for inconsistencies in:

- Format and type
- Link count
- Duplicate block
- Bad block numbers
- Inode size

### *Format and Type of Inodes*

Each inode contains a mode word, which describes the type and state of the inode. Inodes may be one of six types:

- Regular
- Directory
- Block special
- Character special
- FIFO (named-pipe)
- Symbolic link

Inodes may be in one of three states:

- Allocated
- Unallocated
- Partially allocated

When the file system is created, a fixed number of inodes are set aside, but they are not allocated until they are needed. An allocated inode is one that points to a file. An unallocated inode does not point to a file and, therefore, should be empty. The

partially allocated state means that the inode is incorrectly formatted. An inode can get into this state if, for example, bad data is written into the inode list because of a hardware failure. The only corrective action `fsck` can take is to clear the inode.

### *Link Count*

Each inode contains a count of the number of directory entries linked to it. The `fsck` program verifies the link count of each inode by examining the entire directory structure, starting from the root directory, and calculating an actual link count for each inode.

Discrepancies between the link count stored in the inode and the actual link count as determined by `fsck` may be of three types:

- The stored count is *not* 0 and the actual count is 0.

This condition can occur if no directory entry exists for the inode. In this case, `fsck` puts the disconnected file in the `lost+found` directory.

- The stored count is *not* 0 and the actual count is *not* 0, but the counts are *unequal*.

This condition can occur if a directory entry has been added or removed but the inode has not been updated. In this case, `fsck` replaces the stored link count with the actual link count.

- The stored count is 0 and the actual count is not 0.

In this case `fsck` changes the link count of the inode to the actual count.

### *Duplicate Blocks*

Each inode contains a list, or pointers to lists (indirect blocks), of all the blocks claimed by the inode. Because indirect blocks are owned by an inode, inconsistencies in indirect blocks directly affect the inode that owns the indirect block.

The `fsck` program compares each block number claimed by an inode to a list of allocated blocks. If another inode already claims a block number, the block number is put on a list of duplicate blocks. Otherwise, the list of allocated blocks is updated to include the block number.

If there are any duplicate blocks, `fsck` makes a second pass of the inode list to find the other inode that claims each duplicate block. (A large number of duplicate blocks in an inode may be caused by an indirect block not being written to the file system.) It is not possible to determine with certainty which inode is in error. The `fsck` program prompts you to choose which inode should be kept and which should be cleared.

## *Bad Block Numbers*

The `fsck` program checks each block number claimed by an inode to see that its value is higher than that of the first data block and lower than that of the last data block in the file system. If the block number is outside this range, it is considered a bad block number.

Bad block numbers in an inode may be caused by an indirect block not being written to the file system. The `fsck` program prompts you to clear the inode.

## *Inode Size*

Each inode contains a count of the number of data blocks that it references. The number of actual data blocks is the sum of the allocated data blocks and the indirect blocks. `fsck` computes the number of data blocks and compares that block count against the number of blocks the inode claims. If an inode contains an incorrect count, `fsck` prompts you to fix it.

Each inode contains a 64-bit size field. This field shows the number of characters (data bytes) in the file associated with the inode. A rough check of the consistency of the size field of an inode is done by using the number of characters shown in the size field to calculate how many blocks should be associated with the inode, and then comparing that to the actual number of blocks claimed by the inode.

## Indirect Blocks

Indirect blocks are owned by an inode. Therefore, inconsistencies in an indirect block affect the inode that owns it. Inconsistencies that can be checked are:

- Blocks already claimed by another inode
- Block numbers outside the range of the file system

The consistency checks are also performed for indirect blocks.

## Data Blocks

An inode can directly or indirectly reference three kinds of data blocks. All referenced blocks must be of the same kind. The three types of data blocks are:

- Plain data blocks
- Symbolic-link data blocks
- Directory data blocks

Plain data blocks contain the information stored in a file. Symbolic-link data blocks contain the path name stored in a symbolic link. Directory data blocks contain directory entries. `fsck` can check the validity only of directory data blocks.

Directories are distinguished from regular files by an entry in the `mode` field of the inode. Data blocks associated with a directory contain the directory entries. Directory data blocks are checked for inconsistencies involving:

- Directory inode numbers pointing to unallocated inodes
- Directory inode numbers greater than the number of inodes in the file system
- Incorrect directory inode numbers for “.” and “..” directories
- Directories disconnected from the file system

### *Directory Unallocated*

If the inode number in a directory data block points to an unallocated inode, `fsck` removes the directory entry. This condition can occur if the data blocks containing the directory entries are modified and written out but the inode does not get written out. This condition can occur if the CPU is halted without warning.

### *Bad Inode Number*

If a directory entry inode number points beyond the end of the inode list, `fsck` removes the directory entry. This condition can occur when bad data is written into a directory data block.

### *Incorrect “.” and “..” Entries*

The directory inode number entry for “.” must be the first entry in the directory data block. It must reference itself; that is, its value must be equal to the inode number for the directory data block.

The directory inode number entry for “..” must be the second entry in the directory data block. Its value must be equal to the inode number of the parent directory (or the inode number of itself if the directory is the root directory).

If the directory inode numbers for “.” and “..” are incorrect, `fsck` replaces them with the correct values. If there are multiple hard links to a directory, the first one found is considered the real parent to which “..” should point. In this case, `fsck` recommends you have it delete the other names.

### *Disconnected Directories*

The `fsck` program checks the general connectivity of the file system. If a directory is found that is not linked to the file system, `fsck` links the directory to the `lost+found` directory of the file system. (This condition can occur when inodes are written to the file system but the corresponding directory data blocks are not.)

## Regular Data Blocks

Data blocks associated with a regular file hold the contents of the file. `fsck` does not attempt to check the validity of the contents of a regular file's data blocks.

---

## Modifying Automatic Boot Checking

During boot up, a preliminary check on each file system to be mounted from a hard disk is run using the boot script `/sbin/rcS`, which checks the root (`/`) and `/usr` file systems. The other `rc` shell scripts then use the `fsck` command to check each additional file system sequentially. They do not check file systems in parallel. File systems are checked sequentially during booting even if the `fsck` pass numbers are greater than one.

## The `/etc/vfstab` File

When you run the commands for checking and mounting file systems without specifying a file system directly, the commands step through the file system table (`/etc/vfstab`) using the information specified in the various fields. The `fsck` pass field specifies information for file system checking. The `mount` at boot field specifies information for mounting the file system at boot time.

When you create new file systems, add entries to `/etc/vfstab` indicating whether they are to be checked and mounted at boot time. See Chapter 28 for more information about adding entries to the `/etc/vfstab` file.

Information in the `/etc/vfstab` file is specific for the slices and file systems for each system. Here is an example of an `/etc/vfstab` file:

```
$ more /etc/vfstab
#device      device      mount      FS      fsck      mount      mount
#to mount    to fsck      point
#/dev/dsk/c1d0s2 /dev/rdisk/c1d0s2 /usr      ufs      1      yes      -
/proc        -            /proc      proc      -      no      -
fd           -            /dev/fd     fd        -      no      -
swap         -            /tmp        tmpfs     -      yes     -

/dev/dsk/c0t0d0s0 /dev/rdisk/c0t0d0s0 /      ufs      1      no      -
/dev/dsk/c0t0d0s1 -            -          swap     -      no      -
/dev/dsk/c0t0d0s6 /dev/rdisk/c0t0d0s6 /usr     ufs      2      no      -
/dev/dsk/c0t0d0s7 /dev/rdisk/c0t0d0s7 /opt     ufs      3      yes     -
pluto:/export/svr4/man -      /usr/man   nfs      no      yes     -
$
```

Table 31-3 describes the function of the `fsck pass` field.

**TABLE 31-3** The `fsck pass` Field

If the <code>fsck pass</code> Field is Set To ...	Then ...	Comments
- (hyphen)	The generic <code>fsck</code> command will not check the file system regardless of the state of the file system.	Use a hyphen for read-only file systems, remote file systems, or pseudo file systems, such as <code>/proc</code> , to which checking does not apply.
0 or greater	The file system specific <code>fsck</code> command is called.	When the value is greater for UFS file systems, the file system is not checked.
1 or greater and <code>fsck -op</code> is used	The file system specific <code>fsck</code> automatically checks UFS file systems in parallel.	The value can be any number greater than 1.

In `preen` mode, `fsck` allows only one active file system check per disk, starting a new check only after the previous one is completed. `fsck` automatically uses the major and minor numbers of the devices on which the file systems reside to determine how to check file systems on different disks at the same time.

When the `fsck pass` number is 1, file systems are checked sequentially, in the order they appear in the `/etc/vfstab` file. Usually, the root (`/`) file system has the `fsck pass` set to 1.

---

**Note** - `fsck` does *not* use the `fsck pass` number to determine the sequence of file system checking.

---

## ▼ How to Modify Automatic Checking Done During Booting

1. **Become superuser.**
2. **Edit `/etc/vfstab` entries in the `fsck pass` field, and save the changes.**  
The next time the system is booted, the new values are used.

---

# Interactively Checking and Repairing a UFS File System

You may need to interactively check file systems:

- When they cannot be mounted
- When they develop problems while in use

When an in-use file system develops inconsistencies, error messages may be displayed in the console window or the system may crash.

Before using `fsck`, you may want to refer to “Syntax and Options for the `fsck` Command” on page 507 and “Troubleshooting File System Problems” in *System Administration Guide, Volume II* for more information.

## ▼ How to See If a File System Needs Checking

1. **Become superuser.**
2. **Check the file system.**

```
# fsck -m /dev/rdisk/device-name
```

In this command, the state flag in the superblock of the file system you specify is checked to see whether the file system is clean or requires checking.

If you omit the device argument, all the UFS file systems listed in `/etc/vfstab` with a `fsck pass` value greater than 0 are checked.

## Example—Seeing If a File System Needs Checking

The following example shows that the file system needs checking.

```
# fsck -m /dev/rdisk/c0t0d0s6
** /dev/rdisk/c0t0d0s6
ufs fsck: sanity check: /dev/rdisk/c0t0d0s6 needs checking
```

## ▼ How to Check File Systems Interactively

1. **Become superuser.**



2. **Unmount the local file systems except root (/) and /usr.**

```
# umountall -l
```

3. **Check the file system.**

```
# fsck
```

All file systems in the `/etc/vfstab` file with entries in the `fsck pass` field greater than zero are checked. You can also specify the mount point directory or `/dev/rdisk/device-name` as arguments to `fsck`. Any inconsistency messages are displayed. See “Troubleshooting File System Problems” in *System Administration Guide, Volume II* for information about how to respond to the error message prompts to interactively check one or more UFS file systems.

4. **If you corrected any errors, type `fsck` and press Return.**

`fsck` may not be able to fix all errors in one execution. If you see the message `FILE SYSTEM STATE NOT SET TO OKAY`, run the command again. If that does not work, see “How to Fix a UFS File System `fsck` Cannot Repair” on page 506.

5. **Rename and move any files put in the `lost+found` directory.**

Individual files put in the `lost+found` directory by `fsck` are renamed with their inode numbers. If possible, rename the files and move them where they belong. You may be able to use the `grep` command to match phrases with individual files and the `file` command to identify file types. When whole directories are dumped into `lost+found`, it is easier to figure out where they belong and move them back.

## Example—Checking File Systems Interactively

The following example checks `/dev/rdisk/c0t0d0s6` and corrects the incorrect block count.

```
# fsck /dev/rdisk/c0t0d0s6
checkfilesystem: /dev/rdisk/c0t0d0s6
** Phase 1 - Check Block and Sizes
INCORRECT BLOCK COUNT I=2529 (6 should be 2)
CORRECT? y

** Phase 2 - Check Pathnames
** Phase 3 - Check Connectivity
** Phase 4 - Check Reference Counts
** Phase 5 - Cylinder Groups
929 files, 8928 used, 2851 free (75 frags, 347 blocks, 0.6%
```

(continued)

(Continuation)

```
fragmentation)
/dev/rdisk/c0t0d0s6 FILE SYSTEM STATE SET TO OKAY
***** FILE SYSTEM WAS MODIFIED *****
```

## Preening UFS File Systems

The `preen` option to `fsck` (`fsck -o p`) checks UFS file systems and automatically fixes the simple problems that normally result from an unexpected system halt. It exits immediately if it encounters a problem that requires operator intervention. The `preen` option also permits parallel checking of file systems.

You can run `fsck` with the `-o p` option to preen the file systems after an unclean halt. In this mode, `fsck` does not look at the clean flag and does a full check. These actions are a subset of the actions that `fsck` takes when it runs interactively.

### ▼ How to Preen a File System

1. **Become superuser.**
2. **Unmount the file system.**

```
# umount mount-point
```

3. **Check a UFS file system with the `preen` option.**

```
# fsck -o p /dev/rdsk/device-name
```

You can preen individual file systems by using *mount-point* or */dev/rdsk/device-name* as arguments to `fsck`.

### Example—Preening a File System

The following example preens the `/usr` file system.

```
# fsck -o p /usr
```

---

# Restoring a Bad Superblock

When the superblock of a file system becomes damaged, you must restore it. `fsck` tells you when a superblock is bad. Fortunately, redundant copies of the superblock are stored within a file system. You can use `fsck -o b` to replace the superblock with one of the copies.

## ▼ How to Restore a Bad Superblock

1. **Become superuser.**
2. **Change to a directory outside the damaged file system.**
3. **Unmount the file system.**

```
# umount mount-point
```



---

**Caution** - Be sure to use the `-N` option with `newfs` in the next step. If you omit the `-N` option, you will create a new, empty file system.

---

4. **Display the superblock values with the `newfs -N` command.**

```
# newfs -N /dev/rdisk/device-name
```

The output of this command displays the block numbers that were used for the superblock copies when `newfs` created the file system.

5. **Provide an alternative superblock with the `fsck` command.**

```
# fsck -F ufs -o b=block-number /dev/rdisk/device-name
```

`fsck` uses the alternative superblock you specify to restore the primary superblock. You can always try 32 as an alternative block, or use any of the alternative blocks shown by `newfs -N`.

## Example—Restoring a Bad Superblock

The following example restores the superblock copy 5264 for the `/files7` file system:

```

# cd /
# umount /files7
# newfs -N /dev/rdisk/c0t3d0s7
/dev/rdisk/c0t3d0s7: 163944 sectors in 506 cylinders of 9 tracks, 36 sectors
83.9MB in 32 cyl groups (16 c/g, 2.65MB/g, 1216 i/g)
super-block backups (for fsck -b #) at:
32, 5264, 10496, 15728, 20960, 26192, 31424, 36656, 41888,
47120, 52352, 57584, 62816, 68048, 73280, 78512, 82976, 88208,
93440, 98672, 103904, 109136, 114368, 119600, 124832, 130064, 135296,
140528, 145760, 150992, 156224, 161456,
# fsck -F ufs -o b=5264 /dev/rdisk/c0t3d0s7
Alternate superblock location: 5264.
** /dev/rdisk/c0t3d0s7
** Last Mounted on
** Phase 1 - Check Blocks and Sizes
** Phase 2 - Check Pathnames
** Phase 3 - Check Connectivity
** Phase 4 - Check Reference Counts
** Phase 5 - Check Cyl groups
36 files, 867 used, 75712 free (16 frags, 9462 blocks, 0.0% fragmentation)
/dev/rdisk/c0t3d0s7 FILE SYSTEM STATE SET TO OKAY

***** FILE SYSTEM WAS MODIFIED *****
#

```

If the superblock in the root (/) file system becomes damaged and you cannot boot the system, reinstall `/kernel/unix` and rebuild the root (/) file system with `newfs`. Because a superblock is created by the `newfs` command, you do not need to restore it.

## How to Fix a UFS File System `fsck` Cannot Repair

Sometimes you need to run `fsck` a few times to fix a file system because problems corrected on one pass may uncover other problems not found in earlier passes. `fsck` does not keep running until it comes up clean, so you must rerun it manually.

Pay attention to the information displayed by `fsck`. It may help you fix the problem. For example, the messages may point to a bad directory. If you delete the directory, you may find that `fsck` runs cleanly.

If `fsck` still cannot repair the file system, you can try to use the `fsdb`, `ff`, `clri`, and `ncheck` commands to figure out and fix what is wrong. See `fsdb(1M)`, `ff(1M)`, `clri(1M)`, and `ncheck(1M)` for information about how to use these commands. You may, ultimately, need to re-create the file system and restore its contents from backup media. See Chapter 35 for information about restoring complete file systems.

If you cannot fully repair a file system but you can mount it read-only, try using `cp`, `tar`, or `cpio` to retrieve all or part of the data from the file system.

If hardware disk errors are causing the problem, you may need to reformat and divide the disk into slices again before re-creating and restoring file systems.

Hardware errors usually display the same error again and again across different commands. The `format` command tries to work around bad blocks on the disk. If the disk is too severely damaged, however, the problems may persist, even after reformatting. See `format(1M)` for information about using the `format` command. See Chapter 23 or Chapter 24 for information about installing a new disk.

---

## Syntax and Options for the `fsck` Command

The `fsck` command checks and repairs inconsistencies in file systems. It has four options:

- Checks only whether a file system can be mounted (`fsck -m`)
- Interactively asks for confirmation before making repairs (`fsck`)
- Assumes yes or no response for all repairs (`fsck -y`)
- Noninteractively preens the file system, fixing all expected (innocuous) inconsistencies, but exiting when a serious problem is encountered (`fsck -o p`)

## Generic `fsck` Command Syntax, Options, and Arguments

The `fsck` command has two components: a generic component and a component specific to each type of file system. The generic commands apply to most types of file systems, while the specific commands apply to only one type of file system. You should always use the generic command, which calls the file system-specific command, as needed.

Usually, you must be superuser to run `fsck`. You can run the `fsck` command without being superuser; but to make repairs, you should unmount the file system and you must have read permission for the raw device file for the slice (a potential security hole).

The generic `fsck` command goes through `/etc/vfstab` to see what file systems to check. It runs the appropriate file system-specific `fsck` command on each file system listed, except those excluded by an `fsck` pass number of `-` or `0` (UFS only).

The generic `fsck` command has the following syntax:

```
/usr/sbin/fsck [-F type] [-V] [-m] [special]  
/usr/sbin/fsck [-F type] [-V] [-y|Y|n|N] [-o specific-options][special]
```

Table 31-4 describes the options and arguments to the generic `fsck` command.

**TABLE 31-4** The `fsck` Command Options and Arguments

Option Type	Option	Description
Generic	<code>-F</code>	Specifies the file system type ( <i>type</i> ). If <i>type</i> is not specified on the command line, it is obtained from <code>/etc/vfstab</code> by matching an entry in that file with the special device name specified. If no entry is found, the default local file system type specified in <code>/etc/default/fs</code> is used.
	<code>-V</code>	Echoes the completed command line (verbose). The echoed line includes additional information derived from <code>/etc/vfstab</code> . This option can be used to verify and validate the command line. It does not execute the command.
	<code>-m</code>	Performs a preliminary check only. It returns a code indicating the state of the file system: 0 for “clean” and 32 for “dirty.” This option is used by the startup script <code>/sbin/rcS</code> to determine whether a file system needs to be checked.
	<code>-Y</code> or <code>-Yor -n</code> or <code>-N</code>	Runs the command automatically answering yes or no to all prompts.
	<code>c</code>	Converts an old format file system with statically allocated tables to new format dynamically allocated tables. Static allocation imposes a hard maximum on table size, while dynamic allocation means space for tables can be added as needed after the initial allocation. If the file system is in the new format, convert it to the old format, unless the table allocation exceeds the fixed maximum allowed in the old format. <code>fsck</code> lists the direction of the conversion. In interactive mode, <code>fsck</code> prompts for confirmation before doing the conversion. When you use the <code>-o p</code> option, the conversion is attempted without asking for confirmation. This option is useful when you want to convert a number of file systems at once. You can determine whether a file system is in the old or new format by running the <code>fstyp</code> command, and looking at the first line displayed.
	<code>w</code>	Checks only file systems that permit write access.

**TABLE 31-4** The `fsck` Command Options and Arguments *(continued)*

Option Type	Option	Description
Specific	<i>special</i>	Specifies the mount point or raw device name of one or more file systems. An entry for the mount point must exist in <code>/etc/vfstab</code> . If you omit the <i>special</i> argument, entries in <code>/etc/vfstab</code> with a specified <code>fsck</code> device and a <code>fsck pass</code> number greater than zero are checked. If preening ( <code>-o p</code> ) is in effect and more than one entry has an <code>fsck pass</code> number greater than 1, file systems on different disks are checked in parallel.
		This is a comma-separated list of options that follow the <code>-o</code> option. Describes the options that are passed to the UFS-specific <code>fsck</code> command for interpretation.
	<code>p</code>	Preens. Runs the command automatically in silent mode, correcting what it can, but exiting when it encounters a problem that requires intervention. This option also enables parallel checking of UFS file systems.
	<code>b=blocknumber</code>	Uses the alternative (redundant) superblock, located at the specified location. This option can be used to repair a bad superblock. You can display a list of alternative superblocks by using the <code>newfs -N</code> command.





## File System Reference

---

This is a list of the reference information in this chapter.

- “Default Directories for root (/) and /usr File Systems” on page 511
- Table 32-2
- “The Structure of UFS File System Cylinder Groups” on page 519
- “Deciding on Custom File System Parameters” on page 522
- “Commands for Creating a Customized File System” on page 525

---

### Default Directories for root (/) and /usr File Systems

Starting with the Solaris 2.5 release, kernel modules and commands that are platform dependent have moved to new locations. The /kernel directory now contains only platform-independent objects, including a platform-independent kernel, `genunix`. See Table 32-2 for a description of /platform and /usr/platform, the platform-dependent directories.

Table 32-1 describes all the directories contained in the default root (/) and /usr file systems.

**TABLE 32-1** Default Directories for root (/) and /usr File Systems

Directory	Description
Directories in the root (/) file system:	
/	Root of the overall file system name space
/dev	Primary location for special files
/dev/dsk	Block disk devices
/dev/pts	pty slave devices
/dev/rdisk	Raw disk devices
/dev/rmt	Raw tape devices
/dev/sad	Entry points for the STREAMS Administrative Driver
/dev/term	Terminal devices
/etc	Host-specific system administrative configuration files and databases
/etc/acct	Accounting system configuration information
/etc/cron.d	Configuration information for cron
/etc/default	Defaults information for various programs
/etc/dfs	Configuration information for exported file systems
/etc/fs	Binaries organized by file system types for operations required before /usr is mounted.
/etc/inet	Configuration files for Internet services
/etc/init.d	Scripts for changing between run levels
/etc/lp	Configuration information for the printer subsystem
/etc/mail	Mail subsystem configuration

**TABLE 32-1** Default Directories for root (/) and /usr File Systems *(continued)*

Directory	Description
/etc/net	Configuration information for TI (transport- independent) network services
/etc/opt	Configuration information for optional packages
/etc/rc0.d	Scripts for entering/leaving run level 0
/etc/rc1.d	Scripts for entering/leaving run level 1
/etc/rc2.d	Scripts for entering/leaving run level 2
/etc/rc3.d	Scripts for entering/leaving run level 3
/etc/rcS.d	Scripts for bringing the system up in single user mode
/etc/saf	Service access facility files (including FIFOs)
/etc/skel	Default profile scripts for new user accounts
/etc/sm	Status monitor information
/etc/sm.bak	Backup copy of status monitor information
/etc/tm	Trademark files; contents displayed at boot time
/etc/uucp	uucp configuration information
/export	Default root of the exported file system tree
/home	Default root of a subtree for user directories
/kernel	Subtree of platform-independent loadable kernel modules required as part of the boot process. It includes the generic part of the core kernel that is platform independent, /kernel/genunix. See Table 32-2 for the /platform and /usr/platform directory structure.
/mnt	Convenient, temporary mount point for file systems

**TABLE 32-1** Default Directories for root (/) and /usr File Systems *(continued)*

Directory	Description
/opt	Root of a subtree for add-on application packages
/opt/SUNWspro	Mount/installation point for unbundled language products
/sbin	Essential executables used in the booting process and in manual system failure recovery
/stand	Standalone programs
/tmp	Temporary files; cleared during boot sequence
/usr	Mount point for /usr file system
/var	Root of a subtree of varying files
/var/adm	System logging and accounting files
/var/crash	Default depository for kernel crash dumps
/var/cron	cron's log file
/var/lp	Line printer subsystem logging information
/var/mail	Directory where users' mail is kept
/var/news	Community service messages ( <i>note</i> : not the same as USENET-style news)
/var/nis	NIS+ databases
/var/opt	Root of a subtree for varying files associated with software packages
/var/preserve	Backup files for vi and ex
/var/sadm	Databases maintained by the software package management utilities
/var/saf	saf (service access facility) logging and accounting files

**TABLE 32-1** Default Directories for root (/) and /usr File Systems *(continued)*

Directory	Description
/var/spool	Directories for spooled temporary files
/var/spool/cron	cron and at spool files
/var/spool/locks	Spooling lock files
/var/spool/lp	Line printer spool files
/var/spool/mqueue	Mail queued for delivery
/var/spool/pkg	Spooled packages
/var/spool/uucp	Queued uucp jobs
/var/spool/uucppublic	Files deposited by uucp
/var/tmp	Directory for temporary files; not cleared during boot sequence
/var/uucp	uucp log and status files
/var/yp	NIS databases (for backwards compatibility with NIS and unnecessary after full transition to NIS+)
Directories in the /usr file system	
bin	Location for standard system commands
demo	Demo programs and data
games	An empty directory, which is a remnant of the SunOS 4.0/4.1 software
include	Header files (for C programs, etc.)
kernel	Additional modules
kvm	Implementation architecture-specific binaries and libraries

**TABLE 32-1** Default Directories for root (/) and /usr File Systems *(continued)*

Directory	Description
lib	Various program libraries, architecture-dependent databases, and binaries not invoked directly by the user
lib/acct	Accounting scripts and binaries
lib/class	Scheduling class-specific directories containing executables for <code>priocntl</code> and <code>dispadm</code> commands
lib/font	<code>troff</code> font description files
lib/fs	File system type-dependent modules; not invoked directly by the user
lib/iconv	Conversion tables for <code>iconv(1)</code>
lib/libp	Profiled libraries
lib/locale	Internationalization localization databases
lib/lp	Line printer subsystem databases and back-end executables
lib/mail	Auxiliary programs for the <code>mail</code> subsystem
lib/netsvc	Internet network services
lib/nfs	Auxiliary programs and daemons related to NFS
lib/pics	PIC archives needed to build the run-time linker
lib/refer	Auxiliary <code>refer</code> -related programs
lib/sa	Scripts and commands for the system activity report package
lib/saf	Auxiliary programs and daemons related to the service access facility
lib/sparcv9	64-bit Solaris libraries
lib/uucp	Auxiliary <code>uucp</code> -related programs and daemons

**TABLE 32-1** Default Directories for root (/) and /usr File Systems *(continued)*

Directory	Description
lib/zoneinfo	Time zone information
local	Commands local to a site
old	Programs that are being phased out
openwin	Mount/installation point for OpenWindows software
sadm	Various files and directories related to system administration; see specifics below
sadm/bin	"valtools" binaries for use by FMLI scripts
sadm/install	Executables and scripts for pkg management
sbin	Executables for system administration
sbin/static	Statically linked version of selected programs from /usr/bin and /usr/sbin
share	Architecture-independent sharable files
share/lib	Architecture-independent databases
share/lib/keytables	Keyboard layout description tables
share/lib/mailx	mailx-related help files
share/lib/nterm	nroff terminal tables
share/lib/pub	Various data files
share/lib/spell	Auxiliary spell-related databases and scripts
share/lib/tabset	Tab setting escape sequences
share/lib/terminfo	terminfo-style terminal description files

**TABLE 32-1** Default Directories for root (/) and /usr File Systems (continued)

Directory	Description
share/lib/tmac	[nt]roff macro packages
share/src	Source code for kernel, libraries, and utilities
ucb	Berkeley compatibility package binaries
ucbinclude	Berkeley compatibility package header files
ucblib	Berkeley compatibility package libraries

# The Platform-Dependent Directories

Table 32-2 describes the platform-dependent objects in the /platform and /usr/platform directories.

**TABLE 32-2** The /platform and /usr/platform Directories

Directory	Description
/platform	Contains a series of directories, one per supported platform that need to reside in the root (/) file system.
/platform/*/kernel	Contains platform-dependent kernel components, including the file <code>unix</code> , the core kernel that is platform dependent. See <code>kernel(1M)</code> .
/usr/platform	Contains platform-dependent objects that do not need to reside in the root (/) file system. It contains objects which replace the contents of <code>/usr/kvm</code> , which has been removed.
/usr/platform/*/lib	Contains platform-dependent objects similar to those found in the <code>/usr/lib</code> directory.
/platform/*/sbin	Contains platform-dependent objects similar to those found in the <code>/usr/sbin</code> directory.



---

# The Structure of UFS File System

## Cylinder Groups

When you create a UFS file system, the disk slice is divided into *cylinder groups*, which is made up of one or more consecutive disk cylinders. The cylinder groups are then further divided into addressable blocks to control and organize the structure of the files within the cylinder group. Each type of block has a specific function in the file system. A UFS file system has these four types of blocks:

- **Boot block** – Used to store information used when booting the system
- **Superblock** – Used to store much of the information about the file system
- **Inode** – Used to store all information about a file except its name
- **Storage or data block** – Used to store data for each file

This section provides additional information about the organization and function of these blocks.

## The Boot Block

The boot block stores the procedures used in booting the system. If a file system is not to be used for booting, the boot block is left blank. The boot block appears only in the first cylinder group (cylinder group 0) and is the first 8 Kbytes in a slice.

## The Superblock

The superblock stores much of the information about the file system. A few of the more important things it contains are:

- Size and status of the file system
- Label (file system name and volume name)
- Size of the file system logical block
- Date and time of the last update
- Cylinder group size
- Number of data blocks in a cylinder group
- Summary data block
- File system state: clean, stable, or active
- Path name of the last mount point

The superblock is located at the beginning of the disk slice, and is replicated in each cylinder group. Because the superblock contains critical data, multiple superblocks are made when the file system is created. Each of the superblock replicas is offset by a different amount from the beginning of its cylinder group. For multiple-platter disk drives, the offsets are calculated so that a superblock appears on each platter of the drive. That way, if the first platter is lost, an alternate superblock can always be retrieved. Except for the leading blocks in the first cylinder group, the leading blocks created by the offsets are used for data storage.

A summary information block is kept with the superblock. It is not replicated, but is grouped with the first superblock, usually in cylinder group 0. The summary block records changes that take place as the file system is used, and lists the number of inodes, directories, fragments, and storage blocks within the file system.

## Inodes

An inode contains all the information about a file except its name, which is kept in a directory. An inode is 128 bytes. The inode information is kept in the cylinder information block, and contains:

- The type of the file
  - Regular
  - Directory
  - Block special
  - Character special
  - Symbolic link
  - FIFO, also known as named pipe
  - Socket
- The mode of the file (the set of read-write-execute permissions)
- The number of hard links to the file
- The User ID of the owner of the file
- The Group ID to which the file belongs
- The number of bytes in the file
- An array of 15 disk-block addresses
- The date and time the file was last accessed
- The date and time the file was last modified
- The date and time the file was created

The array of 15 disk addresses (0 to 14) point to the data blocks that store the contents of the file. The first 12 are direct addresses; that is, they point directly to the first 12 logical storage blocks of the contents of the file. If the file is larger than 12

logical blocks, the 13th address points to an indirect block, which contains direct block addresses instead of file contents. The 14th address points to a double indirect block, which contains addresses of indirect blocks. The 15th address is for triple indirect addresses, if they are ever needed. Figure 32-1 shows this chaining of address blocks starting from the inode.




Figure 32-1 The File System Address Chain in a UFS System

## Data Blocks

The rest of the space allocated to the file system is occupied by data blocks, also called storage blocks. The size of these data blocks is determined at the time a file system is created. Data blocks are allocated, by default, in two sizes: an 8-Kbyte logical block size, and a 1-Kbyte fragmentation size.

For a regular file, the data blocks contain the contents of the file. For a directory, the data blocks contain entries that give the inode number and the file name of the files in the directory.

## Free Blocks

Blocks not currently being used as inodes, as indirect address blocks, or as storage blocks are marked as free in the cylinder group map. This map also keeps track of fragments to prevent fragmentation from degrading disk performance.

To give you an idea of the appearance of a typical UFS file system, Figure 32-2 shows a series of cylinder groups in a generic UFS file system.




Figure 32-2 A Typical UFS File System

## Deciding on Custom File System Parameters

Before you choose to alter the default file system parameters assigned by the `newfs` command, you need to understand them. This section describes each of these parameters:

- Block size
- Fragment size
- Minimum free space
- Rotational delay
- Optimization type
- Number of files

### Logical Block Size

The logical block size is the size of the blocks that the UNIX kernel uses to read or write files. The logical block size is usually different from the physical block size (usually 512 bytes), which is the size of the smallest block that the disk controller can read or write.

You can specify the logical block size of the file system. After the file system is created, you cannot change this parameter without rebuilding the file system. You can have file systems with different logical block sizes on the same disk.

By default, the logical block size is 8192 bytes (8 Kbytes) for UFS file systems. The UFS file system supports block sizes of 4096 or 8192 bytes (4 or 8 Kbytes). 8 Kbytes is the recommended logical block size.

To choose the best logical block size for your system, consider both the performance desired and the available space. For most UFS systems, an 8-Kbyte file system provides the best performance, offering a good balance between disk performance and use of space in primary memory and on disk.

As a general rule, to increase efficiency, use a larger logical block size for file systems where most of the files are very large. Use a smaller logical block size for file systems where most of the files are very small. You can use the `quot -c file-system` command on a file system to display a complete report on the distribution of files by block size.

## Fragment Size

As files are created or expanded, they are allocated disk space in either full logical blocks or portions of logical blocks called *fragments*. When disk space is needed to hold a data for a file, full blocks are allocated first, and then one or more fragments of a block are allocated for the remainder. For small files, allocation begins with fragments.

The ability to allocate fragments of blocks to files, rather than just whole blocks, saves space by reducing *fragmentation* of disk space resulting from unused holes in blocks.

You define the *fragment size* when you create a UFS file system. The default fragment size is 1 Kbyte. Each block can be divided into 1, 2, 4, or 8 fragments, which results in fragment sizes from 8192 bytes to 512 bytes (for 4-Kbyte file systems only). The lower bound is actually tied to the disk sector size, typically 512 bytes.

---

**Note** - The upper bound may equal the full block size, in which case the fragment is not a fragment at all. This configuration may be optimal for file systems with very large files when you are more concerned with speed than with space.

---

When choosing a fragment size, look at the trade-off between time and space: a small fragment size saves space, but requires more time to allocate. As a general rule, to increase storage efficiency, use a larger fragment size for file systems where most of the files are large. Use a smaller fragment size for file systems where most of the files are small.

## Minimum Free Space

The *minimum free space* is the percentage of the total disk space held in reserve when you create the file system. The default reserve is  $((64 \text{ Mbytes/partition size}) * 100)$ , rounded down to the nearest integer and limited between 1% and 10%, inclusively. Free space is important because file access becomes less and less efficient as a file system gets full. As long as there is an adequate amount of free space, UFS file systems operate efficiently. When a file system becomes full, using up the available user space, only root can access the reserved free space.

Commands such as `df` report the percentage of space that is available to users, excluding the percentage allocated as the minimum free space. When the command reports that more than 100 percent of the disk space in the file system is in use, some of the reserve has been used by root.

If you impose quotas on users, the amount of space available to the users does not include the free space reserve. You can change the value of the minimum free space for an existing file system by using the `tunefs` command.

## Rotational Delay (Gap)

The *rotational delay* is the expected minimum time (in milliseconds) it takes the CPU to complete a data transfer and initiate a new data transfer on the same disk cylinder. The default delay depends on the type of the disk, and is usually optimized for each disk type.

When writing a file, the UFS allocation routines try to position new blocks on the same disk cylinder as the previous block in the same file. The allocation routines also try to optimally position new blocks within tracks to minimize the disk rotation needed to access them.

To position file blocks so they are “rotationally well-behaved,” the allocation routines must know how fast the CPU can service transfers and how long it takes the disk to skip over a block. Using options to the `mkfs` command, you can indicate how fast the disk rotates and how many disk blocks (sectors) it has per track. The allocation routines use this information to figure out how many milliseconds it takes to skip a disk block. Then using the expected transfer time (rotational delay), the allocation routines can position or place blocks so that the next block is just coming under the disk head when the system is ready to read it.

---

**Note** - It is not necessary to specify the rotational delay (`-d` option to `newfs`) for some devices.

---

Place blocks consecutively only if your system is fast enough to read them on the same disk rotation. If the system is too slow, the disk spins past the beginning of the next block in the file and must complete a full rotation before the block can be read, which takes a lot of time. You should try to specify an appropriate value for the gap

so that the head is located over the appropriate block when the next disk request occurs.

You can change the value of this parameter for an existing file system by using the `tune2fs` command. The change applies only to subsequent block allocation, not to blocks already allocated.

## Optimization Type

The *optimization type* is either *space* or *time*.

- **Space** – When you select space optimization, disk blocks are allocated to minimize fragmentation and disk use is optimized.
- **Time** – When you select time optimization, disk blocks are allocated as quickly as possible, with less emphasis on their placement. When there is enough free space, it is relatively easy to allocate disk blocks effectively, without resulting in too much fragmentation. The default is *time*.

You can change the value of the optimization type parameter for an existing file system using the `tune2fs` command.

## Number of Files

The number of inodes determines the number of files you can have in the file system: one inode for each file. The *number of bytes per inode* determines the total number of inodes created when the file system is made: the total size of the file system divided by the number of bytes per inode. Once the inodes are allocated, you cannot change the number without recreating the file system.

The default number of bytes per inode is 2048 bytes (2 Kbytes), which assumes the average size of each file is 2 Kbytes or greater. Most files are larger than 2 Kbytes. If you have a file system with many symbolic links, they can lower the average file size. If your file system is going to have many small files, you can give this parameter a lower value. Note, however, that having too many inodes is much better than running out of them. If you have too few inodes, you could reach the maximum number of files on a disk slice that is practically empty.

---

## Commands for Creating a Customized File System

This section describes the two commands you use to create a customized file system:

- `newfs`
- `mkfs`

## The `newfs` Command Syntax, Options, and Arguments

The `newfs` command is a friendlier version of the `mkfs` command that is used to create file systems. The `newfs` command is located in the `/usr/sbin` directory.

The syntax is:

```
newfs [-Nv] [mkfs_options] raw_device
```

Table 32-3 describes the options and arguments to the `newfs` command.

**TABLE 32-3** The `newfs` Command Options and Arguments

Option	Description
<code>-N</code>	Displays the file system parameters that would be used in creating the file system without actually creating it. This option does not display the parameters used to create an existing file system.
<code>-v</code>	Displays the parameters that are passed to the <code>mkfs</code> command and creates the file system, unless used with the <code>-N</code> option.
<i>mkfs-options</i>	Use the following options to set the parameters passed to the <code>mkfs</code> command. The options are listed below in the order they are passed to <code>mkfs</code> . Separate the options with spaces without any preceding keywords.
<code>-s size</code>	The size of the file system in sectors. The default is automatically determined from the disk label.
<code>-t ntrack</code>	The number of tracks per cylinder on the disk. The default is determined from the disk label.
<code>-b bsize</code>	The logical block size in bytes to use for data transfers. Specify the size of 4096 or 8192 (4 or 8 Kbytes). The default is 8192 bytes (8 Kbytes).
<code>-f fragsize</code>	The smallest amount of disk space in bytes that is allocated to a file. Specify the fragment size in powers of two in the range from 512 to 8192 bytes. The default is 1024 bytes (1 Kbyte).



**TABLE 32-3** The `newfs` Command Options and Arguments *(continued)*

Option	Description
<code>-c cgsiz</code>	The number of disk cylinders per cylinder group. This number must be in the range 1 to 32. The default is 16.
<code>-m free</code>	The minimum percentage of free disk space to allow. The default is ((64 Mbytes/partition size) * 100), rounded down to the nearest integer and limited between 1% and 10%, inclusively.
<code>-r rpm</code>	The speed of the disk, in revolutions per minute. The default is 3600. This parameter is converted to revolutions per second before it is passed to <code>mkfs</code> .
<code>-i nbpi</code>	The number of bytes per inode to use in computing how many inodes to create. The default is 2048.
<code>-o opt</code>	Optimization type to use for allocating disk blocks to files: <i>space</i> or <i>time</i> . The default is <i>time</i> .
<code>-a apc</code>	The number of alternate blocks per disk cylinder (SCSI devices only) to reserve for bad block placement. The default is 0.
<code>-d gap</code>	(Rotational delay) The expected minimum number of milliseconds it takes the CPU to complete a data transfer and initiate a new data transfer on the same disk cylinder. The default is 4.
<code>-d nrpos</code>	The number of different rotation positions in which to divide a cylinder group. The default is 8.

**TABLE 32-3** The `newfs` Command Options and Arguments (continued)

Option	Description
<code>-C maxcontig</code>	<p>The maximum number of blocks, belonging to one file, that will be allocated contiguously before inserting a rotational delay. The default varies from drive to drive. Drives without internal (track) buffers (or drives/controllers that don't advertise the existence of an internal buffer) default to 1. Drives with buffers default to 7.</p> <p>This parameter is limited in the following way:</p> <p><i>blocksize x maxcontig</i> must be <math>\leq</math> <i>maxphys</i></p> <p><i>maxphys</i> is a read-only kernel variable that specifies the maximum block transfer size (in bytes) that the I/O subsystem is capable of satisfying. (This limit is enforced by <code>mount</code>, not by <code>newfs</code> or <code>mkfs</code>.)</p> <p>This parameter also controls clustering. Regardless of the value of <i>rotdelay</i>, clustering is enabled only when <i>maxcontig</i> is greater than 1. Clustering allows higher I/O rates for sequential I/O and is described in <code>tunefs(1M)</code>.</p>
<code>raw_device</code>	<p>The special character (raw) device file name of the partition to contain the file system. This argument is required.</p>

## Examples—`newfs` Command Options and Arguments


This `newfs` example uses the `-N` option to display file system information, including the backup superblocks.

```
# newfs -N /dev/rdisk/c0t0d0s0
/dev/rdisk/c0t0d0s0: 37260 sectors in 115 cylinders of 9 tracks, 36 sectors
19.1MB in 8 cyl groups (16 c/g, 2.65MB/g, 1216 i/g)
superblock backups (for fsck -b #) at:
32, 5264, 10496, 15728, 20960, 26192, 31424, 36656,
#
```

## The Generic `mkfs` Command

The generic `mkfs` command calls a file system-specific `mkfs`, which then creates a file system of a specified type on a specified disk slice. Although `mkfs` can support different types of file systems, in practice you would use it to create UFS file systems. To make other types of file systems, you would have to write the software for the file system-specific versions of the `mkfs` command to use. Normally, you do not run `mkfs` directly; it is called by the `newfs` command.

This annotated example illustrates all of the arguments to the `mkfs` command.



The generic `mkfs` command is located in `/usr/sbin`. See `mkfs(1M)` for a description of the arguments and options.



## PART IX Backing Up and Restoring Data

---

This part provides instructions for backing up and restoring data in the Solaris environment. This part contains these chapters.

Chapter 33	Provides guidelines and planning information on backing up and restoring data using the <code>ufsdump</code> and <code>ufsrestore</code> commands.
Chapter 34	Provides step-by-step instructions for backing up individual files and complete file systems from local or remote devices.
Chapter 35	Provides step-by-step instructions for restoring individual files and complete file systems.
Chapter 36	Describes how <code>ufsdump</code> works, and the syntax and options for the <code>ufsdump</code> and <code>ufsrestore</code> commands.
Chapter 37	Provides step-by-step instructions for copying file systems to disk, for using the <code>dd</code> , <code>cpio</code> , and <code>tar</code> commands with different backup media, and copying files with a different header format.
Chapter 38	Provides step-by-step instructions for how to add a tape drive, how to determine the type of tape drive, backup device names, and working with tape drives and magnetic tape cartridges.



## Backing Up and Restoring File Systems (Overview)

---

This chapter provides guidelines and planning information on backing up and restoring complete file systems using the `ufsdump` and `ufsrestore` commands.

This is a list of overview information in this chapter.

- “Where to Find Backup and Restore Tasks” on page 533
- “Definition: Backing Up and Restoring File Systems” on page 534
- “Why You Should Back Up File Systems” on page 535
- “Choosing a Tape Device” on page 535
- “Planning Which File Systems to Back Up” on page 536
- “Overview of the Backup and Restore Commands” on page 538
- “Choosing the Type of Backup” on page 539
- “Guidelines For Scheduling Backups” on page 540
- “Sample Backup Schedules” on page 542

---

## Where to Find Backup and Restore Tasks

Use these references to find step-by-step instructions for backing up and restoring file systems (using the `ufsdump` and `ufsrestore` commands).

- Chapter 34
- Chapter 35

## Definition: Backing Up and Restoring File Systems

Backing up file systems means copying file systems to removable media (such as tape) to safeguard against loss, damage, or corruption. Restoring file systems means copying reasonably-current backup files from removable media to a working directory.

This chapter describes the commands for *scheduled* backup and restore operations (`ufsdump` and `ufsrestore`); however, there are other commands you can use for copying files and file systems for sharing or transporting files. Table 33-1 provides pointers to all commands that copy individual files and/or file systems to media.

TABLE 33-1 Commands for Copying Files and File Systems

If You Want To ...	Then Use ...	And Go To ...
Back up complete or individual file systems to a local or remote tape device	<code>ufsdump(1M)</code> command	Chapter 34 or Chapter 36
Back up complete file systems for all systems on a network from a server	Solstice Backup™ software	<i>Solstice Backup 5.1 Administration Guide</i>
Backup and restore a NIS+ master server	<code>nisbackup(1M)</code> and <code>nisrestore(1M)</code> commands	<i>Solaris Naming Administration Guide</i>
Copy, list, and retrieve files on tape	<code>tar(1)</code> , <code>cpio(1)</code> , or <code>pax(1)</code> command	Chapter 37
Copy, list, and retrieve files on diskette	<code>tar(1)</code> command	
Copy master disk to a clone disk	<code>dd(1M)</code> command	Chapter 37
Restore complete file systems or individual files from removable media to a working directory	<code>ufsrestore(1M)</code> command	Chapter 35



---

## Why You Should Back Up File Systems

Backing up files is one of the most crucial system administration functions. You should perform regularly-scheduled backups to prevent loss of data due to:

- System crashes
  - Accidental deletion of files
  - Hardware failures
  - Natural disasters (for example, fire, hurricanes)
  - Problems when reinstalling or upgrading a system
- 

## Choosing a Tape Device

Table 33-2 shows typical tape devices used for storing file systems during the backup process. For more detailed information on tape devices, see Chapter 38.

**TABLE 33-2** Typical Media for Backing Up File Systems

Media	Capacity <sup>1</sup>
1/2-inch reel tape	140 Mbytes (6250 bpi)
2.5-Gbyte 1/4 inch cartridge (QIC) tape	2.5 Gbytes
DDS3 4-mm cartridge tape (DAT)	12 - 24 Gbytes
14-Gbyte 8-mm cartridge tape	14 Gbytes
DLT™ 7000 1/2-inch cartridge tape	35 - 70 Gbytes

1. Capacity depends on the type of drive and the data being written to the tape.

## Planning Which File Systems to Back Up

You should back up any file systems that are critical to users, including file systems that change frequently. Table 33-3 and Table 33-4 provide general guidelines on the file systems to back up for standalone systems and servers.

**TABLE 33-3** File Systems to Back Up for Standalone Systems

Consider Backing Up These File Systems <sup>1</sup> ...	Because ...	And At This Interval ...
root (/) – partition 0 <sup>2</sup>	The root (/) file system contains the kernel and may contain the /var directory in which frequently modified files such as mail and accounting are kept.	At regular intervals.
/usr – partition 6 <sup>2</sup> , /opt	Installing new software and adding new commands typically affects the /usr and /opt file systems. /opt is either part of root (/) or is its own file system.	Occasionally.
/export/home	The /export/home file system contains directories and subdirectories of all users on the standalone system.	More often than root (/) or /usr, perhaps as often as once a day, depending on your site needs.
/export, /var, or other file systems	During installation of Solaris software, you may have created these file systems.	As your site requires.

1. Use the `df` command or look at `/etc/vfstab` file to find out on which slice a file system is located.
2. Indicates file systems created by default when installing Solaris software.

**TABLE 33-4** File Systems to Back Up for Servers

Consider Backing Up These File Systems <sup>1</sup> ...	Because ...	And at This Interval ...
root (/) – partition 0 <sup>2</sup> /export – partition 3 <sup>2</sup> /usr – partition 6 <sup>2</sup>	These file systems contain the kernel, major commands, and executables.	<p>Once a day to once a month depending on your site's needs.</p> <p>root (/) - if you frequently add and remove clients and hardware on the network, you have to change important files in root (/), including the kernel configuration file. In this case, you should do a full back up on the root (/) file system between once a week and once a month. If your site keeps users' mail in the /var/mail directory on a mail server (which client systems then mount), you may want to back up root (/) daily (or /var, if it is a separate file system).</p> <p>/export - the root (/) directory of diskless clients is kept in the /export file system. Because the information it contains is similar to the server's root directory in slice 0, it does not change frequently. You need to back up only occasionally, unless your site delivers mail to client systems; then you should back up /export more frequently.</p> <p>/usr and /opt - contents are fairly static and only need to be backed up once a week to once a month.</p>
/export/home – partition 7 <sup>2</sup>	The /export/home file system contains the home directories and subdirectories of all the users on the system; its files are volatile.	Once a day to once a week.

1. Use the `df` command or look at `/etc/vfstab` file to find out on which slice a file system is located.
2. Indicates the file systems created by default when installing Solaris software.

**Note** - You do not need to back up a server's /export/swap file system.

# Overview of the Backup and Restore Commands

The `ufsdump` and `ufsrestore` commands are the recommended commands for scheduled backups of complete file systems. Table 33-5 lists the tasks you can perform with them. For information on how these commands work and their syntax, see Chapter 36.

**TABLE 33-5** Tasks You Can Perform With the `ufsdump` and `ufsrestore` Commands

With This Command ...	You Can ...	Comments
ufsdump	Back up complete or partial file systems to local or remote tape drives	The tape device can be on any system in the network to which the user has access. This command works quickly because it is aware of the structure of the UFS file system type, and works directly through the raw device interface.
	Back up incremental file system changes	This enables you to back up only those files that were changed since a previous backup.
	Back up groups of systems over the network from a single system	You can run <code>ufsdump</code> from one system on each remote system through a remote shell or remote login, and direct the output to the system on which the drive is located. Or, you can pipe the output to the <code>dd</code> command or a file.
	Automate backups	Use the <code>crontab</code> utility to run a script that starts the <code>ufsdump</code> command.
	Restrict user access to backup tables	Use the <code>-a</code> option.

**TABLE 33-5** Tasks You Can Perform With the `ufsdump` and `ufsrestore` Commands *(continued)*

With This Command ...	You Can ...	Comments
	Determine the size of a backup without actually doing the backup	Use the <code>-S</code> option.
	Keep a log of when each file system was backed up	Use the <code>-u</code> option.
	Verify the contents of the tape against the source file system	Use the <code>-v</code> option.
	<code>ufsrestore</code> Restore individual or complete file systems from a local or remote tape drive	

## Choosing the Type of Backup

With the `ufsdump` command, you can perform full or incremental backups. Table 33-6 lists the differences between these types of backup procedures.

**TABLE 33-6** Differences Between Full and Incremental Backups

Backup Type	Copies	Advantages	Disadvantages
Full	A complete file system or directory	Everything is in one place	Requires large numbers of backup tapes that take a long time to write. Takes longer to retrieve individual files because the drive has to move sequentially to the point on the tape where the file is located. May have to search multiple tapes.
Incremental	Only files in the specified file system that have changed since a previous backup	Easier to retrieve small changes in file systems	Finding which incremental tape contains a file can take time. May have to go back to last full dump.

## Guidelines For Scheduling Backups

A *backup schedule* is the schedule you establish to run the `ufsdump` command. This section provides guidelines on the factors to weigh when creating a backup schedule, guidelines on how often to back up file systems, and sample backup schedules.

### What Drives a Backup Schedule

The schedule you create depends on:

- Your need to minimize the number of tapes
- Time available for doing backups
- Time available to do a full restore of a damaged file system
- Time available for retrieving individual files that get accidentally deleted

## How Often Should You Do Backups?

If you do not need to minimize time and media spent on backups, you can do full backups every day. However, this is not realistic for most sites, so incremental backups are most often used. In this case, it is recommended that you back up your site enough to restore files from the last four weeks. This requires at least four sets of tapes—one for each week, which you would reuse each month. In addition, you should archive the monthly backups for at least a year, and then keep yearly backups for a number of years.

## Using Dump Levels to Create Incremental Backups

The dump level you specify in the `ufsdump` command (0-9) determines which files are backed up. Specifying dump level 0 creates a full backup. Numbers 1-9 are used to schedule incremental backups, but have *no defined meanings*. Numbers 1-9 are just a range of numbers used to schedule cumulative or discrete backups. The only meaning levels 1-9 have is in relationship to each other, as a higher or lower number.

The following examples show the flexibility of the incremental dump procedure using levels 1-9.

### Dump Levels For Daily, Cumulative Backups

Doing daily, cumulative incremental backups is the most commonly used backup scheme and is recommended for most situations. The following example shows a schedule using a level 9 dump each day, and a level 5 dump on Friday to restart the process.

---

**Note** - In the following example, you could have used other numbers in the 1-9 range to produce the same results. The key is having the same number each day, with any *lower* number on Friday. For example, you could have specified levels 4, 4, 4, 4, 2 or 7, 7, 7, 7, 5.

---




Figure 33-1 Incremental Backup: Daily Cumulative

## Dump Levels For Daily, Discrete Backups

The following example shows a schedule where you capture only a day's work on different tapes. In this case, sequential dump level numbers are used during the week (3,4,5,6) with a lower number (2) on Friday.

---

**Note** - In the following example, you could have used the sequence 6,7,8,9 followed by 2, or 5,6,7,8 followed by 3. Remember, the number themselves have no defined meaning; you attribute meaning by ordering them in a high/low sequence.

---




Figure 33-2 Incremental Backup: Daily Discrete

---

## Sample Backup Schedules

This section provides sample backup schedules. All schedules assume you begin with a full backup (level 0), and that you use the `-u` option to record each backup.

### Example—Daily Cumulative, Weekly Cumulative Backups

Table 33-7 shows the most commonly used incremental backup schedule; it is recommended for most situations. With this schedule:

- All files that have changed since the lower-level backup at the end of the previous week are saved each day.
- For each weekday level 9 backup, the previous level 0 or level 5 is the closest backup at a lower level. Therefore, each weekday tape contains all the files changed since the end of the previous week (or the initial level 0 for the first week).



- For each Friday level 5 backup, the nearest lower-level backup is the level 0 done at the beginning of the month. Therefore, each Friday's tape contains all the files changed during the month to that point.

**TABLE 33-7** Daily Cumulative/Weekly Cumulative Backup Schedule

	Floating	Mon	Tues	Wed	Thurs	Fri
1st of Month	0					
Week 1		9	9	9	9	5
Week 2		9	9	9	9	5
Week 3		9	9	9	9	5
Week 4		9	9	9	9	5

Table 33-8 shows how the contents of the tapes can change across two weeks using the previous schedule. Each letter represents a different file.

**TABLE 33-8** Contents of Tapes for Daily/Weekly Cumulative Schedule

	Mon	Tues	Wed	Thurs	Fri
Week 1	a b	a b c	a b c d	a b c d e	a b c d e f
Week 2	g	g h	g h i	g h i j	a b c d e f g h i j k

## Tape Needs

With this schedule, you will need six tapes (if you want to reuse daily tapes), or nine tapes (if you want to use four different daily tapes): one for the level 0, four for the Fridays, and one or four daily tapes.

If you need to restore a complete file system, you will need the following tapes: the level 0, the most recent Friday tape, and the most recent daily tape since the last Friday tape (if any).

## Example—Daily Cumulative, Weekly Incremental Backups

Table 33–9 shows a schedule where each weekday tape accumulates all files that changed since the beginning of the week (or the initial level 0 for the first week), and each Friday’s tape contains all the files changed that week.

**TABLE 33–9** Daily Cumulative/Weekly Incremental Backup Schedule

	Floating	Mon	Tues	Wed	Thurs	Fri
1st of Month	0					
Week 1		9	9	9	9	3
Week 2		9	9	9	9	4
Week 3		9	9	9	9	5
Week 4		9	9	9	9	6

Table 33–10 shows how the contents of the tapes can change across two weeks using the previous schedule. Each letter represents a different file.

**TABLE 33–10** Contents of Tapes for Daily Cumulative/Weekly Incremental Backup Schedule

	Mon	Tues	Wed	Thurs	Fri
Week 1	a b	a b c	a b c d	a b c d e	a b c d e f
Week 2	g	g h	g h i	g h i j	g h i j k

## Tape Needs

With this schedule, you will need six tapes (if you want to reuse daily tapes), or nine tapes (if you want to use four different daily tapes): one for the level 0, four for the Fridays, and one or four daily tapes.

If you need to restore a complete file system, you will need the following tapes: the level 0, all the Friday tapes, and the most recent daily tape since the last Friday tape (if any).

## Example—Daily Incremental, Weekly Cumulative Backups

Table 33–11 shows a schedule where each weekday tape contains only the files changed since the previous day, and each Friday's tape contains all files changed since the initial level 0 at the beginning of the month.

**TABLE 33–11** Daily Incremental/Weekly Cumulative Backup Schedule

	Floating	Mon	Tues	Wed	Thurs	Fri
1st of Month	0					
Week 1		3	4	5	6	2
Week 2		3	4	5	6	2
Week 3		3	4	5	6	2
Week 4		3	4	5	6	2

Table 33–12 shows how the contents of the tapes can change across two weeks using the previous schedule. Each letter represents a different file.

**TABLE 33–12** Contents of Tapes for Daily/Weekly Cumulative Backup Schedule

	Mon	Tues	Wed	Thurs	Fri
Week 1	a b	c d	e f g	hi	a b c d e f g h i
Week 2	j k l	m	n o	p q	a b c d e f g h i j k l m n o p q r s

## Tape Needs

With this schedule you will need at least nine tapes (if you want to reuse daily tapes—not recommended), or 21 tapes (if you save weekly tapes for a month): one for the level 0, four for the Fridays, and four or 16 daily tapes.

If you need to restore the complete file system, you will need the following tapes: the level 0, the most recent Friday tape, and all the daily tapes since the last Friday tape (if any).

## Example—Backup Schedule for a Server

Table 33–13 shows an example backup strategy for a heavily-used file server on a small network where users are doing file-intensive work, such as program development or document production. It assumes that the backup period begins on a Sunday and consists of four seven-day weeks.

**TABLE 33–13** Schedule of Backups for a Server Example

Directory	Date	Level	Tape Name
root (/)	1st Sunday	0	<i>n</i> tapes
/usr	1st Sunday	0	"
/export	1st Sunday	0	"
/export/home	1st Sunday	0	"
	1st Monday	9	A
	1st Tuesday	9	B
	1st Wednesday	5	C
	1st Thursday	9	D
	1st Friday	9	E
	1st Saturday	5	F
root (/)	2nd Sunday	0	<i>n</i> tapes
/usr	2nd Sunday	0	"
/export	2nd Sunday	0	"
/export/home	2nd Sunday	0	"
	2nd Monday	9	G
	2nd Tuesday	9	H
	2nd Wednesday	5	I
	2nd Thursday	9	J

**TABLE 33-13** Schedule of Backups for a Server Example *(continued)*

Directory	Date	Level	Tape Name
	2nd Friday	9	K
	2nd Saturday	5	L
root (/)	3rd Sunday	0	n tapes
/usr	3rd Sunday	0	"
/export	3rd Sunday	0	"
/export/home	3rd Sunday	0	"
	3rd Monday	9	M
	3rd Tuesday	9	N
	3rd Wednesday	5	O
	3rd Thursday	9	P
	3rd Friday	9	Q
	3rd Saturday	5	R
root (/)	4th Sunday	0	n tapes
/usr	4th Sunday	0	"
/export	4th Sunday	0	"
/export/home	4th Sunday	0	"
	4th Monday	9	S
	4th Tuesday	9	T
	4th Wednesday	5	U
	4th Thursday	9	V

**TABLE 33-13** Schedule of Backups for a Server Example *(continued)*

Directory	Date	Level	Tape Name
	4th Friday	9	W
	4th Saturday	5	X

With this plan, you use  $4n$  tapes (the number of tapes needed for four full backups of root (/), /usr, /export, and /export/home), plus 24 additional tapes for the incremental backups of /export/home. This plan assumes that each incremental backup uses one tape and you save the tapes for a month.

Here's how this plan works:

1. On each Sunday, do a full backup (level 0) of root (/), /usr, /export, and /export/home. Save the level 0 tapes for at least 3 months.
2. On the first Monday of the month, use tape A to do a level 9 backup of /export/home. `ufsdump` copies all files changed since the previous lower-level backup (in this case, the level 0 backup that you did on Sunday).
3. On the first Tuesday of the month, use tape B to do a level 9 backup of /export/home. Again, `ufsdump` copies all files changed since the last lower-level backup—Sunday's level 0 backup.
4. On the first Wednesday, use tape C to do a level 5 backup. `ufsdump` copies all files changed since Sunday.
5. Do the Thursday and Friday level 9 backups on tapes D and E. `ufsdump` copies all files changed since the last lower-level backup—Wednesday's level 5 backup.
6. On the first Saturday of the month, do a level 5 backup of /export/home, which copies all files changed since the previous lower-level backup—in this case, the level 0 backup you did on Sunday. Store tapes A-F until the first Monday of the next 4-week period, when you use them again.
7. Repeat steps 1-6 for the next three weeks, using tapes G-L and  $4n$  tapes for the level 0 on Sunday, and so on.
8. For each 4-week period, repeat steps 1-7, using a new set of tapes for the level 0s and reusing tapes A-X for the incremental backups. The level 0 tapes could be reused after 3 months.

This plan lets you save files in their various states for a month. It requires many tapes, but ensures that you have a library of tapes to draw upon. To reduce the number of tapes, you could reuse Tapes A-F each week.

## Other Backup Scheduling Suggestions

Table 33-14 provides other suggestions for scheduling backups.

**TABLE 33-14** Other Suggestions for Scheduling Backing Up Systems

If You ...	Then ...	Comments
Need to restore different versions of files (for example, file systems used for word processing)	<ul style="list-style-type: none"> <li>■ Do daily incremental backups every working day.</li> <li>■ Do <i>not</i> reuse the same tape for daily incremental backups.</li> </ul>	This schedule saves all files modified that day, as well as those files still on disk that were modified since the last backup of a lower level. However, with this schedule you should use a different tape each day because a file changed on Tuesday, and again on Thursday, goes onto Friday's lower-level backup looking like it did Thursday night—not Tuesday night. If a user needs the Tuesday version, you cannot restore it unless you have a Tuesday backup tape (or a Wednesday backup tape). Similarly, a file that is present on Tuesday and Wednesday, but removed on Thursday, does not appear on the Friday lower-level backup.
Need to quickly restore a complete file system	Do lower-level backups more frequently.	—
Are backing up a number of file systems on the same server	Consider offsetting the schedule for different file systems.	This way you're not doing all level 0 backups on the same day.
Need to minimize tapes	Increase the level of incremental backups done across the week.	This means only changes from day to day are saved on each daily tape.
	Increase the level of backups done at the end of the week.	This means only changes from week to week (rather than the entire month) are saved on the weekly tapes.
	Put each day's and week's incremental backups onto the same tape.	This is done by using the no rewind option in the <code>ufsdump</code> command.





## Backing Up Files and File Systems (Tasks)

---

This chapter describes the procedures for backing up file systems using the `ufsdump` command.

This is a list of the step-by-step instructions in this chapter.

- “How to Find File System Names” on page 552
- “How to Determine the Number of Tapes for a Full Backup” on page 552
- “How to Do Backups to Tape” on page 554

For detailed information on syntax, options, and arguments for the `ufsdump` command, see Chapter 36.

---

## Preparing to Do Backups

Preparing to back up file systems begins with planning, which is described in Chapter 33 and covers choosing:

- A tape drive
- Which file systems to back up
- The type of backup (full or incremental)
- A backup schedule

This section describes other tasks you may need to perform before backing up file systems including:

- Finding names of file systems to back up
- Determining the number of tapes for a full backup

## ▼ How to Find File System Names

1. Display the contents of the `/etc/vfstab` file.

```
$ more /etc/vfstab
```

2. Look in the `mount point` column for the name of the file system.
3. You will use the mount point in the `mount point` column when you back up the file system.

### Example—Finding File System Names

```
$ more /etc/vfstab
#device          device          mount   FS   fsck  mount  mount
#to mount        to fsck         point   type pass at boot options
#
/proc            -              /proc   proc -    no    -
swap             -              /tmp    tmpfs -    yes   -
/dev/dsk/c0t3d0s0 /dev/rdisk/c0t3d0s0 /        ufs   1     no    -
/dev/dsk/c0t3d0s1 -              -        swap -    no    -
/dev/dsk/c0t1d0s6 /dev/rdisk/c0t1d0s6 /usr     ufs   2     no    -
mars:/share/kit -              /kit    nfs   -     yes   -
mars:/db/doc    -              /db/doc nfs   -     yes   -
```

## ▼ How to Determine the Number of Tapes for a Full Backup

1. Become superuser.
2. Estimate the size of the backup in bytes by using the `ufsdump S` command.

```
# ufsdump S filesystem
```

`S` Displays the estimated number of bytes needed to do the backup.

3. Divide the estimated size by the capacity of the tape to see how many tapes you need.

See Table 33-2 for a list of tape capacities.

## Example—Determining Number of Tapes

In this example, the file system of 489,472 bytes will easily fit on a 150-Mbyte tape.

```
# ufsdump s /export/home
489472
```

---

## Doing Backups

The following are general guidelines for performing backups:

- Use single-user mode or unmount the file system.
- Be aware that backing up file systems when there are directory-level operations (such as creating, removing, and renaming files) and file-level activity occurring means that some data will not be included in the backup.
- You can run the `ufsdump` command from a single system and remotely back up groups of systems across the network through remote shell or remote login, and direct the output to the system on which the tape drive is located. (Typically, the tape drive is located on the system from which you run the `ufsdump` command, but it does not have to be.)

Another way to back up files to a remote drive is to pipe the output from the `ufsdump` command to the `dd` command. See Chapter 37 for information about using the `dd` command.

- If you are doing remote backups across the network, the system with the tape drive must have entries in its `.rhosts` file for each client that will be using the drive. Also, the system initiating the backup must be included in the `.rhosts` file on each system it will back up.
- To specify a remote drive on a system, use the naming convention that matches the OS release of the system with the remote tape drive. For example, use `/dev/rst0` for a remote drive on a system running the SunOS 4.1.1 release or compatible versions; use `/dev/rmt/0` for a system running the Solaris 7 release or compatible versions.

---

**Note** - Use the `nisbackup` command to backup a NIS+ master server running the Solaris 2.5 release or compatible versions. See *Solaris Naming Administration Guide* for information on using this command.

---

## ▼ How to Do Backups to Tape

The following steps provide the general steps for backing up file systems using the `ufsdump` command. The examples show specific uses of options and arguments.

1. **Become superuser.**
2. **Bring the system to run level S (single-user mode).**

```
# shutdown -g30 -y
```

3. **[Optional] Check the file system for consistency with the `fsck` command.**

Running the `fsck -m` command checks for consistency of file systems. For example, power failures can leave files in an inconsistent state. For more information on the `fsck` command, see Chapter 31.

```
# fsck -m /dev/rdisk/ device-name
```

4. **If you need to back up file systems to a remote tape drive:**
  - a. **On the system to which the tape drive is attached (the tape server), add the following entry to its `.rhosts` file.**

```
host root
```

*host* Specifies the name of the system on which you will run `ufsdump` to perform the backup.

- b. **On the tape server, verify that the host added to the `.rhosts` file is accessible through the name service.**

5. **Identify the device name of the tape drive.**

The default tape drive is `/dev/rmt/0`.

6. **Insert a tape that is not write protected into the tape drive.**

7. **Back up file systems using the `ufsdump` command.**

Use the following table to select the most common options and arguments for the `ufsdump` command. See Chapter 36 for other options and arguments.

To ...	Use This Option or Argument ...	For Example ...	See ...
Do a full backup	0 option	<code>ufsdump 0ucf /dev/rmt/0 /</code>	“Example—Full Backup, root (/)” on page 556
Do an incremental backup	1-9 option	<code>ufsdump 9ucf /dev/rmt/0 /</code>	“Example—Incremental Backup, root (/)” on page 556
Back up individual files	Specify a file or directory	<code>ufsdump ucf /dev/rmt/0 /export/home/kryten</code>	
Record dumps to <code>/etc/dumpdates</code> file	<code>-u</code> option	<code>ufsdump 9ucf /dev/rmt/0 /export/home</code>	“Example—Incremental Backup, root (/)” on page 556
Specify a cartridge tape	<code>-c</code> option	<code>ufsdump 9ucf /dev/rmt/0 /export/home</code>	“Example—Incremental Backup, root (/)” on page 556
Specify the tape drive	<code>-f dump-file</code>	<code>ufsdump 9ucf /dev/rmt/0 /export/home</code>	“Example—Incremental Backup, root (/)” on page 556
Back up local file systems to a remote system's tape device	<i>remote-system:dump-file</i>	<code>ufsdump 0ucf pluto:/dev/rmt/0 /export/home</code>	“Example—Full Backup to Remote System (Solaris 2.6 Data to Solaris 7 System)” on page 558

8. If prompted, remove the tape and replace with the next volume.
9. Label each tape with the volume number, level, date, system name, disk slice, and file system.
10. Bring the system back to run level 3 by pressing Control-d.
11. Verify the backup was successful by using the `ufsrestore` command to display the tape contents.  
This command is described in Chapter 35.

## Example—Full Backup, root (/)

The following example shows a full backup of the root (/) file system to a QIC-150 tape (/dev/rmt/0).

```
# shutdown -g30 -y
# ufsdump 0ucf /dev/rmt/0 /
  DUMP: Writing 63 Kilobyte records
  DUMP: Date of this level 0 dump: Tue Jun 09 10:14:54 1998
  DUMP: Date of last level 0 dump: the epoch
  DUMP: Dumping /dev/rdisk/c0t3d0s0 (pluto:/) to /dev/rmt/0.
  DUMP: Mapping (Pass I) [regular files]
  DUMP: Mapping (Pass II) [directories]
  DUMP: Estimated 73708 blocks (35.99MB).
  DUMP: Dumping (Pass III) [directories]
  DUMP: Dumping (Pass IV) [regular files]
  DUMP: Tape rewinding
  DUMP: 73582 blocks (35.93MB) on 1 volume at 100 KB/sec
  DUMP: DUMP IS DONE
  DUMP: Level 0 dump on Tue Jun 09 10:14:54 1998
# ufsrestore tf /dev/rmt/0
    2 .
    3 ./lost+found
    5696 ./usr
   11392 ./export
   17088 ./export/home
   22784 ./export/root
   28480 ./export/swap
   34176 ./opt
   39872 ./var
   45568 ./var/sadm
   51264 ./var/sadm/install
   56960 ./var/sadm/install/admin
   57011 ./var/sadm/install/admin/default
      .
      .
      .
#
(Press Control-d to bring system to run level 3)
```

## Example—Incremental Backup, root (/)

The following example shows an incremental backup of the root (/) file system to a 4-mm DAT tape (/dev/rmt/0).

```
# ufsdump 9ucf /dev/rmt/0 /
  DUMP: Writing 63 Kilobyte records
  DUMP: Date of this level 9 dump: Tue Jun 09 11:04:41 1998
  DUMP: Date of last level 0 dump: Tue Jun 09 10:14:54 1998
  DUMP: Dumping /dev/rdisk/c0t3d0s0 (pluto:/) to /dev/rmt/0.
  DUMP: Mapping (Pass I) [regular files]
  DUMP: Mapping (Pass II) [directories]
  DUMP: Mapping (Pass II) [directories]
```

(continued)

(Continuation)

```
DUMP: Mapping (Pass II) [directories]
DUMP: Mapping (Pass II) [directories]
DUMP: Mapping (Pass II) [directories]
DUMP: Estimated 1502 blocks (751KB).
DUMP: Dumping (Pass III) [directories]
DUMP: Dumping (Pass IV) [regular files]
DUMP: Tape rewinding
DUMP: 1384 blocks (692KB) on 1 volume at 51 KB/sec
DUMP: DUMP IS DONE
DUMP: Level 9 dump on Tue Jun 09 11:04:41 1998
# ufsrestore tf /dev/rmt/0
 39872 ./var
 62671 ./var/adm
 39915 ./var/adm/sa
 40018 ./var/adm/sa/sa09
 62810 ./var/adm/sulog
 62888 ./var/adm/pacct
 91154 ./var/cron
 91311 ./var/cron/log
 5716  ./var/mail
 5835  ./var/mail/adm
 45585 ./var/spool
 51388 ./var/spool/mqueue
 91155 ./var/tmp
.
.
.
```

## Example—Full Backup, Individual Home Directory

The following example shows a full backup of the `/export/home/kryten` directory to a 4-mm DAT tape.

```
# ufsdump 0ucf /dev/rmt/0 /export/home/kryten
DUMP: Writing 63 Kilobyte records
DUMP: Date of this level 0 dump: Tue Jun 09 11:12:44 1998
DUMP: Date of last level 0 dump: the epoch
DUMP: Dumping /dev/rdisk/c0t3d0s7 (pluto:/export/home) to /dev/rmt/0.
DUMP: Mapping (Pass I) [regular files]
DUMP: Mapping (Pass II) [directories]
DUMP: Estimated 232 blocks (116KB).
DUMP: Dumping (Pass III) [directories]
DUMP: Dumping (Pass IV) [regular files]
DUMP: Tape rewinding
DUMP: 124 blocks (62KB) on 1 volume at 8 KB/sec
DUMP: DUMP IS DONE
# ufsrestore tf /dev/rmt/0
 2      .
 2688   ./kryten
 5409   ./kryten/letters
```

(continued)

(Continuation)

```
5410 ./kryten/letters/letter1
5411 ./kryten/letters/letter2
5412 ./kryten/letters/letter3
2689 ./kryten/.profile
8096 ./kryten/memos
30 ./kryten/reports
31 ./kryten/reports/reportA
32 ./kryten/reports/reportB
33 ./kryten/reports/reportC
#
```

## Example—Full Backup to Remote System (Solaris 2.6 Data to Solaris 7 System)

The following example shows a full backup of a local `/export/home` file system on a Solaris 2.6 system to a tape device on a remote Solaris 7 system called `pluto`.

```
# ufsdump 0ucf pluto:/dev/rmt/0 /export/home
# ufsdump 0ucf pluto:/dev/rmt/0 /export/home
DUMP: Writing 63 Kilobyte records
DUMP: Date of this level 0 dump: Tue Jun 09 13:54:27 1998
DUMP: Date of last level 0 dump: the epoch
DUMP: Dumping /dev/rdisk/c0t3d0s7 (venus:/export/home) to pluto:/dev/rmt/
0.
DUMP: Mapping (Pass I) [regular files]
DUMP: Mapping (Pass II) [directories]
DUMP: Estimated 38310 blocks (18.71MB).
DUMP: Dumping (Pass III) [directories]
DUMP: Dumping (Pass IV) [regular files]
DUMP: Tape rewinding
DUMP: 38302 blocks (18.70MB) on 1 volume at 98 KB/sec
DUMP: DUMP IS DONE
DUMP: Level 0 dump on Tue Jun 09 13:54:27 1998
# # ufsrestore tf pluto:/dev/rmt/0
2 .
3 ./lost+found
34180 ./kryten
34182 ./kryten/.login
34183 ./kryten/.cshrc
51266 ./kryten/letters
51272 ./kryten/letters/letter1
51273 ./kryten/letters/letter2
51274 ./kryten/letters/letter3
57032 ./kryten/memos
74095 ./kryten/reports
74096 ./kryten/reports/reportA
74097 ./kryten/reports/reportB
74098 ./kryten/reports/reportC
.
```

(continued)



(Continuation)

```
.  
.  
#
```

## Example—Full Backup to Remote System (Solaris 2.7 Data to SunOS 4.1.3 System)

The following example shows a full backup of a local `/export/home` file system on a Solaris 7 system to a tape device on a remote SunOS 4.1.3 system (mars).

**Note** - Notice the SunOS 4.x-style device name (`/dev/rst0`) used with the `ufsdump` command.

```
# ufsdump 0ucf mars:/dev/rst0 /export/home  
DUMP: Writing 63 Kilobyte records  
DUMP: Date of this level 0 dump: Fri Oct 24 15:06:47 1997  
DUMP: Date of last level 0 dump: the epoch  
DUMP: Dumping /dev/rdsk/c0t3d0s7 (earth:/export/home) to (mars:/dev/  
rst0).  
DUMP: mapping (Pass I) [regular files]  
DUMP: mapping (Pass II) [directories]  
DUMP: estimated 19574 blocks (9.56MB)  
DUMP: dumping (Pass III) [directories]  
DUMP: dumping (Pass IV) [regular files]  
DUMP: level 0 dump on Fri Oct 24 15:06:47 1997  
DUMP: Tape rewinding  
DUMP: 19574 blocks (9.56MB) on 1 volume  
DUMP: DUMP IS DONE  
#  
  
ufsrestore tf mars:/dev/rst0  
2 .  
3 ./lost+found  
2688 ./kryten  
5409 ./kryten/letters  
5410 ./kryten/letters/letter1  
5411 ./kryten/letters/letter2  
5412 ./kryten/letters/letter3  
2689 ./kryten/.profile  
8096 ./kryten/memos  
30 ./kryten/reports  
31 ./kryten/reports/reportA  
32 ./kryten/reports/reportB  
33 ./kryten/reports/reportC  
.  
.  
.
```

(continued)

(Continuation)

```
#
```

## Example—Full Backup to Remote System (SunOS 4.1.3 Data to Solaris 7)

The following example shows a full backup of a local root (/) file system on a Sun 4.1.3 system (mars) to a remote tape device on a Solaris 7 system called pluto.

**Note** - Notice that when you back up data on a system running SunOS 4.1.3 or a compatible version, you must use the `dump` command—not the `ufsdump` command.

```
# dump 0ucf pluto:/dev/rmt/0 /
DUMP: Date of this level 0 dump: Tue Oct 21 16:05:19 1997
DUMP: Date of last level 0 dump: the epoch
DUMP: Dumping /dev/rsd2a (/) to /dev/rmt/0 on host pluto
DUMP: mapping (Pass I) [regular files]
DUMP: mapping (Pass II) [directories]
DUMP: estimated 8686 blocks (4.24MB) on 0.10 tape(s).
DUMP: dumping (Pass III) [directories]
DUMP: dumping (Pass IV) [regular files]
DUMP: level 0 dump on Tue Oct 21 16:05:19 1997
DUMP: Tape rewinding
DUMP: 8690 blocks (4.24MB) on 1 volume
DUMP: DUMP IS DONE
# restore tf pluto:/dev/rmt/0
      2      .
      3      ./lost+found
    3776      ./export
    7552      ./home
   11328      ./usr
   15104      ./pcfs
    3777      ./tftpboot
    3778      ./tftpboot/tftpboot
    3794      ./tftpboot/boot.sun4c.sunos.4.1.3
    7553      ./etc
    7554      ./etc/sendmail.cf
    7555      ./etc/aliases
    7556      ./etc/aliases.dir
    7557      ./etc/aliases.pag
    7558      ./etc/holidays
    7559      ./etc/dumpdates
      .
      .
#
```

---

## Restoring Files and File Systems (Tasks)

---

This chapter describes the procedures for restoring file systems.

This is a list of step-by-step instructions in this chapter.

- “How to Determine Which Tapes to Use” on page 563
- “How to Restore Files Interactively” on page 565
- “How to Restore Specific Files Non-Interactively” on page 567
- “How to Restore Files Using a Remote Tape Drive” on page 569
- “How to Restore a Complete File System” on page 570
- “How to Restore the root (/) and /usr File Systems” on page 573

This chapter describes how to use the **ufsrestore(1M)** command to restore files and file systems that were backed up using the **ufsdump** command. See Chapter 37 for information about other commands you can use to archive, restore, copy, or move files and file systems.

---

## Preparing to Restore Files and File Systems

The **ufsrestore** command copies files to disk, relative to the current working directory, from backups created using the **ufsdump** command. You can use **ufsrestore** to reload an entire file system hierarchy from a level 0 dump and incremental dumps that follow it or to restore one or more single files from any dump tape. If **ufsrestore** is run as superuser, files are restored with their original owner, last modification time, and mode (permissions).

Before you start to restore files or file systems, you need to know:

- Which tapes (or diskettes) you need
- The raw device name on which you want to restore the file system
- The type of tape drive you will use
- The device name (local or remote) for the tape drive

## Determining the Disk Device Name

If you have properly labeled your backup tapes, you should be able to use the disk device name (`/dev/rdisk/devicename`) from the tape label. See “How to Find File System Names” on page 552 for more information.

## Determining the Type of Tape Drive You Will Use

You must use a tape drive that is compatible with the backup media to restore the files. The format of the backup media determines which drive you must use to restore files. For example, if your backup media is 8-mm tape, you must use an 8-mm tape drive to restore the files.

## Determining the Tape Device Name

You may have specified the tape device name (`/dev/rmt/n`) as part of the backup tape label information. If you are using the same drive to restore a backup tape, you can use the device name from the label. See Chapter 38 for more information on media devices and device names.

---

# Restoring Complete File Systems

Occasionally, a file system becomes so damaged that you must completely restore it. Typically, you need to restore a complete file system after a disk head crash. You may need to replace the hardware before you can restore the software. See Chapter 23 or Chapter 24 for information on how to replace a disk. Fully restoring a file system such as `/export/home` can take a lot of time. If you have consistently backed up file systems, you can restore them to their state as of the last incremental backup.

---

## Restoring Individual Files and Directories

When you back up files and directories, they are saved relative to the file system in which they belong. When you restore files and directories, `ufsrestore` recreates the file hierarchy in the current working directory. For example, files backed up from the `/export/doc/books` directory (where `/export` is the file system), would be saved relative to `/export`. In other words, the `book1` file in the `docs` directory would be saved as `./doc/books/book1` on the tape. Later on, if you restored the `./doc/books/book1` file to the `/var/tmp` directory, the file would be restored to `/var/tmp/doc/books/book1`.

When restoring individual files and directories, it is a good idea to restore them to a temporary location, such as the `/var/tmp` directory. After you verify them, you can move the files to their proper locations. You can restore individual files and directories to their original locations. If you do so, be sure you are not overwriting newer files with older versions from the backup tape.

---

**Note** - Do not restore files in the `/tmp` directory even temporarily. The `/tmp` directory is usually mounted as a TMPFS file system and TMPFS does not support UFS file system attributes such as ACLs.

---

---

## Restoring Files and File Systems

Things you need to know:

- Which tapes have the files to be restored
- The path name of the files to be restored

### ▼ How to Determine Which Tapes to Use

1. **Ask the user the approximate date the files to be recovered were last modified.**
2. **Refer to your backup plan to find the date of the last backup that would have the file or file system on it.**

To retrieve the most recent version of a file, work backward through the incremental backups from highest to lowest level and most recent to least recent, unless the user requests otherwise.

3. If you have online archive files, use the `ufsrestore` command to identify correct media.

```
# ufsrestore ta archive-name ./path/filename ./path/filename
```

<code>t</code>	List each file that appears on the tape.
<code>a</code>	Reads the table of contents from the online archive file instead of the tape.
<code>archive-name</code>	Identifies the online archive file name.
<code>./path/filename</code>	Identifies the file name(s) you are looking for on the online archive. If successful, <code>ufsrestore</code> will print out the inode number and file name. If unsuccessful, <code>ufsrestore</code> will print an error message.

4. Insert the media containing the backups in the drive and use the `ufsrestore` command to verify the correct media.

```
# ufsrestore tf device-name ./path/filename ./path/filename
```

Be sure to use the complete path for the *filename(s)*. If a file is in the backup, its name and inode number is listed. Otherwise, a message says it is not on the volume.

5. If you have multiple dump files on the same tape, use the `s /dev/rmt/n` option to position the tape at the dump you want to use.

```
# ufsrestore tfs /dev/rmt/n tape_number
```

## Example—Determining Which Tapes to Use

If you use `ufsdump` to dump the `/usr` file system, the table of contents lists only the files and directories under `/usr`. The following example checks if `/usr/bin/pwd` is in the online archive.

```
# ufsrestore ta archive-name ./bin/pwd
```

The following example checks if `/usr/bin/pwd` is on the backup tape.

```
# ufsrestore tf /dev/rmt/n ./bin/pwd
```

## ▼ How to Restore Files Interactively

1. **Become superuser.**
2. **Write-protect the tape.**
3. **Insert the volume 1 tape into the tape drive.**
4. **Change to a directory that will be used to restore the files temporarily.**

```
# cd /var/tmp
```

To avoid conflicts with other users, you may want to create and change to a subdirectory, such as `/var/tmp/restore`, in which to restore the files.

If you are restoring a hierarchy, you should restore the files in a temporary directory on the same file system where the files will reside, so you can use the `mv` command to move the entire hierarchy where it belongs after it is restored.

5. **Use the `ufsrestore` command to start the interactive restoration.**  
Some informational messages and the `ufsrestore>` prompt are displayed.

```
# ufsrestore if /dev/rmt/n
```

6. **Create a list of files to be restored.**
  - a. **List the contents of a directory.**

```
ufsrestore> ls directory
```

- b. **Change to a directory.**

```
ufsrestore> cd directory-name
```

- c. **Create a list of files and directories you want to restore.**

```
ufsrestore> add filename filename
```

- d. **If you need to remove a directory or file name from the list of files to be restored, use the `delete` command.**

```
ufsrestore> delete filename
```

7. Turn on `verbose` mode to display the file names as they are being restored.

```
ufsrestore> verbose
```

8. Use the `extract` command after the list is complete.

```
ufsrestore> extract
```

The `ufsrestore` command asks you which volume number to use.

9. Type the volume number and press Return. If you have only one volume, type `1` and press Return.

```
Specify next volume #: 1
```

The files and directories in the list are extracted and restored to the current working directory.

10. To keep the mode of the current directory unchanged, enter `n` at the `set owner/mode` prompt.

```
set owner/mode for `.'? [yn] n
```

A delay will occur while `ufsrestore` performs its final cleanup.

11. Quit the `ufsrestore` program.

```
ufsrestore> quit
```

The shell prompt is displayed.

12. Verify the restored files.

- a. List the restored files and directories.

```
# ls -l
```

A list of files and directories is displayed.

- b. Check the list to be sure all the files and directories you specified in the list have been restored.
- c. Move the files to the proper directories.



## Example—Restoring Files Interactively

The following example extracts the files `/etc/passwd` and `/etc/shadow` from the backup tape.

```
# cd /var/tmp
# ufsrestore if /dev/rmt/0
ufsrestore> ls
.:
.cpr_config  etc/          lost+found/   sbin/         usr/
TT_DB/       export/       mnt/          sccs/         var/
b/           home/         net/          share/        vol/
bin          kernel/       opt/          shared/        ws/
dev/         lib/          platform/     src/          xfn/
devices/     license/      proc/         tmp/

ufsrestore> cd etc
ufsrestore> add passwd shadow
ufsrestore> verbose
verbose mode on
ufsrestore> extract
Extract requested files
You have not read any volumes yet.
Unless you know which volume your file(s) are on you should start
with the last volume and work towards the first.
Specify next volume #: 1
extract file ./etc/shadow
extract file ./etc/passwd
Add links
Set directory mode, owner, and times.
set owner/mode for `.'? [yn] n
ufsrestore> quit
#
```

## ▼ How to Restore Specific Files Non-Interactively

1. Become superuser.
2. Write-protect the tape for safety.
3. Insert the volume 1 tape into the tape drive.
4. Change to a directory for restoring files temporarily.

```
# cd /var/tmp
```

To avoid conflicts with other users, you may want to create and change to a subdirectory, such as `/var/tmp/restore`, in which to restore the files.

If you are restoring a hierarchy, you should restore the files in a temporary directory on the same file system where the files will reside, so you can use the `mv` command to move the entire hierarchy where it belongs after it is restored.

**5. Use the `ufsrestore` command to restore the file.**

```
# ufsrestore xvf /dev/rmt/n filename ...
```

<code>x</code>	Tells <code>ufsrestore</code> to copy specific files or directories in the <i>filename</i> argument.
<code>v</code>	Displays the file names as they are restored.
<code>f /dev/rmt/n</code>	Identifies the tape device name.
<i>filename ...</i>	One or more individual file or directory names separated by spaces, for example: <code>./export/home/user1/mail</code> <code>./export/home/user2/mail</code> .

**6. Type the volume number where files are located and press Return.**

```
Specify next volume #: 1
```

The file is restored to the current working directory.

**7. To keep the mode of the current directory unchanged, type `n` and press Return at the `set owner/mode` prompt.**

```
set owner/mode for '.'? [yn] n
```

**8. Verify the restored files.**

**a. List the restored files and directories.**

```
# ls -l
```

A list of files and directories is displayed.

**b. Check the list to be sure all the files and directories you specified in the list have been restored.**

**c. Move the files to the proper directories.**

## Example—Restoring Specific Files Non-Interactively

The following example restores the `passwd` and `shadow` files to the `/var/tmp` directory.

```
# cd /var/tmp
# ufsrestore xvf /dev/rmt/0 ./etc/passwd ./etc/shadow
Verify volume and initialize maps
Media block size is 126
Dump   date: Tue Jun 09 14:30:16 1998
Dumped from: the epoch
Level 0 dump of / on pluto:/dev/dsk/c0t3d0s0
Label: none
Extract directories from tape
Initialize symbol table.
Warning: ./etc: File exists
Extract requested files
You have not read any volumes yet.
Unless you know which volume your file(s) are on you should start
with the last volume and work towards the first.
Specify next volume #: 1
extract file ./etc/passwd
Add links
Set directory mode, owner, and times.
set owner/mode for `.'? [yn] n
Directories already exist, set modes anyway? [yn] n
# cd etc
# mv passwd /etc
# mv shadow /etc
# ls -l etc
```

## ▼ How to Restore Files Using a Remote Tape Drive

You can restore files from a remote tape drive by adding *remote-host*: to the front of the tape device name when using the `ufsrestore` command.

```
ufsrestore xf [user@]remote-host:/dev/rmt/n filename
```

### Example—Restoring Files Using a Remote Drive

The following example restores files using a remote tape drive `/dev/rmt/0` on the system `venus`.

```
# ufsrestore xf venus:/dev/rmt/0 filename
```

## ▼ How to Restore a Complete File System

---

**Note** - You cannot use this procedure to restore root (/) or /usr. See “How to Restore the root (/) and /usr File Systems” on page 573 for instructions on restoring these file systems.

---

1. **Become superuser.**
2. **If necessary, unmount the file system.**

```
# umount /dev/rdisk/device-name
```

3. **Create the new file system with the `newfs(1M)` command.**

```
# newfs /dev/rdisk/device-name
```

You are asked if you want to construct a new file system on the raw device. Verify that the device-name is correct so you don't wipe out the wrong file system.

4. **Confirm that the new file system should be created.**

```
newfs: construct a new file system /dev/rdisk/cwtxdysz:(y/n)? y
```

The new file system is created.

5. **Mount the new file system on a temporary mount point.**

```
# mount /dev/dsk/device-name /mnt
```

6. **Change to the `/mnt` directory.**

```
# cd /mnt
```

You have changed to the mount-point directory.

7. **Write-protect the tapes.**
8. **Insert the first volume of the level 0 tape into the tape drive.**
9. **Use the `ufsrestore` command to restore the files on the tapes.**

```
# ufsrestore rvf /dev/rmt/n
```

The level 0 dump is restored. If the dump required multiple tapes, you will be prompted to load each tape in order.

**10. Remove the tape and load the next level tape in the drive.**

Always restore tapes starting with 0 and continuing until you reach the highest level.

**11. Repeat Step 7 on page 570 through Step 10 on page 571 for each level of dump, from the lowest to the highest level.**

**12. Verify the file system is restored.**

```
# ls
```

**13. Remove the `restoresymtable` file.**

```
# rm restoresymtable
```

The `restoresymtable` file created by `ufsrestore` is removed.

**14. Change to another directory.**

```
# cd /
```

**15. Unmount the newly restored file system.**

```
# umount /mnt
```

**16. Remove the last tape and insert a new tape that is not write-protected in the tape drive.**

**17. Use the `ufsdump` command to make a level 0 backup of the newly restored file system.**

```
# ufsdump 0uf /dev/rmt/n /dev/rdisk/device-name
```

You should always do an immediate backup of a newly created file system, because `ufsrestore` repositions the files and changes the inode allocation (the restored file system will appear to have changed since the previous backup).

**18. Mount the restored file system.**

```
# mount /dev/dsk/device-name mount-point
```

The restored file system is mounted and available for use.

#### 19. Verify the restored and mounted file system is available.

```
# ls mount-point
```

## Example—Restoring a Complete File System

The following example restores the /export/home file system.

```
# umount /export/home
# newfs /dev/rdisk/c0t3d0s7
newfs: construct a new file system /dev/rdisk/c0t3d0s7: (y/n)? y
/dev/rdisk/c0t3d0s7:
410400 sectors in 270 cylinders of 19 tracks, 80 sectors
200.4MB in 17 cyl groups (16 c/g, 11.88MB/g, 5696 i/g)
super-block backups (for fsck -F ufs -o b=#) at:
32, 24432, 48832, 73232, 97632, 122032, 146432, 170832, 195232, 219632,
244032, 268432, 292832, 317232, 341632, 366032, 390432,
# mount /dev/dsk/c0t3d0s7 /mnt
# cd /mnt
# ufsrestore rvf /dev/rmt/0
Verify volume and initialize maps
Media block size is 126
Dump date: Tue Jun 09 15:01:03 1998
Dumped from: the epoch
Level 0 dump of /export/home on pluto:/dev/dsk/c0t3d0s7
Label: none
Begin level 0 restore
Initialize symbol table.
Extract directories from tape
Calculate extraction list.
Warning: ./lost+found: File exists
Make node ./kryten
Make node ./kryten/letters
Make node ./kryten/memos
Make node ./kryten/reports
Make node ./rimmer
Make node ./rimmer/sc.directives
Make node ./rimmer/tests
Make node ./rimmer/answers
Extract new leaves.
Check pointing the restore
# ls
# rm restoresymtable
# cd /
# umount /mnt
# ufsdump 0ucf /dev/rmt/0 /export/home
```

(continued)

(Continuation)

```
# mount /dev/dsk/c0t3d0s7 /export/home
# ls /export/home
```

## ▼ How to Restore the root (/) and /usr File Systems

1. **Add a new system disk to the system where the root (/) and /usr file systems will be restored.**

For a detailed description about adding a system disk, refer to Chapter 23 or Chapter 24.

2. **Mount the new file system on a temporary mount point.**

```
# mount /dev/dsk/device-name /mnt
```

3. **Change to the /mnt directory.**

```
# cd /mnt
```

4. **Write-protect the tapes.**

5. **Use the `ufsrestore` command to restore the root file system.**

```
# ufsrestore rvf /dev/rmt/n
```

The level 0 tape is restored.

6. **Remove the tape and load the next level tape in the drive.**

Always restore tapes starting with 0 and continuing from lowest to highest level.

7. **Continue to use the `ufsrestore` command as needed.**

```
# ufsrestore rvf /dev/rmt/n
```

The next level tape is restored.

**8. Repeat Step 6 on page 573 and Step 7 on page 573 for each additional tape.**

**9. Verify the file system is restored.**

```
# ls
```

**10. Remove the `restoresymtable` file.**

```
# rm restoresymtable
```

Removes the `restoresymtable` file that is created and used by `ufsrestore` to check point the restore.

**11. Change to the root (`/`) directory.**

```
# cd /
```

**12. Unmount the newly created file system.**

```
# umount /mnt
```

**13. Check the new file system.**

```
# fsck /dev/rdisk/device-name
```

The restored file system is checked for consistency.

**14. Create the boot blocks on the root partition by using the `installboot(1M)` command.**

```
# installboot /usr/platform/`uname-i`/lib/fs/ufs/bootblk /dev/rdisk/devicename
```

See “Example—Restoring the root (`/`) File System on a SPARC System” on page 575 for an example of using the `installboot` command on a SPARC system or “Example—Restoring the root (`/`) File System on an x86 System” on page 575 for an example of using the `installboot` command on an x86 system.

**15. Insert a new tape in the tape drive.**

**16. Back up the new file system.**



```
# ufsdump 0uf /dev/rmt/n /dev/rdisk/device-name
```

A level 0 backup is performed. Always do an immediate backup of a newly created file system because `ufsrestore` repositions the files and changes the inode allocation.

**17. Repeat steps 5 through 18 for the `/usr` file system, if necessary.**

**18. Reboot the system.**

```
# init 6
```

The system is rebooted.

## Example—Restoring the root (/) File System on a SPARC System

```
# mount /dev/dsk/c0t3d0s0 /mnt
# cd /mnt
# tapes
# ufsrestore rvf /dev/rmt/0
# ls
# rm restoresymtable
# cd /
# umount /mnt
# fsck /dev/rdisk/c0t3d0s0
# installboot /usr/platform/sun4m/lib/fs/ufs/bootblk /dev/rdisk/c0t3d0s0
# ufsdump 0uf /dev/rmt/0 /dev/rdisk/c0t3d0s0
# init 6
```

## Example—Restoring the root (/) File System on an x86 System

```
# mount /dev/dsk/c0t3d0s0 /mnt
# cd /mnt
# tapes
# ufsrestore rvf /dev/rmt/0
# ls
# rm restoresymtable
# cd /
# umount /mnt
# fsck /dev/rdisk/c0t3d0s0
# installboot /usr/platform/`uname -i`/lib/fs/ufs/pboot /usr/platform/`uname -i`/lib/fs/ ufs/bootblk /dev/rdisk/
# ufsdump 0uf /dev/rmt/0 /dev/rdisk/c0t3d0s0
```

(continued)

(Continuation)

```
# init 6
```

## The `ufsdump` and `ufsrestore` Commands (Reference)

---

This chapter contains reference information on the `ufsdump` and `ufsrestore` commands.

This is a list of reference information in this chapter.

- “How `ufsdump` Works” on page 577
- “Options and Arguments for the `ufsdump` Command” on page 582
- “The `ufsdump` Command and Security Issues” on page 585
- “Options and Arguments for the `ufsrestore` Command” on page 585

---

### How `ufsdump` Works

The `ufsdump` command makes two passes when backing up a file system. On the first pass, it scans the raw device file for the file system and builds a table of directories and files in memory. It then writes the table to the backup media. In the second pass, `ufsdump` goes through the inodes in numerical order, reading the file contents and writing the data to the media.

### Determining Device Characteristics

The `ufsdump` command needs to know only an appropriate block size and how to detect the end of media.

## Detecting the End of Media

`ufsdump` writes a sequence of fixed-size records. When `ufsdump` receives notification that a record was only partially written, it assumes that it has reached the physical end of the media. This method works for most devices. If a device is not able to notify `ufsdump` that only a partial record has been written, a media error occurs as `ufsdump` tries to write.

---

**Note** - DAT devices and 8mm tape devices detect end-of-media. Cartridge tape devices and 1/2-inch tape devices do not detect end-of-media.

---

## Copying Data

The `ufsdump` command copies data only from the raw disk slice. If the file system is still active, anything in memory buffers is probably not copied. The backup done by `ufsdump` does not copy free blocks, nor does it make an image of the disk slice. If symbolic links point to files on other slices, the link itself is copied.

## The Role of the `/etc/dumpdates` File

The `ufsdump` command, when used with the `-u` option, maintains and updates the `/etc/dumpdates` file. Each line in `/etc/dumpdates` shows the file system backed up, the level of the last backup, and the day, date, and time of the backup. Here is a typical `/etc/dumpdates` file from a file server:

<code>/dev/rdisk/c0t3d0s0</code>	0 Tue Jun 9 14:30:16 1998
<code>/dev/rdisk/c0t3d0s0</code>	9 Tue Jun 9 11:04:41 1998
<code>/dev/rdisk/c0t3d0s7</code>	0 Tue Jun 9 13:54:27 1998

When you do an incremental backup, the `ufsdump` command consults `/etc/dumpdates` to find the date of the most recent backup of the next lower level. Then it copies to the media all files that were modified since the date of that lower-level backup. After the backup is complete, a new information line, describing the backup you just completed, replaces the information line for the previous backup at that level.

Use the `/etc/dumpdates` file to verify that backups are being done. This verification is particularly important if you are having equipment problems. If a backup cannot be completed because of equipment failure, the backup is not recorded in the `/etc/dumpdates` file.

If you need to restore an entire disk, check the `/etc/dumpdates` file for a list of the most recent dates and levels of backups so that you can determine which tapes you need to restore the entire file system.

---

**Note** - The `/etc/dumpdates` file is a text file that can be edited, but edit it only at your own risk. If you make changes to the file that do not match your archive tapes, you may not be able to find the tapes (or files) you need.

---

## Backup Device (*dump-file*) Argument

The *dump-file* argument (to the `-f` option) specifies the destination of the backup, which can be one of the following:

- Local tape drive or diskette drive
- Remote tape drive or diskette drive
- Standard output

Use this argument when the destination is not the default local tape drive `/dev/rmt/0`. If you use the `-f` option, then you must specify a value for *dump-file*.

---

**Note** - The *dump-file* argument can also point to a file on a local or remote disk, which, if used by mistake, can fill up a file system.

---

## Local Tape or Diskette Drive

Typically, *dump-file* specifies a raw device file for a tape or diskette drive. When `ufsdump` writes to an output device, it creates a single backup file which may span multiple tapes or diskettes.

You specify the tape or diskette device on your system using a device abbreviation. The first device is always 0. For example, if you have a SCSI tape controller and one QIC-24 tape drive that uses medium-density formatting, use this device name:

```
/dev/rmt/0m
```

When you specify a tape device name, you can also type the letter “n” at the end of the name to indicate that the tape drive should not rewind after the backup is completed. For example:

```
/dev/rmt/0mn
```

Use the “no-rewind” option if you want to put more than one file onto the tape. If you run out of space during a backup, the tape does not rewind before `ufsdump` asks for a new tape. See “Backup Device Names” on page 620 for a complete description of device naming conventions.

## Remote Tape or Diskette Drive

You specify a remote tape or diskette drive using the syntax *host:device*. `ufsdump` writes to the remote device when root on the local system has access to the remote system. If you usually run `ufsdump` as root, the name of the local system must be included in the `/.rhosts` file on the remote system. If you specify the device as *user@host:device*, `ufsdump` tries to access the device on the remote system as the specified user. In this case, the specified user must be included in the `/.rhosts` file on the remote system.

Use the naming convention for the device that matches the operating system for the system on which the device resides, not the system from which you run the `ufsdump` command. If the drive is on a system that is running a previous SunOS release (for example, 4.1.1), use the SunOS 4.1 device name (for example, `/dev/rst0`). If the system is running Solaris software, use the SunOS 5.7 convention (for example, `/dev/rmt/0`).

---

**Note** - You must specify remote devices explicitly with the *dump-file* argument. In previous SunOS releases, the `rdump` command directed the output to the remote device defined by the `dumphost` alias. `ufsdump` does not have an `rufsdump` counterpart.

---

## Standard Output

When you specify a dash (-) as the *dump-file* argument, `ufsdump` writes to the standard output.

---

**Note** - The `-v` option (verify) does not work when the *dump-file* argument is standard output.

---

You can use the `ufsdump` and `ufsrestore` commands in a pipeline to copy a file system by writing to the standard output with `ufsdump` and reading from the standard input with `ufsrestore`, as shown in this example:

```
# ufsdump 0f - /dev/rdsk/c0t0d0s7 | (cd /home; ufsrestore xf -)
```

## Specifying Files to Back Up

You must always include *files-to-backup* as the last argument on the command line. This argument specifies the source or contents of the backup. It usually identifies a file system but can also identify individual files or directories.

For a file system, specify the raw device file for a disk slice. It includes the disk controller abbreviation (c), the target number (t) for SCSI devices only, a number indicating the disk number (d), and the slice number (s). For example, if you have a

SCSI disk controller on your standalone system (or server) and you want to back up `/usr` located in slice 6, specify the device as follows:

```
/dev/rdisk/c0t0d0s6
```

You can specify the file system by its mount point directory (for example, `/home`), as long as there is an entry for it in the `/etc/vfstab` file.

See “Backup Device Names” on page 620 for a complete description of device naming conventions.

For individual files or directories, type one or more names separated by spaces.

---

**Note** - When you use `ufsdump` to back up one or more directories or files (rather than a whole file system), a level 0 backup is done. Incremental backups do not apply.

---

## End-of-Media Detection

The `ufsdump` command automatically detects the end-of-media for most devices. Therefore, you do not usually need to use the `-c`, `-d`, `-s`, and `-t` options to perform multivolume backups.

The only time you need to use the end-of-media options is when `ufsdump` does not understand the way the device detects the end-of-media or you are going to restore the files on a system with an older version of the `restore` command. To ensure compatibility with older versions of the `restore` command, the `size` option can still force `ufsdump` to go to the next tape or diskette before reaching the end of the current tape or diskette.

## Specifying Tape Characteristics

If you do not specify any tape characteristics, the `ufsdump` command uses a set of defaults. You can specify tape cartridge (`c`), density (`d`), size (`s`), and number of tracks (`t`). Note that you can specify the options in any order as long as the arguments that follow match the order of the options.

## Limitations of the `ufsdump` Command

Table 36–1 lists tasks you cannot perform with the `ufsdump` command.

**TABLE 36-1** Tasks You Cannot Perform With the `ufsdump` Command

The <code>ufsdump</code> Command Does Not ...	Comments
Automatically calculate the number of tapes or diskettes needed for backing up file systems	You can use the dry run mode (S option) to determine the amount of space that is needed before actually backing up file systems.
Provide built-in error checking to minimize problems when backing up an active file system	—
Enable you to back up files that are remotely mounted from a server	Files on the server must be backed up on the server itself. Users are denied permission to run <code>ufsdump</code> on files they own that are located on a server.

# Options and Arguments for the `ufsdump` Command

This section describes in detail the options and arguments for the `ufsdump` command. The syntax for the `ufsdump` command is:

```
/usr/sbin/ufsdump [options] [arguments] files-to-back-up
```

<i>options</i>	Is a single string of one-letter option names.
<i>arguments</i>	Identifies option arguments and may be multiple strings. The option letters and the arguments that go with them must be in the same order
<i>files-to-back-up</i>	Identifies the files to back up and these arguments must always come last.

## Default Command Options

If you run the `ufsdump` command without any options, use this syntax:

```
# ufsdump files-to-back-up
```



`ufsdump` uses these options, by default:

```
ufsdump 9uf /dev/rmt/0 files-to-back-up
```

These options do a level 9 incremental backup to the default tape drive at its preferred density.

## Options for the `ufsdump` Command

Table 36–2 describes the options for the `ufsdump` command.

**TABLE 36–2** Options for the `ufsdump` Command

Option	Description
0–9	Backup level. Level 0 is for a full backup of the whole file system specified by <i>files-to-backup</i> . Levels 1–9 are for incremental backups of files that have changed since the last lower-level backup.
a <i>archive-file</i>	Archive file. Store (archive) a backup table of contents in a specified file on the disk. The file can be understood only by <code>ufsrestore</code> , which uses it to determine whether a file to be restored is present in a backup file, and if so, on which volume of the media it resides.
b <i>factor</i>	Blocking factor. The number of 512-byte blocks to write to tape at a time.
c	Cartridge. Back up to cartridge tape. When end-of-media detection applies, this option sets the block size to 126.
d <i>bpi</i>	Tape density. You need to use this option only when <code>ufsdump</code> cannot detect the end of the media.
D	Diskette. Back up to diskette.
f <i>dump-file</i>	Dump file. Write the files to the destination specified by <i>dump-file</i> instead of the default device. If the file is specified as <i>user@system:device</i> , <code>ufsdump</code> attempts to execute as the specified user on the remote system. The specified user must have a <code>/</code> entry in the <code>.rhosts</code> file on the remote system that allows the user invoking the command on the local system to access the remote system.

**TABLE 36-2** Options for the `ufsdump` Command *(continued)*

Option	Description
<code>l</code>	Autoload. Use this option if you have an autoloading (stackloader) tape drive. When the end of a tape is reached, this option takes the drive offline and waits up to two minutes for the tape drive to be ready again. If the drive is ready within two minutes, it continues. If it is not ready after two minutes, it prompts the operator to load another tape.
<code>n</code>	Notify. When intervention is needed, send a message to all terminals of all users in the <code>sys</code> group.
<code>o</code>	Offline. When finished with a tape or diskette, take the drive offline, rewind (if tape), and if possible remove the media (for example, eject a diskette or remove 8-mm autoloaded tape).
<code>s size</code>	Size. Specify the length of tapes in feet or number of 1024-byte blocks for diskettes. You need to use this option only when <code>ufsdump</code> cannot detect the end of the media.
<code>S</code>	Estimate size of backup. Determine the amount of space that is needed to perform the backup, without actually doing it, and output a single number indicating the estimated size of the backup in bytes.
<code>t tracks</code>	Tracks. Specify the number of tracks for 1/4-inch cartridge tape. You need to use this option only when <code>ufsdump</code> cannot detect the end of the media.
<code>u</code>	Update the dump record. For a completed backup on a file system, add an entry to the <code>/etc/dumpdates</code> file. The entry indicates the device name for the file system's disk slice, the backup level (0-9), and the date. No record is written when you do not use the <code>u</code> option or when you back up individual files or directories. If a record already exists for a backup at the same level, it is replaced.
<code>v</code>	Verify. After each tape or diskette is written, verify the contents of the media against the source file system. If any discrepancies occur, prompt the operator to mount new media, then repeat the process. Use this option on an unmounted file system only, because any activity in the file system causes it to report discrepancies.

**TABLE 36-2** Options for the `ufsdump` Command *(continued)*

Option	Description
<code>w</code>	Warning. List the file systems appearing in <code>/etc/dumpdates</code> that have not been backed up within a day. When you use this option all other options are ignored.
<code>W</code>	Warning with highlight. Show all the file systems that appear in <code>/etc/dumpdates</code> and highlight those file systems that have not been backed up within a day. When you use this option all other options are ignored.

**Note** - The `/etc/vfstab` file does not contain information about how often to back up a file system.

## The `ufsdump` Command and Security Issues

If you are concerned about security:

- Require root access for the `ufsdump` command.
- Ensure root access entries are removed from `.rhosts` files on clients and servers if doing centralized backups.

For general information on security, see “Managing System Security (Overview)” in *System Administration Guide, Volume II*.

## Options and Arguments for the `ufsrestore` Command

### Command Syntax

The syntax of the `ufsrestore` command is:

```
ufsrestore [options][arguments][filename ...]
```

<i>options</i>	Is a single string of one-letter option names. You must choose one and only one of these options: <i>i</i> , <i>r</i> , <i>R</i> , <i>t</i> , or <i>x</i> .
<i>arguments</i>	Follows the option string with the arguments that match the options. The option names and the arguments that go with them must be in the same order.
<i>filename</i>	Specifies files to be restored as arguments to the <i>x</i> or <i>t</i> options, and must always come last.

## Options and Arguments

You must use one (and only one) of the `ufsrestore` options shown in Table 36-3.

**TABLE 36-3** One Required Option for the `ufsrestore` Command

Option	Description
<i>i</i>	Interactive. Runs <code>ufsrestore</code> in an interactive mode. In this mode, you can use a limited set of shell-like commands to browse the contents of the media and select individual files or directories to restore. See “Commands for Interactive Restore” on page 588 for a list of available commands.
<i>r</i>	Recursive. Restores the entire contents of the media into the current working directory (which should be the top level of the file system). Information used to restore incremental dumps on top of the full dump (e.g., <code>restoresymtable</code> ) is also included. To completely restore a file system, use this option to restore the full (level 0) dump and each subsequent incremental dump. Although intended for a new file system (one just created with the <code>newfs</code> command), files not on the backup media are preserved.
<i>R</i>	Resume restoring. Prompts for the volume from which to resume restoring and restarts from a checkpoint. You rerun the <code>ufsrestore</code> command with this option after a full restore ( <i>r</i> option) is interrupted.

**TABLE 36-3** One Required Option for the `ufsrestore` Command (continued)

Option	Description
<code>x [filename...]</code>	Extract. Selectively restores the files you specify by the <i>filename</i> argument. <i>filename</i> can be a list of files and directories. All files under a specified directory are restored unless you also use the <code>h</code> option also. If you omit <i>filename</i> or enter “.” for the root directory, all files on all volumes of the media (or from standard input) are restored. Existing files are overwritten, and warnings are displayed.
<code>t [filename...]</code>	Table of contents. Checks the files specified in the <i>filename</i> argument against the media. For each file, lists the full file name and the inode number (if the file is found) or indicates the file is not on the “volume” (meaning any volume in a multivolume dump). If you do not enter the <i>filename</i> argument, all files on all volumes of the media are listed (without distinguishing on which volume files are located). If you also use the <code>h</code> option, only the directory files specified in <i>filename</i> , not their contents, are checked and listed. The table of contents is read from the first volume of the media, or, if you use the <code>a</code> option, from the specified archive file. This option is mutually exclusive with the <code>x</code> and <code>r</code> options.

In addition to one of the options shown in Table 36-3, you can choose from the options shown in Table 36-4.

**TABLE 36-4** Additional Options for the `ufsrestore` Command

Option	Description
<code>a archive-file [filename...]</code>	Takes the dump table of contents from the specified <i>archive-file</i> instead of from the media (first volume). You can use this option in combination with the <code>t</code> , <code>i</code> , or <code>x</code> options to check for the files in the dump without having to mount any media. If you use it with the <code>x</code> and interactive extract options, you will be prompted to mount the appropriate volume before extracting the file(s).
<code>b factor</code>	Blocking factor. Number of 512-byte blocks read from tape at a time. By default, <code>ufsrestore</code> tries to figure out the block size that was used in writing the tape.
<code>d</code>	Debug. Turn on debugging messages.

**TABLE 36-4** Additional Options for the `ufsrestore` Command *(continued)*

Option	Description
<code>f backup-file</code>	Backup file. Reads the files from the source indicated by <i>backup-file</i> , instead of from the default device file <code>/dev/rmt/0m</code> . If you use the <code>f</code> option, you must specify a value for <i>backup-file</i> . When <i>backup-file</i> is of the form <i>system:device</i> , <code>ufsrestore</code> reads from the remote device. You can also use the <i>backup-file</i> argument to specify a file on a local or remote disk. If <i>backup-file</i> is '-', the files are read from standard input.
<code>h</code>	Turns off directory expansion. Only the directory file you specify is extracted or listed.
<code>m</code>	Restores specified files into the current directory on the disk regardless of where they are located in the backup hierarchy and renames them with their inode number. For example, if the current working directory is <code>/files</code> , a file in the backup named <code>./dready/fcs/test</code> with inode number 42, is restored as <code>/files/42</code> . This option is useful only when you are extracting a few files.
<code>s n</code>	Skips to the <i>n</i> th backup file on the media (first volume). This option is useful when you put more than one backup on a single tape.
<code>v</code>	Verbose. Displays the names and inode numbers of each file as it is restored.
<code>y</code>	Continues when errors occur reading the media and tries to skip over bad blocks instead of stopping and asking whether to continue. This option tells the command to assume a yes response.

## Commands for Interactive Restore

**TABLE 36-5** Commands for Interactive Restore

Option	Description
<code>ls [directory-name]</code>	Lists the contents of either the current directory or the specified directory. Directories are marked by a / suffix and entries in the current list to be restored (extracted) are marked by an * prefix. Inode numbers are shown if the verbose option is used.
<code>cd directory-name</code>	Changes to the specified directory in the backup hierarchy.
<code>add [filename]</code>	Adds the current directory or the specified file or directory to the list of files to extract (restore). If you do not use the <code>h</code> option, all files in a specified directory and its subdirectories are added to the list. Note that all the files you want to restore to a directory might not be on a single backup tape or diskette. You might need to restore from multiple backups at different levels to get the latest revisions of all the files.
<code>delete [filename]</code>	Deletes the current directory or the specified file or directory from the list of files to extract (restore). If you do not use the <code>h</code> option, all files in the specified directory and its subdirectories are deleted from the list. Note that the files and directories are deleted only from the extract list you are building. They are not deleted from the media or the file system.
<code>extract</code>	Extracts the files in the list and restores them relative to the current working directory on the disk. Specify <code>1</code> when asked for a volume number for a single-volume backup. If you are doing a multitape or multidiskette restore and restoring a small number of files, start with the last tape or diskette instead.
<code>help</code>	Displays a list of commands you can use in interactive mode.
<code>pwd</code>	Displays the path name of the current working directory in the backup hierarchy.
<code>q</code>	Quits interactive mode without restoring any additional files.
<code>setmodes</code>	Lets you set the mode for files to be restored to match the mode of the root directory of the file system from which they were backed up. You are prompted with: <code>set owner/mode for '. '[yn]? Type y (for yes) to set the mode (permissions, owner, times) of the current directory to match the root directory of the file system from which they were backed up. Use this mode when restoring a whole file system. Type n (for no) to leave the mode of the current directory unchanged. Use this mode when restoring part of a backup to a directory other than the one from which the files were backed up.</code>

**TABLE 36-5** Commands for Interactive Restore *(continued)*

Option	Description
<code>verbose</code>	Turns on or off the verbose option (which can also be entered as <code>v</code> on the command line outside of interactive mode). When verbose is on, the interactive <code>ls</code> command lists inode numbers and the <code>ufsrestore</code> command displays information on each file as it is extracted.
<code>what</code>	Displays the backup header from the tape or diskette.



## Copying UFS Files and File Systems (Tasks)

---

This chapter describes how to copy UFS files and file systems to disk, tape, and diskettes using various backup commands.

This is a list of the step-by-step instructions in this chapter.

- “How to Clone a Disk (`dd`)” on page 594
- “How to Copy Directories Between File Systems (`cpio`)” on page 597
- “How to Copy Files to a Tape (`tar`)” on page 601
- “How to List the Files on a Tape (`tar`)” on page 602
- “How to Retrieve Files From a Tape (`tar`)” on page 603
- “How to Copy All Files in a Directory to a Tape (`cpio`)” on page 605
- “How to List the Files on a Tape (`cpio`)” on page 606
- “How to Retrieve All Files From a Tape (`cpio`)” on page 607
- “How to Retrieve Specific Files From a Tape (`cpio`)” on page 608
- “How to Copy Files to a Remote Tape Drive (`tar` and `dd`)” on page 609
- “How to Extract Files From a Remote Tape Drive” on page 610
- “How to Copy Files to a Single Formatted Diskette (`tar`)” on page 612
- “How to List the Files on a Diskette (`tar`)” on page 613
- “How to Retrieve Files From a Diskette (`tar`)” on page 614
- “How to Archive Files to Multiple Diskettes” on page 615
- “How to Create an Archive for Older SunOS Releases” on page 615
- “How to Retrieve `bar` Files From a Diskette” on page 616

## Commands for Copying File Systems

When you need to back up and restore complete file systems, use the `ufsdump` and `ufsrestore` commands described in Chapter 36. When you want to copy or move individual files, portions of file systems, or complete file systems, you can use the procedures described in this chapter as an alternative to `ufsdump` and `ufsrestore`.

Table 37-1 describes when to use the various backup commands.

**TABLE 37-1** When to Use Various Backup Commands

If You Want To ...	Then Use ...	Reference
Back up file systems to tape	<code>ufsdump(1M)</code>	“How to Do Backups to Tape” on page 554
Restore file systems from tape	<code>ufsrestore(1M)</code>	“How to Restore a Complete File System” on page 570
Transport files to other systems	<code>pax(1)</code> , <code>tar(1)</code> , or <code>cpio(1)</code>	“Copying Files and File Systems to Tape” on page 599
Copy files or file systems between disks	<code>dd(1M)</code>	“How to Clone a Disk ( <code>dd</code> )” on page 594
Copy files to diskette	<code>tar(1)</code>	“How to Copy Files to a Single Formatted Diskette ( <code>tar</code> )” on page 612

Table 37-2 describe various backup and restore commands.

**TABLE 37-2** Summary of Various Backup Commands

Command Name	Aware of File System Boundaries?	Support Multi-Volume Backups?	Physical or Logical Copy?
<code>volcopy</code>	Yes	Yes	Physical
<code>tar</code>	No	No	Logical
<code>cpio</code>	No	Yes	Logical
<code>pax</code>	Yes	Yes	Logical
<code>dd</code>	Yes	No	Physical
<code>ufsdump/</code> <code>ufsrestore</code>	Yes	Yes	Logical

The following sections describe the advantages and disadvantages of each method and provide examples of how to use the commands.

## Copying File Systems Between Disks

Two commands are used to copy file systems between disks:

- `volcopy`
- `dd`

The next section describes how to use the `dd` command to copy file systems between disks.

## Making a Literal File System Copy

The `dd` command makes a literal (block-level) copy of a complete UFS file system to another file system or to a tape. By default, the `dd` command copies its standard input to its standard output.

---

**Note** - Do not use the `dd` command with variable-length tape drives without specifying an appropriate block size.

---

You can specify a device name in place of the standard input or the standard output or both. In this example, contents of the diskette are copied to a file in the `/tmp` directory:

```
$ dd < /floppy/floppy0 > /tmp/output.file
2400+0 records in
2400+0 records out
```

The `dd` command reports on the number of blocks it reads and writes. The number after the `+` is a count of the partial blocks that were copied. The default block size is 512 bytes.

The `dd` command syntax is different from most other commands. Options are specified as *keyword=value* pairs, where *keyword* is the option you want to set and *value* is the argument for that option. For example, you can replace the standard input and output with this syntax:

```
$ dd if=input-file of=output-file
```

For example, to use the *keyword=value* pairs instead of the redirect symbols in the previous example, you would type:

```
$ dd if=/floppy/floppy0 of=/tmp/output.file
```

## ▼ How to Clone a Disk (`dd`)

1. Make sure the source and destination disks have the same disk geometry.
2. Become superuser.
3. Create the `/reconfigure` file on the system so the system will recognize the clone disk to be added when it reboots.

```
# touch /reconfigure
```

4. Shut down the system.

```
# init 0
```

5. Attach the clone disk to the system.

6. Boot the system.

```
ok boot
```

7. Use the `dd` command to copy the master disk to the clone disk.

```
# dd if=/dev/rdisk/device-name of=/dev/rdisk/device-name bs=blocksize
```

`if=/dev/rdisk/device-name` Represents the overlap slice of the master disk device, usually slice 2.

`of=/dev/rdisk/device-name` Represents the overlap slice of the clone disk device, usually slice 2.

`bs=blocksize` Block size, such as 128 Kbytes or 256 Kbytes. A large block size value will decrease the time to copy.

8. Check the new file system.

```
# fsck /dev/rdisk/device-name
```

9. Mount the clone disk's root (/) file system.

```
# mount /dev/dsk/device-name /mnt
```

10. Edit the clone disk's `/etc/vfstab` to reference the correct device names.

For example, changing all instances of `c0t3d0` with `c0t1d0`.

11. Unmount the clone disk's root (/) file system.

```
# umount /mnt
```

12. Shut down the system.

```
# init 0
```

13. Boot from the clone disk to single-user mode.

```
# boot diskn -s
```

---

**Note** - The `installboot` command is not needed for the clone disk because the boot blocks are copied as part of the overlap slice.

---

#### 14. Unconfigure the clone disk.

```
# sys-unconfig
```

The system is shut down after it is unconfigured.

#### 15. Boot from the clone disk again and provide its system information, such as host name, time zone, etc.

```
# boot diskn
```

#### 16. Log in as superuser to verify the system information once the system is booted.

```
hostname console login:
```

### Example—Cloning a Disk (dd)

```
# init 0
ok boot
# dd if=/dev/rdisk/c0t0d0s2 of=/dev/rdisk/c0t2d0s2 bs=128k
# fsck /dev/rdisk/c0t2d0s2
# mount /dev/dsk/c0t2d0s2 /mnt
# cd /mnt/etc
# vi vfstab
(Modify entries for the new disk)
# cd /
# umount /mnt
# init 0
# boot disk2 -s
# sys-unconfig
# boot disk2
```

---

# Copying Directories Between File Systems using the `cpio` Command

You can use the `cpio` (copy in and out) command to copy individual files, groups of files, or complete file systems. This section describes how to use the `cpio` command to copy complete file systems.

The `cpio` command is an archiving program that takes a list of files and copies them into a single, large output file. It inserts headers between the individual files to facilitate recovery. You can use the `cpio` command to copy complete file systems to another slice, another system, or to a media device such as tape or diskette.

Because the `cpio` command recognizes end-of-media and prompts you to insert another volume, it is the most effective command (other than `ufsdump`) to use to create archives that require multiple tapes or diskettes.

With `cpio`, you frequently use commands like `ls` and `find` to list and select the files you want to copy and then pipe the output to the `cpio` command.

## ▼ How to Copy Directories Between File Systems (`cpio`)

1. Become superuser.
2. Change to the appropriate directory.

```
# cd filesystem1
```

3. Copy the directory tree from *filesystem1* to *filesystem2* by using a combination of the `find` and `cpio` commands.

```
# find . -print -depth | cpio -pdm filesystem2
```

.	Starts in the current working directory.
-print	Prints the file names.
-depth	Descends the directory hierarchy and prints file names on the way back up.
-p	Creates a list of files.

<code>-d</code>	Creates directories as needed.
<code>-m</code>	Sets the correct modification times on directories.

The files from the directory name you specify are copied, and symbolic links are preserved.

You may also specify the `-u` option. This option forces an unconditional copy. Otherwise older files will not replace newer files. This may be useful if an exact copy of a directory is desired, and some of the files being copied may already exist in the target directory.

**4. Verify the copy was successful by displaying the destination directory contents.**

```
# cd filesystem2
# ls
```

**5. If appropriate, remove the source directory.**

```
# rm -rf filesystem1
```

## Example—Copying Directories Between File Systems (`cpio`)

```
# cd /data1
# find . -print -depth | cpio -pdm /data2
19013 blocks
# cd /data2
# ls
# rm -rf /data1
```

See `cpio(1)` for more information.



---

## Copying Files and File Systems to Tape

The `pax`, `tar`, and `cpio` commands can be used to copy files and file systems to tape. The command you choose depends on how much flexibility and precision you require for the copy. Because all three commands use the raw device, you do not need to format or make a file system on tapes before you use them.

**TABLE 37-3** Advantages and Disadvantages of `cpio`, `pax`, and `tar` Commands

Command	Function	Advantages	Disadvantages
<code>pax</code>	Copy files, special files, or file systems that require multiple tape volumes or when you want to copy files to and from POSIX-compliant systems	<ul style="list-style-type: none"> <li>■ Better portability than the <code>tar</code> or <code>cpio</code> commands for POSIX-compliant systems</li> <li>■ Multi-vendor support</li> </ul>	See disadvantages for <code>tar</code> command, except that <code>pax</code> can create multi-tape volumes
<code>tar</code>	Copy files and directory subtrees to a single tape	<ul style="list-style-type: none"> <li>■ Available on most UNIX operating systems</li> <li>■ Public domain versions are readily available</li> </ul>	<ul style="list-style-type: none"> <li>■ Is not aware of file system boundaries</li> <li>■ Full pathname length cannot exceed 255 characters</li> <li>■ Does not copy empty directories or special files such as device files</li> <li>■ Cannot be used to create multi-tape volumes</li> </ul>
<code>cpio</code>	Copy files, special files, or file systems that require multiple tape volumes or when you want to copy files from SunOS 5.7 systems to SunOS 4.0/4.1 systems	<ul style="list-style-type: none"> <li>■ Packs data onto tape more efficiently than <code>tar</code></li> <li>■ Skips over any bad spots in a tape when restoring.</li> <li>■ Provides options for writing files with different header formats (<code>tar</code>, <code>ustar</code>, <code>crc</code>, <code>odc</code>, <code>bar</code>) for portability between different system types</li> <li>■ Creates multi-tape volumes</li> </ul>	

The tape drive and device name you use depend on the hardware and configuration for each system. See “Choosing Which Media to Use” on page 619 for more information about tape drives and device names.

---

## Copying Files to Tape With `tar`

Things you should know before copying files to tape with the `tar` command:

- Copying files to a tape using the `-c` option to `tar` destroys any files already on the tape at or beyond the current tape position.
- You can use filename substitution wildcards (`?` and `*`) as part of the file names you specify when copying files. For example, to copy all documents with a `.doc` suffix, type `*.doc` as the file name argument.
- You cannot use filename substitution wildcards for extracting files from a `tar` archive.

### ▼ How to Copy Files to a Tape (`tar`)

1. **Change to the directory that contains the files you want to copy.**
2. **Insert a write-enabled tape into the tape drive.**
3. **Copy the files to tape with the `tar` command.**

```
$ tar cvf /dev/rmt/n filename ...
```

<code>c</code>	Indicates you want to create an archive.
<code>v</code>	Displays the name of each file as it is archived.
<code>f /dev/rmt/n</code>	Indicates that the archive should be written to the specified device or file.
<code>filename ...</code>	Indicates the files and directories you want to copy.

The file names you specify are copied to the tape, overwriting any existing files on the tape.

4. **Remove the tape from the drive and write the names of the files on the tape label.**

5. Verify that the files copied are on the tape using the `tar` command with the `t` option, which displays the tape's contents. See "How to List the Files on a Tape (`tar`)" on page 602 for more information on listing files on a `tar` tape.

```
$ tar tvf /dev/rmt/n
```

## Example—Copying Files to a Tape (`tar`)

The following example copies three files to the tape in tape drive 0.

```
$ cd /export/home/kryten
$ ls reports
reportA reportB reportC
$ tar cvf /dev/rmt/0 reports
a reports/ 0 tape blocks
a reports/reportA 2 tape blocks
a reports/reportB 5 tape blocks
a reports/reportC 6 tape blocks
$ tar tvf /dev/rmt/n
```

## ▼ How to List the Files on a Tape (`tar`)

1. Insert a tape into the tape drive.
2. Display the tape contents with the `tar` command.

```
$ tar tvf /dev/rmt/n
```

<code>t</code>	Lists the table of contents for the files on the tape.
<code>v</code>	Used with the <code>t</code> option, and provides detailed information about the files on the tape.
<code>f /dev/rmt/n</code>	Indicates the tape device.
<code>filename ...</code>	Indicates the files and directories you want to retrieve.

## Example—Listing the Files on a Tape (`tar`)

The following example lists the files on the tape in drive 0.

```
$ tar tvf /dev/rmt/0
drwxr-xr-x 101/10      0 Jun  9 15:40 1998 reports/
-rw-r--r-- 101/10      0 Jun  9 15:40 1998 reports/reportA
-rw-r--r-- 101/10      0 Jun  9 15:40 1998 reports/reportB
-rw-r--r-- 101/10      0 Jun  9 15:40 1998 reports/reportC
```

## ▼ How to Retrieve Files From a Tape (tar)

1. Change to the directory where you want to put the files.
2. Insert the tape into the tape drive.
3. Retrieve files from the tape using the `tar` command.

```
$ tar xvf /dev/rmt/n [filename ...]
```

<code>x</code>	Indicates that files should be extracted from the specified archive file. All of the files on the tape in the specified drive are copied to the current directory.
<code>v</code>	Displays the name of each file as it is archived.
<code>f /dev/rmt/n</code>	Indicates the tape device containing the archive.
<code>filename</code>	Specifies a file to retrieve.

4. Verify the files are copied by listing the contents of the current directory.

```
$ ls -l
```

## Example—Retrieving the Files on a Tape (tar)

The following example retrieves all the files from the tape in drive 0.

```
$ cd /var/tmp
$ tar xvf /dev/rmt/0
x reports/, 0 bytes, 0 tape blocks
x reports/reportA, 0 bytes, 0 tape blocks
x reports/reportB, 0 bytes, 0 tape blocks
```

(continued)

(Continuation)

```
x reports/reportC, 0 bytes, 0 tape blocks
x reports/reportD, 0 bytes, 0 tape blocks
$ ls -l
```

---

**Note** - The names of the files extracted from the tape must exactly match the names of the files stored on the archive. If you have any doubts about the names or paths of the files, first list the files on the tape. See “How to List the Files on a Tape (tar)” on page 602 for instructions.

---

See `tar(1)` for more information.

---

## Copying Files to a Tape With `pax`

This section describes how to copy files with the `pax` command.

### ▼ How to Copy Files to a Tape (`pax`)

1. Change to the directory that contains the files you want to copy.
2. Insert a write-enabled tape into the tape drive.
3. Copy the files to tape with the `pax` command.

```
$ pax -w -f /dev/rmt/0 filename ...
```

<code>-w</code>	Enables the write mode.
<code>-f /dev/rmt/0</code>	Identifies the tape drive.
<code>filename ...</code>	Indicates the files and directories you want to copy.

4. Verify the files are copied to tape.

```
$ pax -f /dev/rmt/0
```

5. Remove the tape from the drive and write the names of the files on the tape label.

### Example—Copying Files to a Tape (pax)

```
$ pax -w -f /dev/rmt/0 .  
$ pax -f /dev/rmt/0  
filea fileb filec
```

See `pax(1)` for more information.

## ▼ How to Copy All Files in a Directory to a Tape (cpio)

1. Insert a tape that is not write-protected into the tape drive.
2. Copy files to a tape using the `ls` and `cpio` commands.

```
$ ls | cpio -oc > /dev/rmt/n
```

`ls`

Provides the `cpio` command with a list of file names.

`cpio -oc`

Specifies that `cpio` should operate in copy-out mode (`-o`) and write header information in ASCII character format (`-c`). This ensures portability to other vendor's systems.

`> /dev/rmt/n`

Specifies the output file.

All of the files in the directory are copied to the tape in the drive you specify, overwriting any existing files on the tape. The total number of blocks copied is displayed.

3. Verify the files are copied to tape by using the following `cpio` command.

```
$ cpio -civt < /dev/rmt/0
```

4. Remove the tape from the drive and write the names of the files on the tape label.

## Example—Copying All Files in a Directory to a Tape (cpio)

The following example copies all of the files in the directory  
/export/home/kryten to the tape in tape drive 0.

```
$ cd /export/home/kryten
$ ls | cpio -oc > /dev/rmt/0
8 blocks
$ cpio -civt < /dev/rmt/0
drwxr-xr-x  2 kryten  users    0   Jun  9 15:56 1998, letters
drwxr-xr-x  2 kryten  users    0   Jun  9 15:56 1998, memos
drwxr-xr-x  2 kryten  users    0   Jun  9 15:55 1998, reports
8 blocks
$
```

## ▼ How to List the Files on a Tape (cpio)

---

**Note** - Listing the table of contents takes as long as it does to read the archive file because the `cpio` command must process the entire archive.

---

1. Insert an archive tape into the tape drive.
2. List the files on the tape using the `cpio` command.

```
$ cpio -civt < /dev/rmt/n
```

<code>-c</code>	Specifies that <code>cpio</code> should read files in ASCII character format.
<code>-i</code>	Specifies that <code>cpio</code> should operate in copy-in mode (even though its only listing files at this point).
<code>-v</code>	Displays the output in a format similar to the output from the <code>ls -l</code> command.
<code>-t</code>	Lists the table of contents for the files on the tape in the tape drive you specify.
<code>&lt; /dev/rmt/n</code>	Specifies the input file of an existing <code>cpio</code> archive.



## Example—Listing the Files on a Tape (cpio)

The following example lists the files on the tape in drive 0.

```
$ cpio -civt < /dev/rmt/0
drwxr-xr-x  2 rimmer users 0   Jun  9 16:07 1998, answers
drwxr-xr-x  2 rimmer users 0   Jun  9 16:07 1998, sc.directives
drwxr-xr-x  2 rimmer users 0   Jun  9 16:07 1998, tests
8 blocks
```

## ▼ How to Retrieve All Files From a Tape (cpio)

If the archive was created using relative path names, the input files are built as a directory within the current directory when you retrieve the files. If, however, the archive was created with absolute path names, the same absolute paths are used to recreate the file on your system.



---

**Caution** - Using absolute path names can be dangerous because you may overwrite existing files on your system.

---

1. **Change to the directory where you want to put the files.**
2. **Insert the tape into the tape drive.**
3. **Copy all files from the tape to the current directory using the `cpio` command.**

```
$ cpio -icvd < /dev/rmt/n
```

<code>-i</code>	Reads in the contents of the tape.
<code>-c</code>	Specifies that <code>cpio</code> should read files in ASCII character format.
<code>-v</code>	Displays the files being retrieved in a format similar to the output from the <code>ls</code> command.
<code>-d</code>	Create directories as needed.
<code>&lt; /dev/rmt/n</code>	Specifies the output file.

4. **Verify the files are copied by listing the contents of the current directory.**

```
$ ls -l
```

## Example—Retrieving All Files From a Tape (cpio)

The following example retrieves all files from the tape in drive 0.

```
$ cd /var/tmp
cpio -icvd < /dev/rmt/0
answers
sc.directives
tests
8 blocks
$ ls -l
```

## ▼ How to Retrieve Specific Files From a Tape (cpio)

1. Change to the directory where you want to put the files.
2. Insert the tape into the tape drive.
3. Retrieve a subset of files from a tape using the `cpio` command.

```
$ cpio -icv "*file" < /dev/rmt/n
```

<code>-i</code>	Reads in the contents of the tape.
<code>-c</code>	Specifies that <code>cpio</code> should read headers in ASCII character format.
<code>-v</code>	Displays the files as they are retrieved in a format similar to the output from the <code>ls</code> command.
<code>"*file"</code>	Specifies that all of the files that match the pattern are copied to the current directory. You can specify multiple patterns, but each must be enclosed in double quotation marks.
<code>&lt; /dev/rmt/n</code>	Specifies the input file.

4. Verify the files are copied by listing the contents of the current directory.

```
$ ls -l
```

## Example—Retrieving Specified Files From a Tape (cpio)

The following example retrieves all files with the suffix `chapter` from the tape in drive 0.

```
$ cd /home/smith/Book
$ cpio -icv "**chapter" < /dev/rmt/0
Boot.chapter
Directory.chapter
Install.chapter
Intro.chapter
31 blocks
$ ls -l
```

See `cpio(1)` for more information.

## ▼ How to Copy Files to a Remote Tape Drive (`tar` and `dd`)

1. **The following prerequisites must be met to use a remote tape drive:**
  - The local hostname (and optionally the username of the user doing the copy) must appear in the remote system's `/etc/hosts.equiv` file, or the user doing the copy must have his or her home directory accessible on the remote machine, and have the local machine name in `$HOME/.rhosts`. See `hosts.equiv(4)` for more information.
  - An entry for the remote system must be in the local system's `/etc/inet/hosts` file or in the name service `hosts` file.
2. **To test whether or not you have the appropriate permission to execute a remote command, try the following.**

```
$ rsh remotehost echo test
```

If "test" is echoed back to you, you have permission to execute remote commands. If "Permission denied" is echoed, check your setup as described in step 1 above.

3. **To copy files to a remote tape drive use the `tar` and `dd` commands.**

```
$ tar cf - files | rsh remotehost dd of=/dev/rmt/n obs=blocksize
```

<code>tar cf</code>	Creates a tape archive and specifies the tape device.
<code>-</code> (Hyphen)	Represents a placeholder for the tape device.
<code>files</code>	Identifies files to be copied.
<code>  rsh remotehost</code>	Pipe the <code>tar</code> command's output to a remote shell to copy the files.
<code>dd of=/dev/rmt/n</code>	Represents the output device.
<code>obs=blocksize</code>	Represents the blocking factor.

#### 4. Remove the tape from the drive and write the names of the files on the tape label.

### Example—Copying Files to a Remote Tape Drive (`tar` and `dd`)

```
# tar cvf - * | rsh mercury dd of=/dev/rmt/0 obs=126b
a answers/ 0 tape blocks
a answers/test129 1 tape blocks
a sc.directives/ 0 tape blocks
a sc.directives/sc.190089 1 tape blocks
a tests/ 0 tape blocks
a tests/test131 1 tape blocks
6+9 records in
0+1 records out
```

## ▼ How to Extract Files From a Remote Tape Drive

### 1. Change to a temporary directory.

```
$ cd /var/tmp
```

### 2. To extract files to a remote tape drive use the `tar` and `dd` commands.

```
$ rsh remotehost dd if=/dev/rmt/n | tar xvBpf -
```

<code>rsh remotehost</code>	Is a remote shell that is started to extract the files from the tape device using the <code>dd</code> command.
<code>dd if=/dev/rmt/n</code>	Indicates the input device.
<code>  tar xvBpf -</code>	Pipes the output of the <code>dd</code> command to the <code>tar</code> command used to restore the files.

### 3. Verify that the files have been extracted.

```
$ ls -l /var/tmp
```

## Example—Extracting Files From a Remote Tape Drive

```
$ rsh mercury dd if=/dev/rmt/0 | tar xvBpf -
x answers/, 0 bytes, 0 tape blocks
x answers/test129, 48 bytes, 1 tape blocks
20+0 records in
20+0 records out
x sc.directives/, 0 bytes, 0 tape blocks
x sc.directives/sc.190089, 77 bytes, 1 tape blocks
x tests/, 0 bytes, 0 tape blocks
x tests/test131, 84 bytes, 1 tape blocks
$ ls -l /var/tmp
```

## Copying Files and File Systems to Diskette

Before you can copy files or file systems to diskette, you must format the diskette. See Chapter 13 for information on how to format a diskette.

Use the `tar` command to copy UFS files to a single formatted diskette.

Use the `cpio` command if you need to copy UFS files to multiple formatted diskettes. `cpio` recognizes end-of-media and prompts you to insert the next volume.

---

**Note** - Using the `cpio` command to copy UFS files to multiple formatted diskettes is not a straightforward procedure because of Volume Management.

---

Use double-sided high-density 3.5-inch diskettes (diskettes are marked “DS, HD”).

## Things You Should Know When Copying Files to Diskettes

- Copying files to a formatted diskette using the `-c` option of `tar` destroys any files already on the diskette.
- A diskette that already contains a `tar` image is not mountable.

### ▼ How to Copy Files to a Single Formatted Diskette (`tar`)

1. Change to the directory that contains the files you want to copy.
2. Insert a formatted diskette that is not write-protected into the drive.
3. Make the diskette available using the `volcheck` command.

```
$ volcheck
```

4. Unmount any file system on the diskette and reformat it.

```
$ fdformat -U /vol/dev/aliases/floppy0
```

5. Copy the files to diskette using the `tar` command.

```
$ tar cvf /vol/dev/rdiskette0/unlabeled filename ...
```

The file names you specify are copied to the diskette, overwriting any existing files on the diskette.

6. Verify that the files copied are on the diskette using the `tar` command with the `-t` option, which displays the diskette’s contents. See “How to List the Files on a Diskette (`tar`)” on page 613 for more information on listing files.

```
$ tar tvf /vol/dev/rdiskette0/unlabeled
```

7. Remove the diskette from the drive.
8. Write the names of the files on the diskette label.

## Example—Copying Files to a Single Formatted Diskette (tar)

The following example copies two files to a diskette.

```
$ cd /home/smith
$ ls evaluation*
evaluation.doc  evaluation.doc.backup
$ tar cvf /vol/dev/rdiskette0/unlabeled evaluation*
a evaluation.doc 86 blocks
a evaluation.doc.backup 84 blocks
$ tar tvf /vol/dev/rdiskette0/unlabeled
```

## ▼ How to List the Files on a Diskette (tar)

1. Insert a diskette into the drive.
2. Run `volcheck` to make the diskette available.

```
$ volcheck
```

3. Use the `tar` command to list the files on a diskette.

```
$ tar tvf /vol/dev/rdiskette0/unlabeled
```

## Example—Listing the Files on a Diskette (tar)

The following example lists the files on a diskette.

```
$ tar tvf /vol/dev/rdiskette0/unlabeled
rw-rw-rw-6693/10  44032 Jun  9 15:45 evaluation.doc
rw-rw-rw-6693/10  43008 Jun  9 15:55 evaluation.doc.backup
$
```

See `tar(1)` for more information.

If you need a multiple-volume interchange utility, use the `cpio` command. The `tar` command is only a single-volume utility.

## ▼ How to Retrieve Files From a Diskette (tar)

1. Change to the directory where you want to put the files.
2. Insert the diskette into the drive.
3. Run `volcheck` to make the diskette available.

```
$ volcheck
```

4. Use the `tar` command to retrieve files from a diskette.

```
$ tar xvf /vol/dev/rdiskette0/unlabeled
```

All of the files on the diskette are copied to the current directory.

5. Verify the files have been retrieved by listing the contents of the current directory.

```
$ ls -l
```

6. Remove the diskette from the drive.

## Examples—Retrieving Files From a Diskette (tar)

The following example retrieves all the files from a diskette.

```
$ /home/smith/Evaluations
$ tar xvf /vol/dev/rdiskette0/unlabeled
x evaluation.doc, 44032 bytes, 86 tape blocks
x evaluation.doc.backup, 43008 bytes, 84 tape blocks
$ ls -l
```

The following example retrieves an individual file from a diskette.

```
$ tar xvf /vol/dev/rdiskette0/unlabeled evaluation.doc
x evaluation.doc, 44032 bytes, 86 tape blocks
$ ls -l
```



The file names you specify are extracted from the diskette and placed in the current working directory.

## ▼ How to Archive Files to Multiple Diskettes

If you are copying large files or file systems onto diskettes, you want to be prompted to replace a full diskette with another formatted diskette. The `cpio` command provides this capability. The `cpio` commands you use are the same as you would use to copy files to tape, except you would specify `/vol/dev/aliases/floppy0` as the device instead of the tape device name. See “How to Copy All Files in a Directory to a Tape (`cpio`)” on page 605 for information on how to use `cpio`.

---

## Copying Files With a Different Header Format

Archives created with the SunOS 5.7 `cpio` command may not be compatible with older SunOS releases. The `cpio` command allows you to create archives that can be read with several other formats. You specify these formats using the `-H` option and one of these arguments:

- `crc` or `CRC` – ASCII header with checksum
- `ustar` or `USTAR` – IEEE/P1003 Data Interchange
- `tar` or `TAR` – tar header and format
- `odc` – ASCII header with small device numbers
- `bar` – bar header and format

The syntax for using the header options is:

```
cpio -o -H header-option < file-list > output-archive
```

## ▼ How to Create an Archive for Older SunOS Releases

Use the `cpio` command to create the archive.

```
$ cpio -oH odc < file-list > /dev/rmt/n
```

The `-H` values have the same meaning for input as they do for output. If the archive was created using the `-H` option, you must use the same option when the archive is read back in or the `cpio` command will fail, as shown below.

## Example—Creating an Archive for Older SunOS Releases

```
$ find . -print | cpio -oH tar > /tmp/test
113 blocks
$ cpio -iH bar < /tmp/test
cpio: Invalid header "bar" specified
USAGE:
    cpio -i[bcdfkmrstuvBSV6] [-C size] [-E file] [-H hdr]
        [-I file [-M msg]] [-R id] [patterns]
    cpio -o[acvABLV] [-C size] [-H hdr] [-O file [-M msg]]
    cpio -p[adlmuvLV] [-R id] directory
```

When you create an archive using different options, always write the command syntax on the media label along with the names of the files or file system on the archive.

If you do not know which `cpio` options were used when an archive was created, all you can do is experiment with different combinations of the options to see which ones allow the archive to be read.

See `cpio(1)` for a complete list of options.

## Retrieving Files Created With the `bar` Command

To retrieve files from diskettes that were archived using the SunOS 4.0/4.1 `bar` command, use the `-H bar` option to `cpio`.

---

**Note** - You can only use the `-H bar` option with `-i` to retrieve files. You cannot create files with the `bar` header option.

---

### ▼ How to Retrieve `bar` Files From a Diskette

1. Change to the directory where you want to put the files.
2. Insert the diskette into the drive.
3. Run `volcheck` to make the diskette available.

```
$ volcheck
```

4. Use the `cpio` command to retrieve `bar` files from a diskette.  
All the files on the diskette are copied to the current directory.

```
$ cpio -ivH bar < /vol/dev/rdiskette/unlabeled
```



## Managing Tape Drives (Tasks)

---

This chapter describes how to manage tape drives.

This is a list of the step-by-step instructions in this chapter.

- “How to Display Tape Drive Status” on page 622
- “How to Retension a Magnetic Tape Cartridge” on page 623
- “How to Rewind a Magnetic Tape Cartridge” on page 624

---

## Choosing Which Media to Use

You typically back up Solaris systems using:

- 1/2-inch reel tape
- 1/4-inch streaming cartridge tape
- 8-mm cartridge tape
- 4-mm cartridge tape (DAT)

You can perform backups using diskettes, but this is time-consuming and cumbersome.

The media you choose depends on the availability of the equipment that supports it and of the media (usually tape) that you use to store the files. Although you must do the backup from a local system, you can write the files to a remote device.

Table 38–1 shows typical media used for backing up file systems and shows the storage capacity for each.

**TABLE 38-1** Media Storage Capacities

Media	Capacity <sup>1</sup>
1/2-inch reel tape	140 Mbytes (6250 bpi)
2.5-Gbyte 1/4 inch cartridge (QIC) tape	2.5 Gbytes
DDS3 4-mm cartridge tape (DAT)	12 - 24 Gbytes
14-Gbyte 8-mm cartridge tape	14 Gbytes
DLT™ 7000 1/2-inch cartridge tape	35 - 70 Gbytes

1. Capacity depends on the type of drive and the data being written to the tape.


## Backup Device Names

You specify a tape or diskette drive to use for backup by supplying a logical device name. This name points to the subdirectory containing the “raw” device file and includes the logical unit number of the drive. Tape drive naming conventions use a logical, not a physical, device name. Table 38-2 shows this naming scheme.

**TABLE 38-2** Basic Device Names for Backup Devices

Device Type	Name
Tape	<code>/dev/rmt/<i>n</i></code>
Diskette	<code>/vol/dev/rdiskette0/unlabeled</code>

In general, you specify a tape drive device as shown in Figure 38-1.



**Figure 38-1** Tape Drive Device Names

If you don't specify the density, a tape drive will typically write at its "preferred" density, which usually means the highest density it supports. Most SCSI drives can automatically sense the density or format on the tape and read it accordingly. To determine the different densities that are supported for a drive, look at the `/dev/rmt` subdirectory, which includes the set of tape device files that support different output densities for each tape.

Also, a SCSI controller can have a maximum of seven SCSI tape drives.

## Specifying the Default Density for a Tape Drive

Normally, you specify a tape drive by its logical unit number, which may run from 0 to *n*. Table 38-3 describes how to specify tape device names using default density settings.

**TABLE 38-3** Specifying Default Densities for a Tape Drive

To Specify The ...	Use ...
First drive, rewinding	<code>/dev/rmt/0</code>
First drive, nonrewinding	<code>/dev/rmt/0n</code>
Second drive, rewinding	<code>/dev/rmt/1</code>
Second drive, nonrewinding	<code>/dev/rmt/1n</code>

By default, the drive writes at its “preferred” density, which is usually the highest density it supports. If you do not specify a tape device, the command writes to drive number 0 at the default density the device supports.

## Specifying Different Densities for a Tape Drive

To transport a tape to a system whose tape drive supports only a certain density, specify a device name that writes at the desired density. Table 38–4 describes how to specify different densities for a tape drive.

TABLE 38–4 Specifying Different Densities for a Tape Drive

To Specify The ...	Use ...
First drive, low density, rewinding	<code>/dev/rmt/0l</code>
First drive, low density, nonrewinding	<code>/dev/rmt/0ln</code>
Second drive, medium density, rewinding	<code>/dev/rmt/1m</code>
Second drive, nonrewinding, medium density	<code>/dev/rmt/1mn</code>

The unit and density characters are shown in Figure 38–1.

## Displaying Tape Drive Status

You can use the `status` option with the `mt` command to get status information about tape drives. The `mt` command reports information about any tape drives described in the `/kernel/drv/st.conf` file.

### ▼ How to Display Tape Drive Status

1. Load a tape into the drive you want information about.
2. Display tape drive status with the `mt` command.

```
# mt -f /dev/rmt/n status
```



3. Repeat steps 1-2, substituting tape drive numbers 1, 2, 3, and so on to display information about all available tape drives.

## Example— Displaying Tape Drive Status

The following example shows status for a QIC-150 tape drive (/dev/rmt/0) and an Exabyte tape drive (/dev/rmt/1).

```
$ mt -f /dev/rmt/0 status
Archive QIC-150 tape drive:
  sense key(0x0)= No Additional Sense   residual= 0   retries= 0
  file no= 0   block no= 0
$ mt -f /dev/rmt/1 status
Exabyte EXB-8200 8mm tape drive:
  sense key(0x0)= NO Additional Sense residual= 0   retries= 0
  file no= 0   block no= 0
```

The following example shows a quick way to poll a system and locate all of its tape drives.

```
$ for drive in 0 1 2 3 4 5 6 7
> do
> mt -f /dev/rmt/$drive status
> done
Archive QIC-150 tape drive:
  sense key(0x0)= No Additional Sense   residual= 0   retries= 0
  file no= 0   block no= 0
/dev/rmt/1: No such file or directory
/dev/rmt/2: No such file or directory
/dev/rmt/3: No such file or directory
/dev/rmt/4: No such file or directory
/dev/rmt/5: No such file or directory
/dev/rmt/6: No such file or directory
/dev/rmt/7: No such file or directory
$
```

---

## Handling Magnetic Tape Cartridges

If errors occur when reading a tape, retension the tape, clean the tape drive, and then try again.

### ▼ How to Retension a Magnetic Tape Cartridge

Retension a magnetic tape cartridge with the `mt` command.

```
$ mt -f /dev/rmt/n retension
```

### Example—How to Retension a Magnetic Tape Drive

The following example retensions the tape in drive `/dev/rmt/1`.

```
$ mt -f /dev/rmt/1 retension
$
```

---

**Note** - Do not retension non-QIC tape drives.

---

## ▼ How to Rewind a Magnetic Tape Cartridge

To rewind a magnetic tape cartridge, use the `mt` command.

```
$ mt -f /dev/rmt/n rewind
```

### Example—Rewinding a Magnetic Tape Cartridge

The following example rewinds the tape in drive `/dev/rmt/1`.

```
$ mt -f /dev/rmt/1 rewind
```

---

## Guidelines for Drive Maintenance and Media Handling

A backup tape that cannot be read is useless. It is a good idea to clean and check your tape drives periodically to ensure correct operation. See your hardware manuals for instructions on procedures for cleaning a tape drive. You can check your tape hardware by:

- Copying some files to the tape, reading them back, and then comparing the original with the copy.
- Or, you could use the `-v` option of the `ufsdump` command to verify the contents of the media with the source file system. The file system must be unmounted or completely idle for the `-v` option to be effective.

Be aware that hardware can fail in ways that the system does not report.

Always label your tapes after a backup. If you have planned a backup strategy similar to those suggested in Chapter 33, you should indicate on the label “Tape A,” “Tape B,” and so forth. This label should never change. Every time you do a backup, make another tape label containing the backup date, the name of the machine and file system backed up, backup level, the tape number (1 of  $n$ , if it spans multiple volumes), plus any information specific to your site. Store your tapes in a dust-free safe location, away from magnetic equipment. Some sites store archived tapes in fireproof cabinets at remote locations.

You should create and maintain a log that tracks which media (tape volume) stores each job (backup) and the location of each backed-up file.



## The 64-bit Solaris Operating Environment

---

This section provides information for system administrators who are working with systems running the 32-bit and 64-bit Solaris operating environments, both of which are available with the Solaris 7 release.

---

### Overview of the 64-bit Solaris Operating Environment

The Solaris 7 release provides the ability to run both of the following environments on a SPARC or Intel platform:

- A 32-bit Solaris application and operating environment for:
  - Developing 64-bit applications (SPARC platforms only)
  - Running a large number of existing 32-bit applications
- A 64-bit Solaris application and operating environment for (SPARC platforms only):
  - Developing 64-bit applications
  - Allowing new 64-bit applications to manipulate large address spaces
  - Running a large number of existing 32-bit applications

Currently, the only platforms capable of supporting the 64-bit Solaris 7 operating environment are systems that have an UltraSPARC™ processor. Developing 64-bit applications on other platforms or previous Solaris releases is not supported.

---

**Note** - Systems that have an UltraSPARC processor are referred to as UltraSPARC systems for the remainder of this appendix.

---

## Do I Need to Use the 64-bit Solaris Application Environment?

No, unless you are developing 64-bit applications on a 32-bit or 64-bit Solaris 7 system or running 64-bit applications on UltraSPARC systems.

Although running 64-bit applications can have enormous advantages over running some 32-bit applications—particularly applications which are able to manipulate large address spaces, such as databases—the 32-bit Solaris application environment will continue to be the default application environment for a long time to come.

## Do I Need to Use the 64-bit Solaris Operating Environment?

The 64-bit Solaris operating environment provides 32-bit application source and binary compatibility. The typical end-user and developer won't even be aware of the Solaris 64-bit environment.

## Which SPARC Systems Support 64-bit Application Development?

You can develop 64-bit applications on the Solaris 7 release running on the `sun4c`, `sun4m`, `sun4d`, and `sun4u` systems. And, of course, you can run 64-bit applications on UltraSPARC systems running the Solaris 7 release.

## How Do I Install the 64-bit Solaris Operating Environment?

Software selection choices include a 64-bit support option when installing the Solaris 7 release for all system types:

- On UltraSPARC systems, 64-bit support is selected by default. You can override this default by deselecting the 64-bit support.

- For all other systems, 32-bit support is selected by default. You can override this default by selecting 64-bit support, available in the Developer and Entire Distribution software clusters, which will provide the 64-bit Solaris libraries for developers who wish to develop 64-bit applications on 32-bit systems.

Look for the 64-bit support option during the various Solaris 7 installation scenarios:

- For an initial installation using the Solaris interactive installation program, the 64-bit support option is displayed on the Software Selection screen, which prompts for the type of system software to be installed: End User, Developer, or Entire Distribution.
- For an upgrade using the Solaris interactive installation program, the 64-bit support option is displayed on the Customize Software screen that appears prior to the start of the software upgrade.
- For an initial installation using Solaris Web Start, the 64-bit support option is displayed on the Configure Solaris screen, which is found after pressing the Custom Install button.
- For an initial installation or upgrade using the custom JumpStart™ technology, 32-bit or 64-bit support can be selected using the profile. Add one of the following keyword value pairs to the profile:

```
isa_bits 32  
isa_bits 64
```

## How Do I Know Whether a System Can Run the 64-bit Solaris Operating Environment?

Currently, the only platform capable of supporting the 64-bit Solaris operating environment is an UltraSPARC system. You can verify whether a system is an UltraSPARC system by using the following command:

```
$ uname -m  
sun4u
```

If the output of the `uname -m` command is `sun4u`, then the machine is an UltraSPARC system.

If you are running the Solaris 7 release, you can verify this by using the `psrinfo` command:

```
# psrinfo -v
Status of processor 0 as of: 02/10/98 14:25:55
  Processor has been on-line since 01/30/98 15:10:29.
  The sparcv9 processor operates at 168 MHz,
    and has a sparcv9 floating point processor.
Status of processor 1 as of: 02/10/98 14:25:55
  Processor has been on-line since 01/30/98 15:10:33.
  The sparcv9 processor operates at 168 MHz,
    and has a sparcv9 floating point processor.
```

If the processor type is `sparcv9`, the platform is capable of running the 64-bit Solaris operating environment. This test does not work on previous versions of the `psrinfo` command, where all platforms report the less precise `sparc` as the processor type.

## ▼ How Do I Determine Whether a System Has 64-bit Solaris Capabilities Enabled?

The basic 64-bit Solaris operating environment looks unchanged from the previous 32-bit environment. You can use a new command to determine whether a system has 64-bit capabilities enabled, which means the system is booted with the 64-bit kernel.

The `isainfo(1)` command, (for *instruction set architecture information*), has two functions:

- It describes the supported applications of the running system (the `isainfo -v` command).
- It reports the number of bits supported by *native* applications on the running system, which can be passed as a token to scripts (the `isainfo -b` command).

## Examples—Determining Whether a System Has 64-bit Solaris Capabilities Enabled

An UltraSPARC system running a 32-bit kernel looks like this:

```
$ isainfo -v
32-bit sparc applications
```

The output means this system is capable of supporting only 32-bit applications.

An UltraSPARC system running a 64-bit kernel looks like this:



```
$ isainfo -v
64-bit sparcv9 applications
32-bit sparc applications
```

This output means this system is capable of supporting both 32-bit and 64-bit applications.

Use the `isainfo -b` command to display the number of bits supported by native applications on the running system.

The output from a SPARC, Intel, or UltraSPARC system running the 32-bit Solaris operating environment looks like this:

```
$ isainfo -b
32
```

The output from a 64-bit UltraSPARC system running the 64-bit Solaris operating environment looks like:

```
$ isainfo -b
64
```

The command returns 64 only. Even though a 64-bit UltraSPARC system is capable of running both types of applications, 64-bit applications are the best kind of applications to run on a 64-bit system.

The `uname -p` output remains `sparc` or `i386` to ensure that existing 32-bit applications continue to run without interruption.

## How Do I Run Applications in the 64-bit Solaris Operating Environment?

You probably run applications in the 64-bit Solaris environment no differently than in the 32-bit Solaris environment.

A user's `PATH` environment variable does not need to change to use a 64-bit Solaris system. Although most system utilities remain 32-bit applications, some are available in 64-bit versions. The 64-bit command versions are automatically invoked by a command wrapper program that transparently starts the correct version of the command based upon the capabilities of the running system.

Other issues to keep in mind when running applications in the 64-bit Solaris operating environment:

- If a 32-bit application reads kernel memory, it needs to be compiled as a 64-bit program because the kernel is now a 64-bit program.
- If a 32-bit program uses the `/proc` file system to look at other processes, it may need to be converted to a 64-bit program to understand the extended capabilities of 64-bit processes.
- If you intend to run 64-bit applications that require large virtual address spaces, you may need to add more swap space to the system.

## What About 64-bit Device Drivers or Third-Party Device Drivers?

System administrators should be certain that they have the correct device drivers available for their 64-bit Solaris systems by following these steps:

1. Verify whether the UltraSPARC system needs a firmware upgrade to boot the 64-bit Solaris kernel. See your hardware manufacturer's documentation to determine whether your UltraSPARC system needs a firmware upgrade.
2. Select the 64-bit Solaris packages during installation.
3. Boot the 64-bit Solaris operating environment.

Another important administration issue is making sure your third-party device drivers are available in 64-bit versions; otherwise you probably won't be able to run the 64-bit Solaris environment until they are available in 64-bit versions.

## Using the `LD_LIBRARY_PATH` Variable in the 64-bit Solaris Operating Environment

If you are running 64-bit applications, you may need to customize your `LD_LIBRARY_PATH` environment variable as follows:

- Set the new environment variable, `LD_LIBRARY_PATH_64`, like `LD_LIBRARY_PATH`, except that it can only be referenced by 64-bit applications.
- Set the `LD_LIBRARY_PATH` variable to allow applications to reference a combination of both 32-bit and 64-bit libraries.

## Do I Boot Systems Running a 32-bit and 64-bit Solaris 7 Kernel the Same Way?

No, but you shouldn't have to boot them differently. The 64-bit Solaris 7 kernel is booted by default if it is installed on an UltraSPARC system. If it isn't installed, the 32-bit kernel is booted instead.

Also, on UltraSPARC systems, `kadb` and various boot programs are now 64-bit programs that can boot either a 32-bit or 64-bit kernel.

If you have problems booting either system type, see the next section.

---

## Troubleshooting 64-bit Solaris Boot Problems

After the 64-bit Solaris release is installed on an UltraSPARC system, the 64-bit kernel will be booted automatically unless any of the following conditions are true:

- A FLASH PROM upgrade may be required on an UltraSPARC system before it can successfully boot the 64-bit kernel. Refer to your hardware manufacturer's documentation to determine whether your UltraSPARC system requires a firmware upgrade.
- The Open Boot PROM `boot-file` parameter is set to `kernel/unix`. If booting the 64-bit kernel fails and this parameter is set, unset it, and reboot the system.
- On some UltraSPARC systems, the 64-bit Solaris kernel is not booted by default, even when the system is completely installed with all the 64-bit Solaris components and the correct firmware is installed. Without booting the 64-bit Solaris kernel, 64-bit applications are unable to run.

To find out more about this issue, and how to enable booting the 64-bit Solaris kernel by default, see `boot(1m)` and *Solaris 7 (SPARC Platform Edition) Release Notes*.

You can always discover which Solaris kernel the system is currently running by using the `isainfo -kv` command.

```
$ isainfo -kv
64-bit sparcv9 kernel modules
```

This output means the system is running the 64-bit Solaris kernel.

You cannot boot the 64-bit Solaris operating environment on a 32-bit Solaris system.

---

## 64-bit Solaris Package Changes

Certain Solaris 7 system packages provide both 32-bit and 64-bit versions. For example:

- The `SUNWcsl` package contains core 32-bit Solaris shared libraries.
- The `SUNWcslx` package contains the Solaris 64-bit versions of the core shared libraries.

You can add 64-bit application tools (64-bit shared libraries) to 32-bit platforms if you want to develop 64-bit applications on a 32-bit system.

---

## Automatically Mounting 32-bit or 64-bit Applications

System administrators can use a new variable, `NATISA`, which corresponds to the output of the `isainfo -n` command, in automounter maps. You can set this variable to allow different parts of a directory hierarchy to be mounted on the system depending on whether the system supports 32-bit or 64-bit native applications.

For example, the following map entry allows a client to mount either `/export/sparc/bin` or `/export/sparcv9/bin` depending on whether 64-bit applications are supported on that system.

```
/export/bin server:/export/$NATISA/bin -ro
```

See `automount(1m)` for more information.

# Index

---

## Numbers

- 1.2 Mbyte diskettes, 191, 193
- 1.44 Mbyte diskettes, 191, 193
- 1.44 Mbyte diskettes, 169
- 2.88 Mbyte diskettes, 192
- 2.88 Mbyte diskettes, 169
  - formatting options, 191
- 3.5" diskettes, , *see* diskettes\x0d,
- 4.3 Tahoe file system, 401
- 5.25" diskettes, , *see* diskettes\x0d,
- 360 Kbyte diskettes, 191, 193
- 360 Kbyte diskettes, 169
- 720 Kbyte diskettes, 191, 193
- 720 Kbyte diskettes, 169
- 9660 CD format, 177, 242

## A

- access, 169
  - CD access points, 173
  - diskette access points, 173
  - PCMCIA memory cards on other systems, 229
- accessing
  - disk devices, 302, 306
  - tape devices, 306
- accounting, user, , *see* user accounts\x0d,
- Add option (Edit menu)
  - Admintool: Groups, 38
  - Admintool: Users, 39, 40
- adding
  - a disk
    - x86, 366

- device driver, 295
- groups
  - Admintool: Groups, 38
  - commands, 12
- peripheral device, 293
- run control script, 114
- server and client support
  - description, 60
  - for a diskless client, 91
  - for a standalone system, 77
  - for an OS server, 77
  - Host Manager, 64
  - setting defaults for, 77
- Solaris 7 OS services to an OS server, 86
- SunOS 4.0 and compatible OS services to an OS Server, 82
- swap to vfstab, 485
- user accounts
  - Admintool: Users, 39, 40
  - commands, 12
- user initialization files, 15
- users to groups
  - Admintool: Groups, 45
  - Admintool: Users, 14
  - commands, 12
- adding, *see* software administration, adding packages\x0d
  - software packages.,
- administration files, 253, 254, 257, 262, 268
- administrative commands, 404
- Admintool

- software administration and, 276
  - overview, 248 to 250, 276
  - third-party packages, 252
- Admintool: Users, 247
  - Add option (Edit menu), 39, 40
  - advantages, 14
  - Delete option (Edit menu), 15
  - described, 14
  - disabling accounts, 16
  - initialization files, 15
  - Modify option (Edit menu), 14, 15
  - password administration, 15
- aging user passwords, 9, 15, 16
- aliases
  - deleting, 15
  - user login names vs., 5
- aliases directory, 240
- aliases file, 15
- allocated inodes, 496
- ARCH environment variable, 24
- archives (cpio), 615
- archiving files to multiple diskettes (cpio), 615
- AutoClient system, 251
- autoconfiguration process, 292
- autofs, 413
- autofs, , *see* automounting\x0d,
- automatic mounting, , *see* mounting,
- automount /home, 414
- automounting
  - user home directories, 10
- auto\_home file, 15
- awk command, 12

## B

- backing up and restoring file systems
  - commands for, 534
  - defined, 534
  - overview of commands, 538
- backup
  - choosing file systems to, 536
  - device names, 620
  - full (level 0) backup to tape, 554
  - full and incremental, defined, 539
  - preparing for, 551
  - reasons for, 535
  - record of incremental, 578
  - types of, 539

- backup schedules
  - daily cumulative, weekly cumulative
    - backups, 542
  - daily cumulative, weekly incremental
    - backups, 544
  - daily incremental, weekly cumulative
    - backups, 545
  - examples, 542, 548
  - for a server, 546
  - guidelines for, 540
  - recommendations, 549, 557
  - using dump levels for, 541
- bad block numbers, 498
- bad inode number, 499
- bad superblock, 505
- banner PROM command, 130
- bar command
  - retrieving files created with, 616
- base directory (basedir), 253, 254, 262, 268
- basedir keyword (administration files), 253, 254, 262, 268
- big-endian bit coding, 189
- bin group, 5
- block disk device interface
  - defined, 303
  - when to use, 303
- block size, 418
- blocks
  - bad, 498
  - boot, 519
  - directory data, 498
  - duplicate, 497
  - free, 521
  - indirect, 498
  - logical size, 522
  - regular data, 500
  - special inodes, 496
  - storage, 521
- boot block, 519
- boot server, 69
- boot types, described, 101
- boot-from PROM setting, 130
- booting
  - and PC BIOS, 159
  - boot process
    - SPARC, 158
    - x86, 166

- for recovery purposes
  - SPARC, 138
  - x86, 151
- interactively
  - SPARC, 136
- modifying automatic checking, 500, 501
- to force a crash dump and reboot
  - SPARC, 141
  - x86, 155
- to run level 3
  - SPARC, 134
  - x86, 146
- to run level S
  - SPARC, 135
  - x86, 147
- with the kernel debugger (kadb)
  - SPARC, 142
- booting a system (guidelines), 101
- bootparams entry, 67
- Bourne shell
  - basic features, 22, 23
  - environment variables and, 23, 24, 28
  - shell (local) variables and, 23, 24, 26
  - user initialization files and, 20 to 22, 30, 37
- Break key, 140, 142
- BSD Fat Fast File system, 401
- bus-oriented disk controllers, 305, 306
- bytes (number per inode), 525

## C

- C shell
  - basic features, 22, 23
  - environment variables and, 23, 24, 28
  - shell (local) variables and, 23, 24, 26
  - user initialization files and, 20 to 22, 30, 37
- cached file systems, 446
  - checking (fsck), 459
  - creating, 448
  - deleting, 458
  - displaying information about, 456
  - parameters, 479
  - setting parameters, 450
  - setting up, 448
- CALENDAR environment variable, 24
- canceling, 169
  - UFS diskette formatting, 194
- capacity of tapes, 581

- cartridge tape
  - retensioning, 623
- causes of file system damage, 492
- CD-ROM devices (naming), 307
- CD-ROM drives, 169
  - access points, 173
  - directories under Volume Management, 237, 238
  - preparing for new drive, 185
  - sharing, 181
  - software installation and
    - from mounted CD to diskless client, 266
    - from mounted CD to server, 270
    - from mounted CD to standalone system, 258
  - spool directory from mounted CD, 260
- CD-ROMs, , see CDs\x0d,
- CDPATH environment variable, 24
- /cdrom mount point, 238, 240
- CDs, 169
  - access
    - access points, 173
    - raw-character access, 240
    - using Volume Management, 235, 237, 238
  - commands, 186
  - copying information
    - using command line, 177, 178
  - directories under Volume Management, 235, 237, 238
  - ejecting
    - using command line, 179
  - examining contents
    - using command line, 177
  - finding out if CD is in use, 178, 179
  - ISO 9660 format, 177, 242
  - killing processes accessing, 178, 179
  - loading
    - using command line, 177
  - mixed formats, 242, 243
  - mount points, 180, 238, 240
  - mounting
    - manual compared to automatic, 172
    - remote CDs, 180, 181

- musical CDs
  - configuring system to play, 184
- names
  - designators, 176
  - finding a CD's name, 180
- remote access
  - accessing CDs on other systems, 180, 181
  - making local CDs available to other systems, 181
- UFS CDs
  - mixed formats, 242, 243
  - SPARC vs. x86 format, 177, 196
- Volume Management, 169
- cfsadmin command, 448, 458
- changing, 247
  - directory ownership for user accounts, 14
  - file ownership for user accounts, 14
  - user accounts
    - Admintool: Users, 14, 15
    - commands, 12
  - user ID numbers, 14
  - user login names, 14
  - user passwords
    - Admintool: Users and, 15
    - by user, 8
    - commands for, 12
    - frequency of, 8, 18
- changing, *see* groups, changing\x0d groups, ,
- changing, *see* user initialization files, customizing\x0d user initialization files, ,
- character special inodes, 496
- checking
  - file system size, 495
  - file systems, 502
  - file systems interactively, 502
  - format and type of inodes, 496
  - free blocks, 495
  - free inodes, 496
  - inode list for consistency, 495
  - modifying automatic boot, 500
- clean shutdown, 120
- clients
  - software administration, 250, 252
    - displaying installed software information, 270, 273
  - heterogeneous environments, 252, 263, 264
  - homogeneous environments, 261
  - removing packages, 275
  - sharing software with servers, 250, 275
  - Solstice AutoClient systems, 251
  - Sun packages, 251, 262
  - third-party packages, 252, 263
  - support for, 95
- clients, *see* diskless clients\x0d software administration diskless clients, ,
- cloning disks, 594
- clri command, 404
- compatibility problems, , *see* version incompatibilities\x0d,
- compatible archives, 615
- controlling file and directory access, 4, 28
- converting system types, 80
- copying, 169
  - all files in a directory to tape (cpio), 605
  - CD information
    - using command line, 177, 178
  - complete file systems (dd), 593
  - data (ufsdump), 578
  - directories between file systems (cpio), 597
  - diskette information
    - from diskettes, 203
    - to diskettes, 204, 205
  - files to diskette, 611
  - files to diskette (tar), 612
  - files to remote tape (tar and dd), 609
  - files to tape (pax), 604
  - files to tape (tar), 601
  - files with different header format (cpio), 615
  - groups of files (cpio), 597
  - individual files (cpio), 597
  - information from a PCMCIA memory card, 225
  - information to a PCMCIA memory card, 226



- user accounts
    - commands, 12
- cp command
  - copying CD information, 177, 178
  - copying from diskettes, 203
  - copying to diskettes, 204
- cpio command, 597, 605, 609
  - copying all files in a directory to tape, 605
  - copying directories between file
    - systems, 597
  - copying files with different header
    - format, 615
  - listing files on tape, 606
  - retrieving all files from tape, 607
  - retrieving specific files from tape, 608
  - when to use, 601
- creating, 247
  - a format.dat entry, 343
  - a Solaris fdisk partition, 369
  - compatible archives (cpio), 615
  - disk slices and labeling a disk
    - SPARC, 356
    - x86, 376
  - file systems, 418
  - loopback file system, 422
  - mount point, 410
  - Solaris fdisk partition, 366
  - swap file, 487
  - temporary file system, 420
  - UFS file system, 418
- cred file, 15
- .cshrc file
  - customizing, 10, 20, 22, 30
- custom parameters for file systems, 522
- customizing, 247
- customizing, *see* user initialization files,
  - customizing\x0d
- user initialization files,,
  - formatting options, 191, 193

## D

- daemon group, 5
- daily cumulative backups, 541
- daily discrete backups, 542
- damage to file systems, 492
- data block, 500
- data directory blocks, 498
- DD (Medium Density) diskettes, 169

- dd command, 593, 594, 596
  - cloning disks, 595
  - copying files to remote tape (tar), 609
  - retrieving files from remote tape drive
    - (tar), 610
- default
  - file system for /tmp (TMPFS), 402
  - mount options, 435, 438
  - SunOS file system, 406
  - tape drive densities, 621
- defaults
  - file permissions, 28
  - groups, 11
  - LOGNAME environment variable, 25
  - PATH environment variable, 25, 27
  - printer, 25
  - SHELL environment variable, 26
  - spool directory, 259
  - TZ (time zone) environment variable, 26
  - user account default setup
    - commands, 12
    - user initialization files, 20
- delay (rotational), 524
- Delete option (Edit menu)
  - Admintool: Users, 15
- deleting
  - cached file systems, 458
  - groups
    - commands, 12
  - mail aliases, 15
  - user accounts
    - Admintool: Users, 15
    - commands, 12
    - user home directories, 15
    - user mailboxes, 15
- deleting, *see* groups, changing users in\x0d
  - users from groups,,
    - deleting, *see* software administration,
      - removing packages\x0d
    - software packages,,
      - diskette formats, 191, 193
      - DOS diskettes, 198
      - UFS diskettes, 193, 194
- designators
  - CDs, 176

- diskettes, 190
- DESKSET environment variable, 25
- detecting end of media
  - cpio command, 597
  - ufsdump command, 578, 581
- determining
  - file system types, 415
  - tape device name, 562
  - type of tape drive, 562
  - who is logged in to a system, 121
- /dev/dsk directory, 303
- /dev/rdisk directory, 303
- device driver
  - adding, 295
  - defined, 291
- device instance name, 302
- device names
  - backup, 620
  - finding disk, 562
  - finding tape, 562
- devices
  - accessing, 301
  - when to turn off power to, 121
- df command, 303, 404
- dfstab file
  - configuring for shared CDs, 182
  - user home directory sharing and, 42
- direct disk controllers, 304
- directories, 169
  - base directory (basedir), 253, 254, 262, 268
  - CDs
    - /cdrom mount point, 238, 240
    - under Volume Management, 235, 237, 238
  - changing ownership for user accounts, 14
  - controlling access to, 4, 28
  - copying
    - from CDs, 177, 178
    - from diskette, 203
    - to diskettes, 204, 205
  - copying between file systems (cpio), 597
  - diskettes
    - /floppy mount point, 238, 240
    - under Volume Management, 235
  - home, 9
  - inodes, 496
  - PATH environment variable and, 25 to 27
  - path shell variable and, 23, 25
  - /proc, 403
  - skeleton, 10, 15
  - /tmp, 402
  - unallocated blocks, 499
- directories, *see* spool directories\x0d
  - spool,,
- directories, *see* user home directories\x0d
  - user home,,
- disabling
  - run control script, 115
  - user accounts
    - Admintool: Users, 16
    - commands, 12
    - passwords and, 16, 18
- disk
  - adding a
    - x86, 366
  - automatic configuration of SCSI
    - drives, 344
  - connecting a secondary disk
    - SPARC, 355
    - x86, 368
  - connecting a system disk
    - SPARC, 354
    - x86, 367
  - creating a file system on a new disk
    - SPARC, 361
    - x86, 379
  - creating disk slices and labeling a disk
    - SPARC, 357
    - x86, 376
  - determining if formatted, 332
  - examining a disk label, 338
  - formatting a, 321
  - formatting, when to, 331
  - identifying on a system, 329
  - labeling, 336
  - recovering a corrupted disk label, 339
  - repairing defective sectors, 347, 350
- disk controllers, 304
- disk device name, 562
- disk label
  - creating, 336
  - described, 322
  - examining with prtvtoc command, 338
- Disk Operating System, , *see* DOS\x0d,
- disk slice

- defined, 312
- disk slices
  - determining which slices to use, 317
  - displaying information about, 334
  - requirements for system configurations, 317
- disk-based file systems, 401
- diskette
  - archiving files to multiple (cpio), 615
  - copying files to, 611
  - copying files to (tar), 612
  - listing files on (tar), 613
  - retrieving files from (tar), 614
- diskette directories, 236
- diskette drives, 169
  - access points, 173
  - directories under Volume Management, 236
- diskettes, 169
  - access
    - access points, 173
    - raw-character access, 240
    - using Volume Management, 235
  - commands, 189
  - copying information
    - from diskettes, 203
    - to diskettes, 204, 205
  - directories under Volume Management, 236
  - ejecting
    - using command line, 206
  - examining contents
    - using command line, 202, 203
  - finding out if diskette is in use, 205
  - formatting, 199
    - canceling formatting, 194
    - caution, 193, 197
    - complete format, 191
    - diskette names, 190
    - DOS diskettes, 197, 199
    - File Manager unreliability, 193, 197
    - hardware considerations, 191, 193
    - size and density options, 191, 193, 194, 198
    - UFS diskettes, 193, 195
  - killing processes accessing, 205
  - loading
    - using Volume Management, 200, 202
  - mount points, 238, 240
  - mounting
    - manual compared to automatic, 172
    - remote diskettes, 206, 207
  - moving information
    - using command line, 203, 205
  - names, 190
  - remote access
    - accessing diskettes on other systems, 206, 207
    - making diskettes available to other systems, 208
  - UFS diskettes
    - adding UFS file system, 196, 197
    - canceling formatting, 194
    - formatting, 193, 195
    - SPARC vs. x86 formats, 191, 241
  - Volume Management, 169
- diskless clients
  - software administration for
    - adding packages, 251, 252, 261, 265, 267
    - adding support for, 91
    - displaying installed software information, 271
    - removing packages, 275
- disks, removable media, , *see* CDs,
- displaying
  - CD contents
    - using command line, 177
  - CD user, 178, 179
  - device information, 299
  - disk slice information, 334
  - diskette contents
    - using command line, 202, 203
  - environment variables, 23
  - PCMCIA contents, 225
  - swap space, 486
  - system configuration information, 296, 298
  - user mask, 28
- displaying, *see* software administration,
  - displaying installed software information\x0d
  - installed software information,,
- dmesg command, 299
  - SPARC example, 299
  - x86 example, 300

“Do you want to continue with this  
installation?” message, 268

donor slice, described, 326

## DOS

- file system, 401

- formatting diskettes, 197, 199

  - complete format, 191

  - platform-compatibility, 191

  - size and density options, 191, 193

driver not attached message, 296

drives, removable media, , *see* CD-ROM

- drives,

/vol/dev/dsk directory, 237, 238

## dump levels

- daily, cumulative backups, 541

- daily, discrete backups, 542

- defined, 541

duplicate blocks, 497

## E

### Edit menu

- Admintool: Groups

  - Add option, 38

  - Modify option, 45

- Admintool: Users

  - Add option, 39, 40

### eject command

- CDs, 179

- diskettes, 206

### ejecting

- CDs

  - using command line, 179

- diskettes

  - using command line, 206

- PCMCIA memory cards

  - using command line, 228

encryption, 16

### end-of-media detection

- cpio command, 597

- ufsdump command, 578, 581

env command, 23

### environment

- shell, 23, 26

environment variables, 247

- described, 23, 28

environment, *see* initialization files\%x0d  
work,,

/etc files

- user account information and, 4, 16

/etc/dfs/dfstab file

- user home directory sharing and, 42, 182

/etc/dumpdates file, 578

/etc/init.d directory, 115

/etc/inittab file, 109, 111

/etc/inittab file

- entries described, 109, 110

/etc/passwd file, 16, 140, 153

/etc/passwd file

- user ID number assignment and, 6, 15 to  
17

/etc/rmmount.conf file

- sharing CDs, 183, 184, 209, 210

/etc/shadow file

- described, 16

/etc/skel directory, 20

/etc/vfstab file, 43

export command, 23, 24

/export/home file system, 9

/export/root file system, 265

/export/home directory, 406

Extended Density diskettes, 169

- formatting options, 191, 192

extended fundamental types (UFS file  
system), 408

## F

fdformat command, 216

- confirmation message, 194

- convenience options, 193, 198

- formatting DOS diskettes, 198, 199

- formatting UFS diskettes, 193

- options, 215

- size and density options, 192, 193, 198

- syntax, 193, 194, 198, 199

- verifying correct format, 193

FDFS file system, 403

ff command, 404

### field

- group file, 19

- passwd file, 17

- shadow file, 18

field (group file), 19

field (passwd file), 17

- field (shadow file), 18
- field replaceable unit (FRU), 63
- FIFO inodes, 496
- FIFOFS file system, 403
- File Manager
  - formatting diskettes, 193, 197
- file system table
  - virtual, 412
- file systems
  - /, 406
  - 4.3 Tahoe, 401
  - administrative commands, 404
  - BSD Fat Fast, 401
    - cached, 446
  - checking, 502
  - checking interactively, 502
  - checking size, 495
  - copying complete (dd), 593
  - creating loopback, 422
  - creating UFS, 418
  - custom parameters, 522
  - cylinder group struct, 519
  - damage to, 492
  - default SunOS, 406
  - definition of, 401
  - disk-based, 401
  - DOS, 401
  - /export/home, 406
  - FDFS, 404
  - FIFOFS, 403
  - finding types, 415
  - fixing, 506
  - High Sierra, 401
  - ISO 9660, 401
  - making available, 425
  - manual pages, 406
  - mount table, 411
  - mounting NFS, 437
  - NAMEFS, 404
  - network-based, 402
  - /opt, 407
  - PC, 401
  - preening, 504
  - /proc, 407
  - process, 403
  - PROCFS, 403
  - pseudo, 402
  - reasons for inconsistencies, 494
  - restoring complete, 562, 570
  - sharing, 413
  - SPECFS, 404
  - SWAPFS, 404
  - table (vfstab), 412
  - table of administrative commands, 404
  - terminating all processes, 440
  - TMPFS, 402
  - types of, 401
  - UFS, 401
  - understanding UFS, 407
  - UNIX, 401
  - unmounting, 441
  - /usr, 406
  - /var, 407
  - which to back up, 536
  - why you back up, 535
- files, 247
  - archiving to multiple diskettes (cpio), 615
  - changing ownership for user accounts, 14
  - controlling access to, 4, 28
  - copying (cpio), 597
  - copying to diskette, 611
  - copying to diskette (tar), 612
  - copying to tape (pax), 604
  - copying to tape (tar), 601
  - /etc/default/fs, 415
  - /etc/dfs/fstypes, 415
  - in the /proc directory, 403
  - listing on diskette (tar), 613
  - listing on tape (cpio), 606
  - listing on tape (tar), 602
  - number of, 525
  - restoring interactively, 565
  - restoring specific, 567
  - retrieving from diskette (tar), 614
  - retrieving from tape (cpio), 607, 608
  - retrieving from tape (tar), 603
  - sharing, 413
  - verifying attributes for newly installed packages, 272
- files and file systems, 169
  - accessing files
    - CD files, 173
    - diskette files, 173
    - UFS file systems, 196, 197
  - moving, 169

- files, *see* permissions\x0d
  - permissions,,
- filesystems
  - large, 428
- finding
  - disk device name, 562
  - number of tapes for a full backup, 552
  - PROM release level, 130
  - tape device name, 562
  - tape drive type, 622
  - type of file system, 415
  - user accounts, 12
- finding out, , *see* verifying\x0d,
- fixing bad file systems, 506
- floppy disks, , *see* diskettes\x0d,
- /floppy mount point, 238, 240
- format of inodes, 496
- format utility
  - analyze menu, 386, 388
  - automatic configuration of SCSI disk drives, 344, 346
  - creating a Solaris fdisk partition, 369, 373
  - creating disk slices and labeling disk SPARC, 357
    - x86, 376, 378
  - defect menu, 388
  - determining if a disk is formatted, 331
  - displaying disk slice information, 334, 335
  - fdisk menu, 385
  - features and benefits, 318
  - formatting a disk, 332, 333
  - guidelines for using, 320
  - how to enter command names, 395
  - how to specify block numbers, 394
  - identifying disks on a system with, 329, 330
  - input to, 394, 396
  - labeling a disk, 336, 338
  - main menu, 382
  - man pages associated with, 396
  - overview, 318
  - partition menu, 384, 385
  - recommendations for preserving information, 382
  - recovering corrupted disk label, 340, 342
  - requirements for using, 381
  - using help facility, 396
  - when to use, 319

- format.dat file
  - contents of, 389
  - creating an entry, 343
  - keywords, 390, 393
  - syntax rules, 390
- formatting
  - diskettes, 199
    - canceling formatting, 194
    - caution, 193, 197
    - complete format, 191
    - diskette names, 190
    - DOS diskettes, 197, 199
    - File Manager unreliability, 193, 197
    - hardware considerations, 191, 193
    - size and density options, 191, 193, 194, 198
    - UFS diskettes, 193, 195
  - PCMCIA memory cards
    - for DOS, 220
    - for UFS file systems, 215
- formatting a disk, overview, 321
- fragment size, 523
- free blocks, 495, 521
- free hog slice, , *see* donor slice,
- free inodes, 496
- free space (minimum), 524
- fs file, 415
- fsck command, 303, 404
  - checking free blocks, 495
  - checking free inodes, 496
  - checking inode list size, 495
  - checking superblock, 495
  - conditions to repair, 494
  - FSACTIVE state flag, 492
  - FSBAD state flag, 492
  - FSCLEAN state flag, 492
  - FSSTABLE state flag, 492
  - preening, 504
  - state flags, 492
  - syntax and options, 507, 509
  - using interactively, 502
- fsck pass field (vfstab), 500
- fsdb command, 404
- fstyp command, 404
- fstypes file, 415
- full backup
  - defined, 540

- determine number of tapes for, 552
- using the `ufsdump` command, 554
- `fuser` command, 228
  - finding if CD is in use, 178, 179
  - finding if diskette is in use, 205
  - killing processes accessing CDs, 178, 179

## G

- `gap`, , *see* rotational delay,
- GECOS field (`passwd` file), 17
- GIDs, 5
  - assigning, 11
  - definition, 10
  - in the group file, 19
  - large, 6
- `grep` command, 12, 415
- group file
  - deleting user accounts and, 15
  - described, 16
  - fields in, 18, 19
- group ID numbers, 5, 10, 11, 19
- group names
  - changing, 45
  - described, 10
- `group*` commands, 12
- `groupadd` command, 12
- `groupdel` command, 12
- `groupmod` command, 12
- groups
  - adding
    - Admintool: Groups, 38
    - commands, 12
  - changing name, 45
  - changing primary, 11
  - changing users in
    - Admintool: Users, 14
    - commands, 12
  - commands for, 12
  - default, 11
  - deleting
    - commands, 12
  - described, 4, 10
  - displaying groups a user belongs to, 11
  - guidelines for managing, 10, 11
  - ID numbers, 5, 10, 11, 19
  - name services and, 11, 12

- names
  - changing, 45
  - described, 10
- passwords, 19
- permissions setting for, 28
- primary, 10, 11
- secondary, 10, 11, 19
- storage of information for, 16, 18
- tools for managing, 11, 12
- UNIX, 10
- `groups` command, 11
- groups, *see* groups, changing users in\
  - deleting users from,,

## H

- `halt` command, 120
- HD (High Density) diskettes, 169
  - formatting options, 191, 193
- header format
  - copying files with different (`cpio`), 615
- High Density (HD) diskettes, 169
  - formatting options, 191, 193
- High Sierra file system, 401
- history environment variable, 25
- `/home` (automounted), 414
- home directories, , *see* user home
  - directories\
    - directories\
      - `$HOME` directory, 9, 22
      - `HOME` environment variable, 25
      - home shell variable, 23, 25
      - `/home` file system
        - user home directories and, 9
- `$HOME/$ENV` file, 20
- `$HOME/.cshrc` file, , *see* `.cshrc` file,
- `$HOME/.login` file, , *see* `.login` file,
- `$HOME/.profile` file, , *see* `.profile` file,
- Host Manager, 64
  - add and maintain support, 65
  - add OS services, 67
  - prerequisites for running, 75
  - server-client configurations supported, 65
  - set up remote installation services, 68
  - starting, 75
  - SunOS 4.0/4.1 restrictions, 68
  - SunOS 4.x restrictions, 66
  - update system types, 66

Update System Types menu, 77  
HSFS, , *see* High Sierra file system,

## I

ID numbers  
    group, 5, 10, 11, 19  
    user, 5, 6, 14  
identifying  
    devices, 297  
    disks on a system, 329  
    PCMCIA memory cards, 214  
inconsistencies in file systems, 494  
incorrect . and .. entries, 499  
incremental backup, 540, 578  
indirect blocks, 498  
init command  
    described, 120  
    shutting down a standalone system, 126  
init states, , *see* run levels,  
initialization files  
    system, 10  
initialization files, *see* user initialization  
    files\x0d  
    user,,  
inode list size, 495  
inode states, 496  
inodes, 520  
    bad number, 499  
    block special, 496  
    character special, 496  
    checking format and type, 496  
    directory, 496  
    FIFO, 496  
    link count, 497  
    number of bytes per, 525  
    regular, 496  
    size, 498  
    symbolic link, 496  
install server, 69  
install4x, 82  
installboot command, 362, 380  
installing a boot block  
    SPARC, 362  
    x86, 380  
installing software packages, , *see* software  
    administration\x0d,  
integrity checking, , *see* verifying\x0d,

interactive  
    checking file systems, 502  
    restore, 565  
interactive booting  
    SPARC, 136  
    x86, 149  
International Standards Organization, , *see*  
    ISO standards\x0d,  
ISO 9660 file system, 401  
ISO standards  
    9660 CD format, 177  
    aab9660 CD format, 242  
iso\_8895\_1, 28  
  
**K**  
/kernel/drv directory, 292  
killing, 169  
    processes accessing CDs, 178, 179  
    processes accessing diskettes, 205  
killing all processes for a file system, 440  
Korn shell  
    basic features, 22, 23  
    environment variables and, 23, 24, 28  
    shell (local) variables and, 23, 24, 26  
    user initialization files and, 20 to 22, 30, 37

## L

L1-A keys, 140, 142  
labelit command, 404  
LANG environment variable, 25, 27, 28  
large files option, 428  
LC environment variables, 27, 28  
level 0 backup, 541  
link count of inodes, 497  
listing, 169  
    files on a diskette (tar), 613  
    files on a tape (cpio), 606  
    files on a tape (tar), 602  
listing, *see* software administration, displaying  
    installed software  
    information\x0d  
    installed software,,  
little-endian bit coding, 189  
\*LK\* password, 16, 18  
loading, 169



- CDs
  - using command line, 177
- diskettes
  - using Volume Management, 200, 202
- PCMCIA memory cards, 223
- local variables, , *see* shell variables\x0d,
- local.cshrc file, 20
- local.login file, 20
- local.profile file, 21
- locale environment variables, 25
- locking, , *see* disabling\x0d,
- log (record of dumps), 578
- logical block size, 522
- logical device name
  - CD-ROM, 307
  - defined, 302
  - disk, 302
  - tape, 306
- login names (user)
  - changing, 14
  - described, 4
- .login file
  - customizing, 10, 20, 22, 30
- LOGNAME environment variable, 25
- loopback file system
  - creating, 422
  - mounting, 432
- lost+found directory, 492
- Low Density diskettes, 169
  - formatting options, 191, 193
- LPDEST environment variable, 25
- ls command
  - examining CD contents, 177
  - examining diskette contents, 202, 203

## M

- magnetic tape cartridge
  - retensioning, 623
  - rewinding, 624
- mail aliases
  - deleting, 15
  - user login names vs., 5
- MAIL environment variable, 24, 25
- mailboxes (user), 15
- maintaining server and client support, 94, 95
- maintaining tape drives, 624
- make command, 12

- MANPATH environment variable, 25
- MANSECT environment variable, 25
- manual mounting, 169
  - automatic mounting compared to, 172
  - remote CDs, 180, 181
  - remote diskettes, 206, 207
- manual pages, 406
- mask, 28
- maximums
  - secondary groups users can belong to, 10
  - user ID number, 5
  - user login name length, 5
  - user password length, 8
- media was found message, 201
- Medium Density (DD) diskettes, 169
  - formatting options, 191, 193
- memory storage (virtual), 407, 482
- minimum free space, 524
- minimums
  - user login name length, 4
  - user password length, 8
- mkfile command, 487, 488
- mkfs command, 405, 418
- mnttab file, 411
- Modify option (Edit menu)
  - Admintool: Groups, 45
  - Admintool: Users, 14, 15
- modifying automatic boot checking, 500, 501
- modifying, , *see* changing\x0d,
- monitor (PROM), 157
- mount command, 303, 405
  - remote CDs, 180
  - remote diskettes, 207
- mount point, 410
- mount table, 411
- mountall command, 405
- mounting, 169
  - all files in vfstab file, 432
  - file systems, 410
  - file systems automatically, 413
  - LOFS file systems, 432
  - manual compared to automatic, 172
  - mount points
    - CDs, 180, 238, 240
    - diskettes, 238, 240
    - NFS file systems, 432, 437
    - PCMCIA memory cards, 229

- remote CDs, 180, 181
- remote diskettes, 206, 207
- s5fs file systems, 438
- UFS file systems, 432
- user home directories, 43
  - automounting, 10
  - remote, 41, 43
- using default options, 435, 438
- Volume Management, 169
- moving, 169
  - diskette information
    - from diskettes, 203
    - to diskettes, 204, 205
- MS-DOS, , *see* DOS\x0d,
- mt command, 624
- multiple versions of software packages, 253, 254
- multiuser state, , *see* run level 3,
- musical CDs, 184

## N

- name services, 247
  - groups and, 11, 12
  - user accounts and, 4, 12, 16
- NIS+, 247
- NAMEFS file system, 404
- names
  - group
    - described, 10
  - software package naming conventions, 250
  - SUNW prefix, 250
  - user login
    - changing, 14
    - described, 3, 4
- names/naming
  - CD names
    - designators, 176
    - finding a CD's name, 180
  - diskette names, 190
- ncheck command, 405
- nec option, 192, 198
- NEC-DOS, , *see* DOS\x0d,
- network-based file systems, 402
- networks, 247
- servers, 247
- newfs command, 196, 304, 418, 526
- newgrp command, 11, 19

- NFS, 27, 413
- NFS daemon, , *see* nfsd daemon\x0d,
- NFS file systems, 432
- NFS server, 413
- nfsd daemon
  - starting, 182, 209
  - verifying if running
    - making CDs available to other systems, 181, 182
    - making diskettes available to other systems, 208, 209

## NIS

- groups and, 12
- user accounts and, 4, 12, 16
- nis\* commands, 12
- NIS+
  - groups and, 11, 12
  - user accounts and, 4, 12, 16
- nistbladm command, 12
- no media was found message, 201
- noaccess group, 5, 19
- noask\_pkgadd administration file, 254, 259
- nobody group, 5, 19
- notifying users of system down time, 121
- NP password, 18

## O

- OPENWINHOME environment variable, 25
- /opt directory, 407
- /opt directory
  - software package installation in, 251, 264
- optimization type, 525
- options
  - for mkfile, 488
  - for ufsdump command, 582
  - for ufsrestore command, 586
- OS server
  - adding Solaris 7 OS services, 86
  - adding SunOS 4.0 and compatible OS services, 82
  - converting from standalone system, 80
  - description, 67
  - other (permissions setting), 28

## P

- packages, software, , *see* software
  - administration\x0d,
- parameters (file system), 522
- partition (swap), 407, 482
- passwd command, 12
- passwd file, 16
  - deleting user accounts and, 15
  - fields in, 16, 17
  - restoring from tape, 569
  - user ID number assignment and, 6
- passwords (group), 19
- passwords (user)
  - Admintool: Users and, 15
  - aging, 9, 15, 16
  - changing
    - Admintool: Users and, 15
    - commands for, 12
    - frequency of, 8, 18
    - by user, 8
  - choosing, 8
  - described, 4, 8, 9
  - disabling/locking user accounts and, 16, 18
  - encryption, 16
  - expiration, 18
  - NP password, 18
  - \*LK\* password, 16, 18
  - precautions, 8
  - setting, 8, 15
- patch
  - defined, 281
  - finding already installed, 282
  - installation README, 282
  - numbering scheme, 284
  - utilities, 282
- patchadd command, 282, 284
- patches
  - accessing via ftp, 284
  - accessing via world wide web, 283
  - availability for Sun Service customers, 283
  - general availability, 283
  - installing, 284
  - removing, 285
  - where to find, 283
- patchrm command, 282
- PATH environment variable
  - described, 25, 26
  - setting up, 26, 27
- path shell variable, 23, 25
- pathchrn command, 285
- pathnames, 173
- PC BIOS (and booting), 159
- PC file system, 401
- PC-DOS, , *see* DOS\x0d,
- PCMCIA memory cards
  - accessing on other systems, 229
  - copying or moving information from, 225
  - copying or moving information to, 226
  - default label, 215
  - displaying the contents of, 225
  - ejecting, 228
  - formatting for a UFS file system, 215
  - formatting for DOS, 220
  - identifying, 214
  - loading, 223
  - making available to other systems, 231
  - mounting, 230
- permissions, 28, 37
  - copying files from CDs, 178
- physical device name, 302
- /pkg directory, 260, 261
- pkgadd command
  - alternate base directory and, 254, 262
  - bypassing user interaction, 253, 254
  - diskless clients, 265, 267
  - overview, 248, 256
  - a option (administration file), 253, 254, 257, 259, 262, 268
  - d option (device name), 257 to 261, 265, 268
  - R option (root file system), 262, 265
  - s option (spool directory), 260, 261
  - prerequisites for using, 250
  - servers, 267
  - spool directories and, 260, 261
  - standalone systems a, 257, 265
  - standalone systems and, 259, 274
  - third-party packages and, 252
- pkgchk command
  - options, 270, 272
  - overview, 256, 270
  - using, 270, 272
- pkginfo command

- all packages installed, 271
- overview, 250, 256, 270
- l option (detailed information), 273
- R option (diskless and AutoClient systems), 271
- using, 260, 270
- pkginfo file, 251
- pkgmap file, 252, 264
- pkgparam command, 256, 264
- pkgrm command, 274
  - basic procedure, 274
  - caution, 253, 274
  - overview, 248, 256
  - R option (diskless and AutoClient systems), 275
  - s option (spooled packages), 274
  - prerequisites for using, 250
  - rm command vs., 253, 274
- playing musical CDs, 184
- preening file systems, 504
- preparing
  - for backups, 551
  - to restore files, 561
- primary groups, 10, 11, 247
- printers (default), 25
- /proc directory, 403, 407
- process file system, 403
- PROCFS file system, 403
- profile server, 69
- .profile file
  - customizing, 10, 20, 22, 30
- PROM
  - changing boot-from setting, 130
  - finding release level, 130
  - finding the ROM revision, 130
  - monitor, 157
  - switching to the ok prompt, 130
- prompt shell variable, 25
- prtconf command, 297
- prvtoc command, 304, 338
- PS1 environment variable, 25
- pseudo file systems, 402
- pseudo user logins, 6
- pseudo-ttys, 6

## Q

quitting, , *see* stopping\x0d,

## R

- raw disk device interface, 303
- rdiskette directories, 236
- /vol/dev/rdisk directory, 237, 238
- reboot command, 120
- reconfiguration boot, 345
  - SPARC example, 355
  - x86 example, 368
- record of
  - dumps, 578
  - incremental backup, 578
- recylinder group, 519
- regular inodes, 496
- release level of PROM, 130
- remote access
  - CDs
    - accessing CDs on other systems, 179, 181
    - making CDs available to other systems, 181
  - diskettes
    - accessing diskettes on other systems, 206, 207
    - making diskettes available to other systems, 208
- remote drive (restoring from), 569
- remote mounting, 41, 43
- remote package server
  - software installation from, 258, 259
  - software installation to spool directory, 261
- removable media, , *see* CDs,
- rmovf command, 253
- removing swap file from use, 489
- removing, , *see* deleting,
- repairing the /etc/passwd file
  - SPARC, 139
  - x86, 153
- reset button, 154
- reset command, 132
- resetting a SPARC system, 132
- restore
  - complete file system, 570
  - from remote drive, 569
  - interactively, 565
  - preparing to, 561
  - specific files, 567

- type of tape drive, 562
- restore command, , *see* command,
- restoring bad superblock, 505
- restoring file systems
  - complete, 570, 572
  - root and /usr, 573, 575
- retensioning magnetic tape cartridge, 623
- retrieving
  - files created with bar command, 616
  - files from a tape (cpio), 607
  - files from a tape (tar), 603
  - files from diskette (tar), 614
  - files from remote tape (tar and dd), 610
  - specific files from tape (cpio), 608
- rewinding magnetic tape cartridge, 624
- rm command, 253, 274
- rmmount.conf file
  - playing musical CDs, 184
  - sharing CDs, 183
  - sharing diskettes, 209, 210
- Rock Ridge extension (HSFS file system), 401
- root (/) file system, 406
  - software package installation in, 251, 262
  - software package removal from, 275
- root group, 5
- rotational delay, 524
- run control scripts, 112
  - adding, 114
  - disabling, 115
  - starting and stopping services, 113
- run level
  - 0 (power-down state), 108
  - 1 (single-user state), 108
  - 2 (multiuser state), 108
  - 3 (multiuser with NFS), 108
    - booting to, 134, 147
    - processes executed at, 111
    - what happens when system is brought to, 111
  - 6 (reboot state), 108
  - default run level, 107
  - defined, 107
  - determining, 108
  - s or S (single-user state), 108
    - booting to, 135, 148

## S

- /sbin/rc0 script, 116, 117
- /sbin/rc1 script, 117, 124
- /sbin/rc2 script, 117, 124
- /sbin/rc3 script, 118, 124
- /sbin/rc5 script, 118, 124
- /sbin/rc6 script, 118, 124
- /sbin/rcS script, 118, 124
- scheduling backups, 540
- SCSI disk drives, 344
- SCSI tape drives, 621
- secondary disk
  - connecting to the system
    - SPARC, 356
    - x86, 369
  - described, 317
- secondary groups, 10, 11, 19, 247
- security, 247
  - user ID number reuse and, 6
- permissions, 247
- servers
  - boot server, 69
  - description, 62
  - install server, 69
  - OS server, 67
  - profile server, 69
  - software administration
    - adding packages, 267, 270
    - heterogeneous environments, 252, 263, 264, 267
    - homogeneous environments, 261
    - removing packages, 274
    - sharing software with clients, 250, 275
    - Sun packages, 251
    - third-party packages, 252
  - support for, 95
    - maintaining, 95
- set command, 23
- setenv command, 23, 24
- shadow file
  - described, 16
  - fields in, 17, 18
- share command, 413
  - making disks available to other systems
    - CDs, 182, 183
    - diskettes, 209, 210
- shareall command, 413

- sharing
  - files, 413
  - software by clients and servers, 250, 275
  - user home directories, 41, 43
- sharing CD-ROM drives, 181
- SHELL environment variable, 26
- shell variables, 24, 26
- shells
  - basic features, 22, 23
  - environment of, 23, 26
  - environment variables and, 23, 28
  - local variables, 24, 26
  - local)variables, 23
  - user initialization files and, 20 to 22, 30, 37
- showing, , *see* displaying\x0d,
- shutdown command
  - described, 120
  - notifying users, 121
  - shutting down a server, 101, 122
- shutting down
  - a server, 122
  - a standalone system, 125
  - a system cleanly with shutdown and init commands, 120
- shutting down a system, 101
- single-user state, , *see* run level s or S,
- site initialization files, 21
- size
  - checking file system, 495
  - diskette formats, 191, 193
    - DOS diskettes, 198
    - UFS diskettes, 193, 194
  - fragment, 523
  - inode, 498
- /skel directory, 20
- skeleton directories, 10, 15
- slice (defined), 312
- software administration, 247
  - adding packages, 247, 248, 252, 254, 256
    - administration files and, 253, 254, 257
    - base directory and, 253, 254
    - bypassing user interaction when, 253, 254
    - diskless clients, 251, 252, 261, 265, 267
    - guidelines for, 250, 252
    - heterogeneous environments, 252, 263
    - homogeneous environments, 261
    - multiple versions of a package, 253, 254
    - prerequisites, 250
    - servers, 267
    - from mounted CD, 258
    - from remote package server, 258, 259
    - to a spool directory, 260, 261, 272
    - standalone systems, 257, 259, 265
    - Sun packages, 251, 258 to 262
    - third-party packages, 252, 263
    - tools for, 248, 249
  - clients, 250, 252
    - heterogeneous environments, 252, 263
    - homogeneous environments, 261
    - sharing software with servers, 250, 275
    - Solstice AutoClient systems, 251
    - Sun packages, 251, 262
    - third-party packages, 252, 263
  - defined, 248
  - displaying installed software
    - information, 250 to 252, 256, 264, 270, 273
  - naming conventions for packages, 250
  - overview, 247, 252
  - package defined, 248
  - removing packages, 248, 250, 253, 274
    - administration files and, 254
    - diskless clients, 275
    - guidelines for, 253
    - spool directories, 274
    - standalone systems, 274
    - tools for, 248, 249

- servers
  - adding packages, 267
  - heterogeneous environments, 252, 263, 267
  - homogeneous environments, 261
  - removing packages, 274
  - sharing software with clients, 250, 275
  - Sun packages, 251
  - third-party packages, 252
- Solaris upgrade option and, 253
- tools for, 247 to 249
  - commands, 248, 256
- verifying installation
  - pkgchk command, 256, 270, 272
  - pkginfo command, 256, 260, 273
- software administration, removing
  - packages, 247
- software administration, *see* Admintool, software administration and \x0d
- tools for
  - Admintool,,
- software administration, *see* diskless clients \x0d
- clients
  - diskless clients,,
- Software Manager, 247, 249
- software packages, , *see* software administration \x0d,
- Solaris diskette formats, 191, 193
- Solaris fdisk partition, 366
- Solaris upgrade option, 253
- Solaris User Registration, *see* User Registration,
- Solstice AdminSuite, 11
- Solstice AutoClient systems, 251
- sort command, 12
- sorting user accounts, 12
- space optimization type, 525
- spaces (in user login names), 5
- SPARC systems
  - diskette formats, 191, 193
  - UFS format, 177, 241
- SPECFS file system, 404
- specifying a disk slice, 304, 306
- spool directories
  - installing software packages to, 260, 261, 272
  - removing software packages from, 274
- staff group, 11
- standalone system, 62
- standalone systems
  - adding software packages to, 257, 259, 265
  - converting to OS server, 80
  - removing software packages from, 274
- start command, 186
- starting, 169
  - nfsd daemon, 182, 209
  - Volume Management, 186
- starting and stopping services, 113
- mounting, 169
- state flag
  - fsck, 492
  - UFS file systems, 408
- status messages, , *see* messages \x0d,
- stop command, 186
- Stop-A keys, 140, 142
- stopping, 169
  - all processes for a file system, 440
  - ejecting CDs
    - using command line, 179
  - killing processes accessing CDs, 178, 179
  - killing processes accessing diskettes, 205
  - Volume Management, 186
- storage (virtual memory), 407
- storage block, 521
- storage capacities (media), 535, 539, 619
- storage, virtual memory, 482
- structure of cylinder groups, 519
- stty command, 27
- Sun software packages
  - displaying installation location, 264
  - installing, 251, 258 to 262
- SunOS default file system, 406
- SUNW prefix, 250
- SUNW\_PKGTYPE parameter, 251, 252, 264
- superblock, 495, 505, 519
- support for servers and clients
  - description, 60
  - setting defaults for, 77
- swap command, 487
- swap file
  - adding to vfstab, 485
  - creating, 487
  - displaying, 486

- removing from use, 489
- swap partition, 407, 482
- swapadd command, 485
- SWAPFS file system, 404
- swmtool command, 247, 249
- symbolic links, 496
  - file system access, 240
  - listing CD directories using, 177
  - listing diskette directories using, 202
  - raw device access, 240
- sync command, 141, 142
- synchronize the disk using sync
  - command, 141, 142
- syntax
  - fsck command, 507, 509
  - newfs, 526
- sysdef command, 297
- system accounts, 5
- system architecture, 24
- system disk
  - connecting
    - SPARC, 354
    - x86, 367
  - described, 317
  - installing a boot block on
    - SPARC, 362
    - x86, 380
- system initialization files, 10
- system shutdown commands, 120
- system types
  - converting, 67
  - generic, 66
  - guidelines for choosing, 63
  - overview, 61
  - server, 62
  - standalone system, 62
  - updating, 76

## T

- table
  - default SunOS file system, 406
  - file system administrative commands, 404
  - interactive commands for ufsrestore, 589, 590
  - media storage capacities, 535, 539, 619
  - mount, 411
  - options for mkfile, 488

- options for ufsdump command, 583, 584
- options for ufsrestore command, 586
- tape capacity, 581
- tape, 624
  - capacity, 581
  - characteristics, 581
  - copying all files in a directory (cpio), 605
  - listing files using tar command, 602
  - retrieving files from (cpio), 607
  - retrieving files from (tar), 603
  - retrieving specific files from (cpio), 608
  - sizes, 535, 539, 619
  - storage capacities, 535, 539, 619
- tape (magnetic cartridge)
  - retensioning, 623
- tape devices (naming), 307
- tape drive
  - default densities, 621
  - determining type for restore, 562
  - finding type, 622
  - maintaining, 624
  - maximum SCSI, 621
  - restoring from remote, 569
- tar command, 601, 604
  - copying files to a single diskette, 612
  - copying files to remote tape (dd), 609
  - copying files to tape, 601
  - listing files on diskette, 613
  - listing files on tape, 602
  - retrieving files from diskette, 614
  - retrieving files from remote tape (dd), 610
  - retrieving files from tape, 603
- temporary file system, 402, 420
- TERM environment variable, 26
- term shell variable, 23, 26
- terminating all processes, 440
- TERMINFO environment variable, 26
- testing, , *see* verifying,
- third-party software packages
  - displaying installation location, 264
  - installing on clients, 252, 263
  - installing on servers, 252
- time (optimization type), 525
- time zone environment variable, 26
- /tmp directory, 402, 407
- TMPFS file system, 402
- ttys (pseudo), 6



- ttytype pseudo user logins, 6
- turn off power to all devices, how to, 127
- type of file systems, 401
- type of inodes, 496
- type of tape drive, 622
- TZ environment variable, 26

## U

- UFS CDs
  - mixed formats, 242, 243
  - SPARC vs. x86 formats, 177, 241
- UFS diskettes, 169
  - adding UFS file system, 196, 197
  - formatting, 193, 195
    - canceling, 194
    - complete format, 191
    - size and density options, 191, 193
  - SPARC vs. x86 formats, 191
- UFS file system, 401, 407
  - adding to diskettes, 196, 197
  - extended fundamental types, 408
  - large file systems, 408
  - mounting, 432
  - placing on a PCMCIA Memory Card, 218
  - state flags, 407
- ufsdump command, 553
  - backing up file systems to tape, 554
  - end-of-media detection, 578
  - how data is copied with, 578
  - how it works, 577
  - limitations, 581
  - options and arguments, 582
- ufsrestore command, 561, 575, 585
  - preparing to use, 561
  - restoring complete file systems from tape, 570
- UIDs, 14
  - assigning, 6
  - definition, 5
  - large, 6
- umask command, 28
- umount command, 405
- umountall command, 405
- unallocated directory blocks, 499
- unallocated inodes, 496
- underscore (`_`), in user login names, 5

- UNIX file system, 401
- UNIX groups, 10, 247
- unmounting file systems, 410, 441, 442
- unsupported devices, 292, 293
- updating system types, 76
- upgrade option (Solaris), 253
- user access, 4
- user accounts, 3
  - adding
    - Admintool: Users, 39, 40
    - commands, 12
  - changing
    - Admintool: :Users, 14
    - Admintool: Users, 15
    - commands, 12
  - commands for, 12
  - copying
    - commands, 12
  - default setup
    - commands, 12
  - deleting
    - Admintool: Users, 15
    - commands, 12
  - described, 3
  - disabling/locking
    - Admintool: Users, 16
    - commands, 12
    - passwords and, 16, 18
  - finding (commands), 12
  - guidelines for, 4, 10
  - ID numbers, 5, 6, 14
  - login names, 3, 4, 14
  - name services and, 4, 12, 16
  - setting up
    - information sheet, 35
  - sorting (commands), 12
  - storage of information for, 4, 16, 19
  - tools for managing, 12
- user accounts, *see* groups\x0d groups and,,
- user accounts, *see* passwords (user)\x0d passwords,,
- user accounts, *see* user home directories\x0d home directories and,,
- user accounts, *see* user initialization files\x0d initialization files and,,
- user home directories

- changing ownership of, 14
- customized initialization files in, 10, 15
- deleting, 15
- described, 4, 9
- mounting, 43
  - automounting, 10
  - remote, 41, 43
- nonlocal reference to (\$HOME), 9, 21
- sharing, 41, 43
- size, 9
- user ID numbers, 5, 6, 14
- user initialization files
  - customizing, 20, 30
    - adding customized files, 15
    - avoiding local system references, 21
    - environment variables, 23, 28
    - overview, 10, 20, 21
    - procedure for, 36
    - shell variables, 24, 26
    - site initialization files, 21
    - user mask setting, 28
  - default, 20
  - described, 4, 10, 20
  - examples, 29
  - shells and, 20 to 22, 30
- user login names
  - changing, 14
  - described, 3, 4
- user logins (pseudo), 6
- user mailboxes, 15
- User Manager, Solstice AdminSuite, 11
- user mask, 28
- user passwords, , *see* passwords (user)\x0d,
- User Registration
  - problems, 53
- User Registration
  - described, 52
  - disabling, 55
  - solregis command, 52
- user shell variable, 23
- user work environment, , *see* user
  - initialization files\x0d,
- useradd command, 12
- userdel command, 12
- usermod command, 12
- /usr file system, 406
- /usr file system
  - dataless clients and, 251, 263, 265, 268, 270

- /usr/openwin/bin/ab\_admin command, , *see*
  - ab\_admin command,
- uucp group, 6

## V

- /var directory, 407
- /var/sadm/install/admin directory, 253
- /var/sadm/patch, 284
- /var/spool/pkg directory, 259 to 261
- variables, 247
  - environment, 23, 28
  - shell (local), 23, 26
- verifying
  - CD is in use, 178, 179
  - diskette is in use, 205
  - nfsd daemon is running
    - making CDs available to other
      - systems, 181, 182
    - making diskettes available to other
      - systems, 208, 209
  - software package installation
    - pkgchk command, 256, 270, 272
    - pkginfo command, 256, 260, 274
- vfstab file, 415, 485
  - adding swap to, 485
  - creating entries in, 431
  - default, 412
  - entry for temporary file system, 423
  - finding file system names in, 552
  - modifying fsck pass, 500
  - mounting all files, 432
- viewing, , *see* displaying\x0d,
- vipw command, 12
- virtual file system table, 412
- virtual memory storage, 407, 482
- /vol/dev directory, 235, 236
- /vol/dev directory
  - symbolic links
    - file system access, 240
  - CD subdirectories, 235, 237, 238, 240
- volcopy command, 405
- Volume Management, 169, 235, 243
  - access to removable media, 235
  - benefits, 172

- CDs
  - access locations, 173, 235, 241
  - directories, 235, 237, 238
  - /cdrom mount point, 238, 240
- configuring, 186
- diskettes
  - access locations, 173, 235, 237, 238
  - directories, 236
  - loading, 200, 202
  - /floppy mount point, 238, 240
- manual mounting compared to, 172
- restarting, 186
- stopping, 186
- symbolic links
  - file system access, 240
  - raw device access, 240
- UFS limitations, 241

## W

“WARNING: ” message, 266

- when to turn off power to devices, 121
- who command, 108, 121
- who pseudo user logins, 6
- work environment, , *see* initialization
  - files\x0d,
- world (permissions), 28
- write permissions
  - described, 178
- write-protection (PCMCIA memory cards), 216

## X

- x86 systems
  - diskette formats, 191, 193
  - UFS format, 177, 241

## Y

- yp\* commands, 12